

**Program Directory for
Advanced Communication Function (ACF)
System Support Programs (SSP)**

Version 4 Release 7, **Service Level SMC9908**

Program Number 5654-009

for Use with
VM/ESA

Document Date: April 1999

GI10-0990-01

Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page vi.

This program directory, dated April 1999, applies to System Support Programs V4R7 for VM (SSP V4R7 VM), Service Level SMC9908, Program Number 5654-009 for the following:

COMP ID	Rel	Feature Numbers	System Names
565400900	470	5801, 5802, 5700	VM/ESA

and to all subsequent releases and modifications until otherwise indicated in new editions.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

Copyright International Business Machines Corporation 1984, 1998. All rights reserved.

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

Notices	vi
Notice to Users of Online Versions of This Book	vii
Trademarks	vii
1.0 Introduction	1
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.1.1 SSP Base Product	3
2.2 Optional Machine-Readable Material	4
2.3 Program Publications	4
2.3.1 Basic Program Publications	4
2.3.2 Optional Program Publications	5
2.3.3 Softcopy Publications	5
2.3.4 Publications Associated with SSP V4R7 VM	5
2.4 Microfiche Support	6
2.5 Publications Useful During Installation	6
3.0 Program Support	8
3.1 Preventive Service Planning	8
3.2 Statement of Support Procedures	8
4.0 Program and Service Level Information	9
4.1 Program Level Information	9
4.2 Service Level Information	9
4.3 Cumulative Service Tape	9
5.0 Installation Requirements and Considerations	10
5.1 Hardware Requirements	10
5.2 Program Considerations	10
5.2.1 Operating System Requirements	10
5.2.2 Other Program Product Requirements	10
5.2.2.1 Programming Requirements	10
5.2.3 Machine Requirements	10
5.2.3.1 Minimum Requisites	11
5.2.3.2 Functional Requisites	11
5.2.3.3 Compatibility Requisites	11
5.2.3.4 NCP	11
5.2.3.4.1 NPSI	14
5.2.3.4.2 DFSMS	15
5.3 Program Installation and Service Considerations	15
5.4 DASD Storage and User ID Requirements	15

6.0 Installation Instructions	17
6.1 VMSES/E Installation Process Overview	17
6.2 Plan Your Installation For SSP V4R7 VM	18
6.3 Allocate Resources for Installing SSP V4R7 VM	20
6.3.1 Installing SSP V4R7 VM on Minidisk	21
6.3.2 Installing SSP V4R7 VM in SFS Directories	21
6.4 Install SSP V4R7 VM	23
6.4.1 Update Build Status Table for SSP V4R7 VM	26
6.5 Place SSP V4R7 VM Into Production	26
6.5.1 Copy SSP V4R7 VM Files Into Production	26
7.0 Service Instructions	28
7.1 VMSES/E Service Process Overview	28
7.2 Servicing SSP V4R7 VM	29
7.2.1 Prepare to Receive Service	29
7.2.2 Receive the Service	31
7.2.3 Apply the Service	31
7.2.4 Update the Build Status Table	33
7.2.5 Build Serviced Objects	35
7.3 Place the New SSP V4R7 VM Service Into Production	35
7.3.1 Copy the New SSP V4R7 VM Serviced Files Into Production	35
Appendix A. APARs Incorporated into this Program	37
A.1 PTFs and APARs Incorporated into This Service Level	37
Reader's Comments	39

Figures

1. High Level Assembler Integrated with Operating System	2
2. Basic Material: Program Tape	3
3. Program Tape: File Content	4
4. Basic Material: Program Publications	4
5. Optional Material: Licensed Publications	5
6. Softcopy Publications	5
7. Publications Associated with SSP V4R7 VM	6
8. Publications Useful During Installation / Service on VM/ESA Version 2.2.0	6
9. Publications Useful During Installation / Service on VM/ESA Version 2.3.0	6
10. PSP Upgrade and Subset ID	8
11. Component IDs	8
12. NCP APARs Required to Generate NCP with SSP NDF	12
13. NCP APAR Required to Code RNRLIMIT	12

14.	NCP APARs Required to Code BAN Connections	12
15.	NCP APAR required to Code a Default TCP/IP Route in NCP V7R1	12
16.	NCP APARs Required to Increase the Inter-Frame Gap	12
17.	NCP APARs Required to Initiate Deactivation of an Out-of-Sequence Virtual Route (VR)	13
18.	NCP APAR Required to Use a Duplicate TIC Configuration for Subarea Connections	13
19.	NCP APAR Required to Generate Backup Channel Connections for NCP-NCPROUTE IP Interface	13
20.	NCP APAR Required to Generate INN Connections	13
21.	NCP APAR Required to Code MAXDLCI for D-Channel	13
22.	NCP APARs Required If You Code USGTIER=1, 2, 2.5, or 3	14
23.	NCP APAR Required to Include QSZALERT Function in NCP V7R5.	14
24.	NCP APARs Required for Committed Information Rate (CIR)	14
25.	NCP APAR Required for Transmission Head Buffers	14
26.	NPSI APARs Required to Generate NPSI V3R8 with NCP V7R4, NCP V7R5, or NCP V7R6	15
27.	APARs Required to Use the High Level Assembler	15
28.	DASD Storage Requirements for Target Minidisks	16
29.	SSP V4R7 PTFs and Corresponding APARs for Service Level 9908	37

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make them available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, are the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

International Business Machines Corporation
IBM Director of Licensing
500 Columbus Avenue
Thornwood, NY 10594
USA

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Site Counsel
IBM Corporation
P.O. Box 12195
3039 Cornwallis
Research Triangle Park, NC 27709 2195
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement.

This document is not intended for production use and is furnished as is without any warranty of any kind, and all warranties are hereby disclaimed including the warranties of merchantability and fitness for a particular purpose.

Notice to Users of Online Versions of This Book

For online versions of this book, you are authorized to:

Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.

Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine-readable documentation.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

BookManager	NTuneMON
DFSMS	OS/2
DFSMS/MVS	OS/390
FunctionPac	RETAIN
IBM	SystemPac
IBMLink	VM/ESA
MVS/ESA	VTAM
NetView	

Microsoft, Windows, and the Windows95 logo are trademarks of Microsoft Corp.

Other company, product, and service names may be trademarks or service marks of others.

1.0 Introduction

This program directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of SSP V4R7 VM. You should read all of this program directory before installing the program and then keep it for future reference.

The program directory contains the following sections:

Section 2.0, "Program Materials" on page 3 identifies the basic and optional program materials and documentation for SSP V4R7 VM.

Section 3.0, "Program Support" on page 8 describes the IBM support available for SSP V4R7 VM.

Section 4.0, "Program and Service Level Information" on page 9 lists the program and service level information incorporated into SSP V4R7 VM.

Section 5.0, "Installation Requirements and Considerations" on page 10 identifies the resources and considerations for installing and using SSP V4R7 VM.

Section 6.0, "Installation Instructions" on page 17 provides detailed installation instructions for SSP V4R7 VM.

Section 7.0, "Service Instructions" on page 28 provides detailed servicing instructions for SSP V4R7 VM.

Appendix A, "APARs Incorporated into this Program" on page 37 lists the APARs incorporated into SSP V4R7 VM.

This program directory is for SSP V4R7 VM Service Level 9908. See Appendix A, "APARs Incorporated into this Program" on page 37 for a list of APARs.

Throughout this program directory, SSP V4R7 VM Service Level 9908 is referred to as SSP V4R7 VM. SSP V4R7 VM has been updated to a new service level and assigned a new SOURCEID, SMC9908.

When installing this service level of SSP V4R7 for VM, you should also consider installing the same service level of NCP for VM, NCP V7R7 for VM, Service Level 9906.

Before installing SSP V4R7 VM, read section 3.1, "Preventive Service Planning" on page 8. This section tells you how to find any updates to the information and procedures in this program directory.

This release builds the ASM3705 assembler. A link to the CMSTOOLS (193) disk is added.

Starting with ACF/NCP V7R7, important changes have been made to the NCP generation assembler support. Beginning with ACF/SSP V4R7, the Network Definition Facility (NDF) will offer exclusive support for the High Level Assembler (HLAS) program product, 5696-234. Prior to ACF/SSP V4R7, two different assemblers were shipped with ACF/SSP. Support for the IFZ assembler (VSE) and IHR90 assembler (MVS and VM) will be discontinued on the ACF/NCP V7R7 platform. You will now be required to use the High Level Assembler for generating NCP V7R7 load modules.

If the High Level Assembler does not come installed on your system, you will need to order it.

Figure 1 shows the operating systems and indicates whether the High Level Assembler is integrated.

Figure 1. High Level Assembler Integrated with Operating System

Operating System	High Level Assembler V1R2
MVS/ESA V5R1 or later	Order separately
VSE/ESA V1R4.3 or V1R4.4	Order separately
VM/ESA V2R2 or V2R3	Order separately
OS/390 R1, R2, or R3	Integrated
OS/390 R4 or R5	Integrated
VSE/ESA V2R2 and V2R3	Integrated

In addition to the High Level Assembler requirements, the APARs listed in Figure 27 on page 15 are required.

The IFZ and IHR90 assemblers will still be shipped with ACF/SSP V4R7 for use with levels of ACF/NCP prior to NCP V7R7.

A good place to start any task regarding this program is *NCP V7R7, SSP V4R7, and EP R14 Library Directory*, SC30-3971. This directory introduces the enhancements for the current release and shows where these enhancements are described in the NCP library. It gives you an overview of NCP, SSP, and EP and directs you to a variety of tasks related to these programs.

At the end of this program directory you will find a Reader's Comment Form. Please take time to complete this form and return it to the address shown on the form. Your comments and suggestions help improve this program directory and make installation easier.

2.0 Program Materials

An IBM program is identified by a program number and a feature number. The program number for SSP V4R7 VM is 5654-009. Feature numbers associated with this release are provided in the following sections.

The program announcement material describes the features supported by SSP V4R7 VM. Ask your IBM marketing representative for this information if you have not already received a copy.

The following sections identify:

- Basic and optional program materials available with this program
- Basic, optional, and associated publications available for this program
- Publications useful during installation

2.1 Basic Machine-Readable Material

This section describes the basic machine-readable material for SSP V4R7 VM.

The distribution medium for this program is a 9-track magnetic tape (written at 6250 bpi), a 3480 tape cartridge, or a 4 mm cartridge. The tape or cartridge contains all programs and data needed for installation. SSP V4R7 VM is installed using VMSES/E. See 6.0, "Installation Instructions" on page 17 for more information about how to install the program.

2.1.1 SSP Base Product

Figure 2 describes the program tape or cartridge for the SSP V4R7 VM program. Figure 3 on page 4 describes the file content of the program tape or cartridge for the SSP V4R7 VM program.

Figure 2. Basic Material: Program Tape

Medium	Feature Number	Physical Volume	Tape Content	External Tape Label
6250 tape	5801	1	SSP V4R7 VM R	SSP V4R7 VM
3480 cart.	5802	1	SSP V4R7 VM R	SSP V4R7 VM
4 mm cart.	5700	1	SSP V4R7 VM R	SSP V4R7 VM

Figure 3. Program Tape: File Content

Tape File	Content
1	Tape Header
2	Tape Header
3	Product Header
4	Product Memo
5	Service Apply Lists
6	PTFPARTs
7	SSP V4R7 VM Service
8	SSP V4R7 VM Service
9	SSP V4R7 VM Base Code
10	SSP V4R7 VM Executable Code

2.2 Optional Machine-Readable Material

There are no optional machine-readable materials for SSP V4R7 VM.

2.3 Program Publications

The following sections identify the basic, optional, and associated publications for SSP V4R7 VM.

2.3.1 Basic Program Publications

Figure 4 identifies the basic and licensed program publications for SSP V4R7 VM. One copy of each of these publications is included when you order the basic materials. For additional copies, contact your IBM representative. A fee is charged for additional copies.

Figure 4 (Page 1 of 2). Basic Material: Program Publications

Publication Title	Form Number
Network Control Program, System Support Programs, and Emulation Program Generation and Loading Guide	SC31-6221
Network Control Program, System Support Programs, and Emulation Program Messages and Codes	SC31-6222
Licensed Program Specifications: System Support Programs Version 4 Release 7 for VM	GC31-6227
Network Control Program Version 7 Release 7, System Support Programs Version 4 Release 7, and Emulation Program Release 14 Library Directory	SC30-3971

Figure 4 (Page 2 of 2). Basic Material: Program Publications

Publication Title	Form Number
Network Control Program, System Support Programs, and Emulation Program Diagnosis Guide	LY43-0033#
Network Control Program, System Support Programs, and Emulation Program Trace Analysis Handbook	LY43-0037#

Note: A pound symbol (#) next to the form number indicates that it contains “Restricted Materials of IBM.”

2.3.2 Optional Program Publications

Figure 5 identifies the optional licensed program publications for SSP V4R7 VM. The first copy is available at no charge to licensees of the basic material by ordering the 7xxx feature number. Order additional copies using the 8xxx feature number. A fee is charged for additional copies.

Figure 5. Optional Material: Licensed Publications

Publication Title	Form Number	Feature Number First Copy	Feature Number Additional Copy
Network Control Program and System Support Programs Customization Guide	LY43-0031#	7011	8011
Network Control Program and System Support Programs Customization Reference	LY43-0032#	7012	8012

Note: A pound symbol (#) next to the form number indicates that it contains “Restricted Materials of IBM.”

2.3.3 Softcopy Publications

All SSP V4R7 VM manuals, licensed and unlicensed, except for *SSP Licensed Program Specifications*, are offered in displayable softcopy form on the media listed in Figure 6.

Figure 6. Softcopy Publications

Title	Form Number	Feature Number First Copy	Feature Number Additional Copy
ACF/NCP, ACF/SSP, EP, NPSI, and NTuneMON Softcopy Collection Kit	LK2T-0414#	7110	8110

Note:

Order this collection kit under the NCP product. (It is not orderable under SSP.) A pound symbol (#) beside the Form Number indicates that it contains “Restricted Materials of IBM.”

2.3.4 Publications Associated with SSP V4R7 VM

Figure 7 on page 5 identifies publications that may be helpful when you use SSP V4R7 VM. To order copies, contact your IBM representative. A fee is charged for each copy of these publications.

Figure 7. Publications Associated with SSP V4R7 VM

Publication Title	Order/Form Number
Network Control Program Version 7 Release 7 Migration Guide	SC30-3889
Network Control Program, System Support Programs, and Emulation Program Resource Definition Guide	SC31-6223
Network Control Program, System Support Programs, and Emulation Program Resource Definition Reference	SC31-6224
Planning for NetView, NCP, and VTAM	SC31-8063
Planning for Integrated Networks	SC31-8062

2.4 Microfiche Support

Microfiche program listings are not provided with SSP V4R7 VM. Customers with access to View Program Listings (VPL), such as through SoftwareXcel Extended, can access program listings formerly provided through microfiche.

Those customers without access to VPL can contact their IBM representative.

The VPL facility provides online viewing of program listings that are available to customers.

2.5 Publications Useful During Installation

The publications listed in Figure 8 or Figure 9, depending on your VM/ESA release, may be useful during the installation of SSP V4R7 VM. To order copies, contact your IBM representative.

Figure 8. Publications Useful During Installation / Service on VM/ESA Version 2.2.0

Publication Title	Form Number
VM/ESA: VMSES/E Introduction and Reference	SC24-5747
VM/ESA: Service Guide	SC24-5749
VM/ESA: Planning and Administration	SC24-5750
VM/ESA: CMS Command Reference	SC24-5776
VM/ESA: CMS File Pool Planning, Administration, and Operation	SC24-5751
VM/ESA: System Messages and Codes	SC24-5784

Figure 9 (Page 1 of 2). Publications Useful During Installation / Service on VM/ESA Version 2.3.0

Publication Title	Form Number
VM/ESA: VMSES/E Introduction and Reference	GC24-5837
VM/ESA: Service Guide	GC24-5838

Figure 9 (Page 2 of 2). Publications Useful During Installation / Service on VM/ESA Version 2.3.0

Publication Title	Form Number
<i>VM/ESA: Planning and Administration</i>	SC24-5750
<i>VM/ESA: CMS Command Reference</i>	SC24-5776
<i>VM/ESA: CMS File Pool Planning, Administration, and Operation</i>	SC24-5751
<i>VM/ESA: System Messages and Codes</i>	GC24-5841

3.0 Program Support

This section describes the IBM support available for SSP V4R7 VM.

3.1 Preventive Service Planning

Before installing SSP V4R7 VM, check with your IBM Support Center or use IBMLink (Service Link) to determine if there is additional Preventive Service Planning (PSP) information. To obtain this information, specify the following UPGRADE and SUBSET values:

Figure 10. PSP Upgrade and Subset ID

Retain			
COMPID	Release	Upgrade	Subset
565400900	470	SSP470	470/9908

3.2 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 11 identifies the component ID (COMPID), RETAIN Release, and Field Engineering Service Number (FESN) for SSP V4R7 VM.

Figure 11. Component IDs

Retain			
COMPID	Release	Component Name	FESN
565400900	470	SSP V4R7 VM R	0466643

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of SSP V4R7 VM. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs shipped with this program. Information about the cumulative service tape is also provided.

4.1 Program Level Information

The program level refers to the APAR fixes incorporated into SSP V4R7 VM.

See Appendix A, "APARs Incorporated into this Program" on page 37, for a complete listing of the APARs incorporated into this program.

4.2 Service Level Information

The service level refers to the PTFs integrated into the program. See A.1, "PTFs and APARs Incorporated into This Service Level" on page 37 for a list of PTFs that are incorporated into this service level and their corresponding APARs.

Check the SSP470 PSP bucket for any additional PTFs that should be installed or any additional install information.

4.3 Cumulative Service Tape

Cumulative service for SSP V4R7 VM is available through a monthly corrective service tape, Expanded Service Option (ESO).

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing SSP V4R7 VM.

5.1 Hardware Requirements

There are no special hardware requirements for SSP V4R7 VM.

5.2 Program Considerations

The following sections list the programming considerations for installing SSP V4R7 VM.

5.2.1 Operating System Requirements

SSP V4R7 VM supports the following VM operating systems for as long as program services are available for the particular version and release.

VM/ESA V2R2, or later

VMSES/E on VM/ESA 2.2. Prior to installing SSP V4R7 VM, **RSU9403 service level** or later must be applied.

High Level Assembler 1.2 (5696-234)

5.2.2 Other Program Product Requirements

5.2.2.1 Programming Requirements

A platform-dependent BookManager product is required to display softcopy publications on CD-ROM. Limited function DOS, Windows, and OS/2 versions of these products are available on your CD-ROM. For more information or to order full-function releases of these products, or VM or MVS versions, refer to the IBM BookManager home page at <http://booksrv2.raleigh.ibm.com>.

5.2.3 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.3.1 Minimum Requisites

A minimum requisite is defined as one of the following:

Installation Requisite: A product that is required at installation time. i.e. this product **will not install** successfully unless this requisite is met.

Run Time Requisite: A product that is **not** required for the successful installation of this product, but **is** needed at run time in order for this product to work.

VM/ESA APAR VM61534 is required to use the High Level Assembler.

SSP V4R7 VM supports the following licensed VM programs at the function level of the version and release for as long as program services are available for the particular version and release.

NCP V7R3 or later

NCP V5R4

NCP V4R3.1

5.2.3.2 Functional Requisites

The IFWNET CLIST requires NetView V1R3, or later, with REXX support.

SSP V4R7 VM supports the following licensed VM programs at the function level of the version and release for as long as program services are available for the particular version and release.

Emulation Program R14

Emulation Program R12

Emulation Program R11

Emulation Program R9

Emulation Program R8

Emulation Program R6.1

5.2.3.3 Compatibility Requisites

The following sections describe cross product service considerations for NCP, NPSI, and DFSMS.

5.2.3.4 NCP

The NCP APARs listed in Figure 12 are required to generate NCP with SSP NDF.

Figure 12. NCP APARs Required to Generate NCP with SSP NDF

Product Name	APAR
NCP V4R3.1	IR82746
	IR83237
	IR83303
	IR83307
	IR83826
	IR83952
	IR86790
	IR89297

The NCP APAR listed in Figure 13 is required if you want to code RNRLIMIT on a NTRI logical GROUP definition statement in NCP V5R4.

Figure 13. NCP APAR Required to Code RNRLIMIT

Product Name	APAR
NCP V5R4	IR99583

The NCP APARs listed in Figure 14 are required if your generation definition contains frame-relay boundary access node (BAN) connections.

Figure 14. NCP APARs Required to Code BAN Connections

Product Name	APAR
NCP V7R1	IR28397
NCP V7R2	IR28239

The NCP APAR listed in Figure 15 is required to code a default TCP/IP route in NCP V7R1.

Figure 15. NCP APAR required to Code a Default TCP/IP Route in NCP V7R1

Product Name	APAR
NCP V7R1	IR26000

The NCP APARs listed in Figure 16 are required if you use the ADDIFG keyword to increase the inter-frame gap for IBM 3746 Model 900 frame relay, SDLC, or X.25 physical lines.

Figure 16. NCP APARs Required to Increase the Inter-Frame Gap

Product Name	APAR
NCP V6R3	IR27091
NCP V7R1	IR27090

The NCP APAR listed in Figure 17 is required if you want NCP to initiate the deactivation of an out-of-sequence virtual route (VR).

Figure 17. NCP APARs Required to Initiate Deactivation of an Out-of-Sequence Virtual Route (VR)

Product Name	APAR
NCP V7R1	IR35146
NCP V7R2	IR35146
NCP V7R3	IR35146
NCP V7R4	IR35146
NCP V7R5	IR35146

The NCP APAR listed in Figure 18 is required if you want to use a duplicate TIC configuration for subarea connections.

Figure 18. NCP APAR Required to Use a Duplicate TIC Configuration for Subarea Connections

Product Name	APAR
NCP V7R5	IR35842

The NCP APAR listed in Figure 19 is required if you generate backup channel connections for the NCP-NCROUTE IP interface.

Figure 19. NCP APAR Required to Generate Backup Channel Connections for NCP-NCROUTE IP Interface

Product Name	APAR
NCP V7R5	IR33961

The NCP APAR listed in Figure 20 is required if you generate INN connections using LIC16 ISDN to ISDN TA.

Figure 20. NCP APAR Required to Generate INN Connections

Product Name	APAR
NCP V7R5	IR34013

The NCP APAR listed in Figure 21 is required if you code MAXDLCI for an ISDN physical line (D-Channel).

Figure 21. NCP APAR Required to Code MAXDLCI for D-Channel

Product Name	APAR
NCP V7R5	IR33979

The NCP APARs listed in Figure 22 are required if you code USGTIER=1, 2, 2.5, or 3 and have only channel links defined, and you wish to take advantage of the higher limits regarding the number of channel links that can be defined.

Figure 22. NCP APARs Required If You Code USGTIER=1, 2, 2.5, or 3

Product Name	APAR
NCP V7R1	IR34014
NCP V7R2	IR34014
NCP V7R3	IR34014
NCP V7R4	IR34014
NCP V7R5	IR34014

The NCP APAR listed in Figure 23 is required if you code QSZALERT on the BUILD statement to determine if a session or station is using an inordinate number of buffers.

Figure 23. NCP APAR Required to Include QSZALERT Function in NCP V7R5.

Product Name	APAR
NCP V7R5	IR36167

The NCP APARs listed in Figure 24 are required if you want to use CIR (Committed Information Rate) for bandwidth management of the 3746 Model 900 frame-relay lines.

<i>Figure 24. NCP APARs Required for Committed Information Rate (CIR)</i>	
Product Name	APAR
NCP V7R3	IR36380
NCP V7R4	IR36380
NCP V7R5	IR36380
NCP V7R6	IR36484

The NCP APAR listed in Figure 25 is required if you want to code TRANSBUF to indicate the number of transmission head buffers allocated for 3745 frame-relay physical lines.

<i>Figure 25. NCP APAR Required for Transmission Head Buffers</i>	
Product Name	APAR
NCP V7R6	IR36886

5.2.3.4.1 NPSI:

The NPSI APARs shown in Figure 26 are required to generate NPSI V3R8 with NCP V7R4, NCP V7R5, or NCP V7R6.

Figure 26. NPSI APARs Required to Generate NPSI V3R8 with NCP V7R4, NCP V7R5, or NCP V7R6

Product Name	APAR
NCP NPSI V3R8	IR32271 IR37825

5.2.3.4.2 DFSMS: The APARs listed in Figure 27 are required to use the High Level Assembler.

Figure 27. APARs Required to Use the High Level Assembler

Product Name	APAR
DFSMS/MVS Binder	OW26738
DFSMS/MVS Linkage Editor	OW27802
VM/ESA Linkage Editor	VM61534

5.3 Program Installation and Service Considerations

This section describes items that should be considered before you install or service SSP V4R7 VM.

VMSES/E is required to install and service this product.

If multiple users install and maintain licensed products on your system, there may be a problem getting the necessary access to MAINT's 51D disk. If you find there is contention for write access to the 51D disk, you can eliminate it by converting the Software Inventory from minidisk to Shared File System (SFS). Refer to *VMSES/E Introduction and Reference*, "Changing the Software Inventory to an SFS Directory" section, for information about how to make this change.

Customers will no longer install and service SSP V4R7 VM strictly using the MAINT user ID, but will use a new user ID, P654009E. This is the IBM suggested user ID name. You are free to change this to any user ID name you wish; however, a PPF override must be created.

Note: It may be easier to make the changes during the installation procedure 6.2, "Plan Your Installation For SSP V4R7 VM," step 6 on page 19, than after you have installed this product.

5.4 DASD Storage and User ID Requirements

Figure 28 on page 16 lists the user IDs and minidisks that are used to install and service SSP V4R7 VM.

Important Installation Notes:

User ID(s) and minidisks and SFS directories will be defined in 6.2, "Plan Your Installation For SSP V4R7 VM" on page 18 and are listed here so that you can get an idea of the resources that you will need prior to allocating them.

P654009E is a default user ID and can be changed. If you choose to change the name of the installation user ID, you need to create a Product Parameter Override (PPF) to change the name. This can be done in 6.2, "Plan Your Installation For SSP V4R7 VM," step 6 on page 19.

Note: If you choose to install SSP V4R7 VM on a common user ID, the default minidisk addresses for SSP V4R7 VM may already be defined. If any of the default minidisks required by SSP V4R7 VM are already in use, you have to create an override to change the default minidisks for SSP V4R7 VM so they are unique.

This release builds the ASM3705 assembler. A link to the CMSTOOLS (193) disk has been added to the Prodpart file.

Figure 28. DASD Storage Requirements for Target Minidisks

Minidisk owner (user ID)	Default Address	Storage in Cylinders		FB-512 Blocks	SFS 4-K Blocks	Usage
		DASD	CYLS			Default SFS Directory Name
P654009E	2B2	3390 3380 9345	29 35 35	42000	5250	Contains all the base code shipped with SSP V4R7 VM VMSYS:P654009E.SSP.OBJECT
P654009E	2C2	3390 3380 9345	4 5 5	6000	750	Contains customization files. This disk may also be used for local modifications. VMSYS:P654009E.SSP.LOCAL
P654009E	2D2	3390 3380 9345	16 20 20	24000	3000	Contains serviced files VMSYS:P654009E.SSP.DELTA
P654009E	2A6	3390 3380 9345	16 20 20	24000	3000	Contains AUX files and software inventory tables that represent the test service level of SSP V4R7 VM VMSYS:P654009E.SSP.APPLYALT
P654009E	2A2	3390 3380 9345	16 20 20	24000	3000	Contains AUX files and software inventory tables that represent the service level of SSP V4R7 VM that is currently in production. VMSYS:P654009E.SSP.APPLYPRD
P654009E	400	3390 3380 9345	25 30 30	36000	4500	Test BUILD disk. This code will be copied to a production disk. VMSYS:P654009E.SSP.TRUN
P654009E	401	3390 3380 9345	25 30 30	36000	4500	Production BUILD disk. Files from the test BUILD disk are copied here for application use. VMSYS:P654009E.SSP.RUN
P654009E	191	3390 3380 9345	25 30 30	36000	4500	P654009E user ID's 191 minidisk VMSYS:P654009E.

Note: Cylinder values defined in this table are based on a 4-K block size. FB-512 block and SFS values are derived from the 3380 cylinder values in this table. The FBA blocks are listed as 1/2-K but should be CMS formatted at 1-K size. 28 500 4-K blocks are needed for SFS install.

6.0 Installation Instructions

This section describes the installation methods and the step-by-step procedures to install SSP V4R7 VM.

The step-by-step procedures are in two column format. The steps to be performed are in bold large numbers. Commands for these steps are on the left hand side of the page in bold print. Additional information for a command may exist to the right of the command. For more information about the two column format refer to "Understanding Dialogs with the System" in *VM/ESA Installation Guide* (SC24-5526).

Each step of the installation instructions must be followed. Do not skip any step unless directed otherwise.

Throughout these instructions, the use of IBM-supplied default minidisk addresses and user IDs is assumed. If you use different user IDs, minidisk addresses, or SFS directories to install SSP V4R7 VM, adapt these instructions as needed for your environment.

Note!

The sample console output presented throughout these instructions was produced on a VM/ESA R2.2.0 system. If you are installing SSP V4R7 VM on a different VM/ESA system, the results obtained for some commands may differ from those depicted here.

6.1 VMSES/E Installation Process Overview

The following is a brief description of the main steps in installing SSP V4R7 VM using VMSES/E.

Plan Your Installation

Use the VMFINS command to load several VMSES/E files from the product tape and to obtain SSP V4R7 VM resource requirements.

Allocate Resources

The information obtained from the previous step is used to allocate the appropriate minidisks (or SFS directories) and user IDs needed to install and use SSP V4R7 VM.

Install the SSP V4R7 VM Product

Use the VMFINS command to load the SSP V4R7 VM product files from tape to the test BUILD and BASE minidisks/directories. VMFINS is used to update the VM SYSBLDS file used by VMSES/E for software inventory management.

Place SSP V4R7 VM Files into Production

Once the product files have been installed and the operation of SSP V4R7 VM is satisfactory, the product files are copied from the test BUILD disk to the production BUILD disk.

For a complete description of all VMSES/E installation options refer to *VMSES/E Introduction and Reference*.

6.2 Plan Your Installation For SSP V4R7 VM

The VMFINS command will be used to plan the installation. This section has 2 main steps that will:

- load the first tape file, containing installation files
- generate a "PLANINFO" file listing
 - all user ID and minidisk/SFS directory requirements
 - required products

To obtain planning information for your environment:

- 1** Log on as SSP V4R7 VM installation planner.
This user ID can be any ID that has read access to MAINT's 5E5 minidisk and write access to the MAINT 51D minidisk.
- 2** Mount the SSP V4R7 VM installation tape and attach it to the user ID at virtual address 181. The VMFINS EXEC requires the tape drive to be at virtual address 181.
- 3** Establish read access to the VMSES/E code.

**link MAINT 5e5 5e5 rr
access 5e5 b**

The MAINT 5E5 disk contains the VMSES/E code.

- 4** Establish write access to the Software Inventory disk.

**link MAINT 51d 51d mr
access 51d d**

The MAINT 51D disk is where the VMSES/E system-level Software Inventory and other dependent files reside.

Note: If another user already has the MAINT 51D minidisk linked in write mode (R/W), you only obtain read access (R/O) to this minidisk. If this occurs, you need to have that user re-link the 51D in read-only mode (RR), and re-issue the above LINK and ACCESS commands. Do not continue with these procedures until a R/W link is established to the 51D minidisk.

- 5** Load the SSP V4R7 VM product control files to the 51D minidisk.

vmfins install info (nomemo)

The NOMEMO option will load the memos from the tape but will not issue a prompt to send them to the system printer. Specify the MEMO option if you want to be prompted for printing the memo.

This command will perform the following:

- load Memo-to-Users

- load various product control files, including the Product Parameter File (PPF) and the PRODPART files

- create VMFINS PRODLIST on your A-disk. The VMFINS PRODLIST contains a list of products on the installation tape.

```
VMFINS2760I VMFINS processing started
VMFINS1909I VMFINS PRODLIST created on your A-disk
VMFINS2760I VMFINS processing completed successfully
Ready;
```

6 Obtain resource planning information for SSP V4R7 VM.

Notes:

- The product will **not** be loaded by the VMFINS command at this time.

vmfins install ppf 5654009E {SSP | SSPSFS} (plan nomemo)

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

The PLAN option indicates that VMFINS will perform requisite checking, plan system resources, and provide an opportunity to override the defaults in the product parameter file.

You can override any of the following:

- the name of the product parameter file

- the default user IDs

- minidisk/directory definitions

Notes:

- a. If you change the PPF name, a default user ID, or other parameters via a PPF override, you need to use your changed values instead of those indicated (when appropriate), throughout the rest of the installation instructions, as well as the instructions for servicing SSP V4R7 VM. For example, you need to specify your PPF override file name instead of 5654009E for certain VMSES/E commands.
- b. If you are not familiar with creating PPF overrides using VMFINS, you should review the “Using the Make Override Panel” section in the *VMSES/E Introduction and Reference* before you continue.
- c. For more information about changing the VMSYS file pool name, refer to *VMSES/E Introduction and Reference*.

```
VMFINS2760I VMFINS processing started
VMFREQ2805I Product 5654009E component SSP passed requisite checking
Do you want to create an override for 5654009E SSP (prodid 5654009E)?
Enter 0 (No), 1 (Yes) or 2 (Exit)
0
VMFRMT2760I VMFRMT processing started
VMFRMT2760I VMFRMT processing completed successfully
VMFPLA1909I 5654009E PLANINFO created on your A-disk
VMFINS2760I VMFINS processing completed successfully
```

- 7** Review the install message log (\$VMFINS \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA: System Messages and Codes*, or use on-line HELP.

vmfview install

6.3 Allocate Resources for Installing SSP V4R7 VM

Use the planning information in the 5654009E PLANINFO file, created in the **PLAN** step, to:

Create the P654009E user directory for minidisk install

OR

Create the P654009E user directory for SFS install

6.3.1 Installing SSP V4R7 VM on Minidisk

- 1 Obtain the user directory from the 5654009E PLANINFO file.

Note: The user directory entry is located at the bottom of the PLANINFO file of the resource section; these entries will contain all of the links and privilege classes necessary for the P654009E user ID. Use the directory entry found in PLANINFO as a model for input to your system directory.

- 2 Add the MDISK statements to the directory entry for P654009E. Use Figure 28 on page 16 to obtain the minidisk requirements.

- 3 If you are installing SSP V4R7 VM on a VM/ESA 370 system, the following directory entry change must be made:

For the P654009E directory entry:

- Change the user ID storage from 24M to 16M.
- Comment out or remove the MACHINE XA statement from the directory entry.

- 4 Add the P654009E directory to the system directory. Change the password for P654009E from xxxxxx to a valid password, in accordance with your security guidelines.

- 5 Place the new directories on-line using VM/Directory Maintenance (DIRMAINT) or an equivalent CP directory maintenance method.

Note

All minidisks for the P654009E user ID must be formatted before installing SSP V4R7 VM.

6.3.2 Installing SSP V4R7 VM in SFS Directories

- 1 Obtain the user directory from the 5654009E PLANINFO file.

Note: The user directory entry is located at the bottom of the PLANINFO file of the resource section; these entries contain all of the links and privilege classes necessary for the P654009E user ID. Use the directory entry found in PLANINFO as a model for input to your system directory.

- 2 If you are installing SSP V4R7 VM on a VM/ESA 370 Feature system, the following directory entry change must be made:

For the P654009E directory entry:

- Change the user ID storage from 24M to 16M.

- Comment out or remove the MACHINE XA statement from the directory entry.
- 3** Add the P654009E directory to the system directory. Change the password for P654009E from xxxxxx to a valid password, in accordance with your security guidelines.
- 4** Place the new directories on-line using VM/Directory Maintenance (DIRMAINT) or an equivalent CP directory maintenance method.
- 5** An SFS install also requires the following steps:
 - a** Determine the number of 4K blocks that are required for SFS directories by adding up the 4K blocks required for each SFS directory you plan to use.

If you intend to use all of the default SSP V4R7 VM SFS directories, the 4K block requirements for each SSP V4R7 VM are summarized in Figure 28 on page 16.

This information is used when enrolling the P654009E to the VMSYS filepool.
 - b** Enroll user P654009E in the VMSYS filepool using the ENROLL USER command:

```
ENROLL USER P654009E VMSYS: (BLOCKS blocks
```

where *blocks* is the number of 4K blocks that you calculated in the previous step.

Note: This must be done from a user ID that is an administrator for VMSYS: filepool.
 - c** Determine if there are enough blocks available in the filepool to install SSP V4R7 VM. This information can be obtained from the QUERY FILEPOOL STATUS command. Near the end of the output from this command is a list of minidisks in the filepool and the number of blocks free. If the number of blocks free is smaller than the total 4K blocks needed to install SSP V4R7 VM, you need to add space to the filepool. Refer to *VM/ESA SFS/CRR Planning, Administration, and Operation* for information about adding space to a filepool.
 - d** Create the necessary subdirectories listed in the 5654009E PLANINFO file using the CREATE DIRECTORY command.

set filepool vmsys:
create directory *dirid*

dirid is the name of the SFS directory you're creating, such as:

```
create directory vmsys:P654009E.SSP  
create directory vmsys:P654009E.SSP.object  
:
```

If necessary, refer to *VM/ESA CMS Command Reference* for more information about the CREATE DIRECTORY command.

A complete list of default SSP SFS directories is provided in Figure 28 on page 16.

- e** If you intend to use an SFS directory as the work space for the P654009E user ID, include the following IPL control statement in the P654009E directory entry:

```
IPL CMS PARM FILEPOOL VMSYS
```

This will cause CMS to automatically access the P654009E's top directory as file mode A.

6.4 Install SSP V4R7 VM

The *ppfname* used throughout these installation instructions is **5654009E**, which assumes you are using the PPF supplied by IBM for SSP V4R7 VM. If you have your own PPF override file for SSP V4R7 VM, you should use your file's *ppfname* instead of **5654009E**. The *ppfname* you use should be used **throughout** the rest of this procedure.

- 1** Log on to the installation user ID **P654009E**.
- 2** Create a PROFILE EXEC that will contain the ACCESS commands for MAINT 5E5 and 51D minidisks.

```
xedit profile exec a  
====> input /**/  
====> input 'access 5e5 b'  
====> input 'access 51d d'  
====> file
```

If either 5E5 or 51D is in a shared file system (SFS) then substitute your SFS directory name in the access command.

- 3** Execute the profile to access MAINT's minidisks.

profile

- 4** Establish write access to the Software Inventory disk, if it is not already linked R/W.

Note: If the MAINT 51D minidisk was accessed R/O, you need to have the user who has it linked R/W link it as R/O. You can then issue the following commands to obtain R/W access to it.

**link MAINT 51d 51d mr
access 51d d**

5 Have the SSP V4R7 VM installation tape mounted and attached to P654009E at virtual address 181. The VMFINS EXEC requires the tape drive to be at virtual address 181.

6 Install SSP V4R7 VM.

Notes:

If you have already created a PPF override file, you should specify your override file name after the **PPF** keyword for the following VMFINS command.

You may be prompted for additional information during VMFINS INSTALL processing depending on your installation environment. If you are unsure how to respond to a prompt, refer to “Installing Products with VMFINS” and “Install Scenarios” chapters in *VMSES/E Introduction and Reference* to decide how to proceed.

vmfins install ppf 5654009E {SSP | SSPSFS} (nomemo nolink

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

The NOLINK option indicates that you don't want VMFINS to link to the appropriate minidisks, only access them if not accessed.


```

VMFINS2760I VMFINS processing started
VMFREQ2805I Product 5654009E component SSP passed requisite checking
Do you want to create an override for 5654009E SSP (prodid 5654009E)?
Enter 0 (No), 1 (Yes) or 2 (Exit)
0
VMFINT2760I VMFINST processing started
VMFSET2760I VMFSETUP processing started
VMFUTL2205I Minidisk|Directory Assignments:
      String      Mode  Stat  Vdev  Label/Directory
VMFUTL2205I LOCALSAM  E    R/W  2C2   SES2C2
VMFUTL2205I APPLY    F    R/W  2A6   SES2A6
VMFUTL2205I          G    R/W  2A2   SES2A2
VMFUTL2205I DELTA    H    R/W  2D2   SES2D2
VMFUTL2205I BUILD0   I    R/W  400   SES400
VMFUTL2205I BASE1    J    R/W  2B2   SES2B2
VMFUTL2205I -----  A    R/W  191   SES191
VMFUTL2205I -----  B    R/O  5E5   MNT5E5
VMFUTL2205I -----  D    R/W  51D   SES51D
VMFUTL2205I -----  S    R/O  190   MNT190
VMFUTL2205I -----  Y/S  R/O  19E   MNT19E
VMFSET2760I VMFSETUP processing completed successfully
VMFREC2760I VMFREC processing started
VMFREC1852I Volume 1 of 1 of INS TAPE 9800
VMFREC1851I (1 of 6) VMFRCAXL processing AXLIST
VMFRCX2159I Loading 0 part(s) to DELTA 2D2 (H)
VMFREC1851I (2 of 6) VMFRCPTF processing PARTLST
VMFRCP2159I Loading 0 part(s) to DELTA 2D2 (H)
VMFREC1851I (3 of 6) VMFRCCOM processing DELTA
VMFRCC2159I Loading 0 part(s) to DELTA 2D2 (H)
VMFREC1851I (4 of 6) VMFRCALL processing APPLY
VMFRCA2159I Loading part(s) to APPLY 2A6 (F)
VMFRCA2159I Loaded 1 part(s) to APPLY 2A6 (F)
VMFREC1851I (5 of 6) VMFRCALL processing BASE
VMFRCA2159I Loading part(s) to BASE1 2B2 (J)
VMFRCA2159I Loaded 2482 part(s) to BASE1 2B2 (J)
VMFREC1851I (6 of 6) VMFRCALL processing BUILD
VMFRCA2159I Loading part(s) to BUILD0 400 (I)
VMFRCA2159I Loaded 112 part(s) to BUILD0 400 (I)
VMFREC2760I VMFREC processing completed successfully
VMFINT2603I Product installed
VMFINS2760I VMFINS processing completed successfully

```

- 7** Review the install message log (\$VMFINS \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA System Messages and Codes*, or use on-line HELP.

vmfview install

6.4.1 Update Build Status Table for SSP V4R7 VM

- 1 Update the VM SYSBLDS software inventory file for SSP V4R7 VM.

vmfins build ppf 5654009E {SSP | SSPSFS} (serviced nolinek

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

The SERVICED option will build any parts that were not built on the installation tape (if any) and update the Software Inventory build status table showing that the product 5654009E has been built.

- 2 Review the install message log (\$VMFINS \$MSGLOG). If necessary, correct any problems before going on. For information about handling specific error messages, refer to *VM/ESA: System Messages and Codes*, or use on-line HELP.

vmfview install

6.5 Place SSP V4R7 VM Into Production

This section describes the procedure to place SSP V4R7 VM into production.

6.5.1 Copy SSP V4R7 VM Files Into Production

- 1 Log on to P654009E user ID. This user ID owns the disk that will contain the "production" level of the SSP V4R7 VM code.

- a If installing using minidisks

access 400 e

access 401 f

vmfcopy * * e = = f2 (prodid 5654009E%SSP olddate replace

The VMFCOPY command will update the VMSES PARTCAT file on the 401 disk.

- b If installing using Shared File System

access P654009E.SSP.trun e

access P654009E.SSP.run f

vmfcopy * * e = = f2 (prodid 5654009E%SSP olddate replace

The VMFCOPY command will update the VMSES
PARTCAT file on the 401 disk.

SSP V4R7 VM is now installed and built on your system.

7.0 Service Instructions

This section contains the procedure to install CORrective service to SSP V4R7 VM. VMSES/E is used to install service for SSP V4R7 VM.

To become more familiar with service using VMSES/E, you should read the introductory chapters in *VMSES/E Introduction and Reference*. This manual also contains the command syntax for the VMSES/E commands listed in the procedure.

Note: Each step of the service instructions must be followed. Do not skip any step unless otherwise directed. All instructions showing accessing of disks assume the use of default minidisk addresses. If different minidisk addresses are used, or if using a shared file system, change the instructions appropriately.

7.1 VMSES/E Service Process Overview

The following is a brief description of the main steps in servicing SSP V4R7 VM using VMSES/E.

Setup Environment

Access the software inventory disk. Use VMFSETUP command to establish the correct minidisk access order.

Merge Service

Use the VMFMRDSK command to clear the alternate apply disk before receiving new service. This allows you to easily remove the new service if a serious problem is found.

Receive Service

The VMFREC command receives service from the delivery media and places it on the Delta disk.

Apply Service

The VMFAPPLY command updates the version vector table (VVT), which identifies the service level of all the serviced parts. In addition, AUX files are generated from the VVT for parts that require them.

Reapply Local Service (if applicable)

All local service (mods) must be entered into the software inventory to allow VMSES/E to track the changes and build them into the system. Refer to Chapter 7 in the *VM/ESA Service Guide* for this procedure.

Build New Levels

The build task generates the serviced level of an object and places the new object on a test BUILD disk.

Place the New Service into Production

Once the service is satisfactorily tested, it should be put into production by copying the new service to the production disk, re-saving the NSS (Named Saved System).

7.2 Servicing SSP V4R7 VM

This section describes the procedure to service SSP V4R7 VM.

7.2.1 Prepare to Receive Service

The *ppfname* used throughout these servicing instructions is **5654009E**, which assumes you are using the PPF supplied by IBM for SSP V4R7 VM. If you have your own PPF override file for SSP V4R7 VM, you should use your file's *ppfname* instead of **5654009E**. The *ppfname* you use should be used **throughout** the rest of this procedure, unless otherwise stated differently.

1 Log onto SSP V4R7 VM service user ID **P654009E**

2 Establish access to the software inventory disk.

Note: If the MAINT 51D minidisk was accessed R/O, you need to have the user that has it accessed R/W link it R/O. You can then issue the following commands to obtain R/W access to it.

**link MAINT 51d 51d mr
access 51d d**

The 51D minidisk is where the VMSES/E Software Inventory files and other product dependent files reside.

3 Have the SSP V4R7 VM CORrective service tape mounted and attached to **P654009E**.

4 Establish the correct minidisk access order.

vmfsetup 5654009E {SSP | SSPSFS}

5654009E is the PPF that was shipped with the product. If you have your own PPF override, you should substitute your PPF name for 5654009E.

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

5 Receive the documentation. VMFREC, with the INFO option, loads the documentation and displays a list of all the products on the tape.

Electronic Service

If you are receiving service from Service Link (electronic service), refer to Appendix A, "Receiving Service for VMSES Envelopes", section "Receive Service Documentation", in the *VM/ESA Service Guide*. Remember to substitute the *ppfname* and *compname* used for servicing SSP V4R7 VM in the instructions shown in that Appendix. Then return back to this program directory and continue with step 7 on page 30 below.

vmfrec info

This command will load the service memo to the 191 disk.

- 6 Check the receive message log (\$VMFREC \$MSGLOG) for warning and error messages.

vmfview receive

Also make note of which products and components have service on the tape. To do this, use the PF5 key to show all status messages which identify the products on the tape.

- 7 Clear the alternate APPLY disk to ensure that you have a clean disk for new service.

vmfmrdsd 5654009E {SSP | SPSFS} apply

Use **SSP** for installing on minidisks or **SPSFS** for installing in Shared File System directories.

This command clears the alternate APPLY disk.

- 8 Review the merge message log (\$VMFMRD \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA System Messages and Codes*, or use on-line HELP.

vmfview mrd

7.2.2 Receive the Service

Note: If you are installing multiple service tapes, you can receive all of the service for this prodid before applying and building it.

Electronic Service

If you are receiving service from Service Link (electronic service), refer to Appendix A, "Receiving Service for VMSES Envelopes", section "Receive the Service", in the *VM/ESA Service Guide*. Remember to substitute the *ppfname* and *compname* used for servicing SSP V4R7 VM in the instructions shown in that Appendix. Then return back to this program directory and continue with section 7.2.3, "Apply the Service."

For **each** service tape you want to receive, do the following:

- 1 Receive the service.

vmfrec ppf 5654009E {SSP | SSPSFS}

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

This command receives service from your service tape. All new service is loaded to the DELTA disk.

- 2 Review the receive message log (\$VMFREC \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA System Messages and Codes*, or use on-line HELP.

vmfview receive

7.2.3 Apply the Service

- 1 Apply the new service.

vmfapply ppf 5654009E {SSP | SSPSFS}

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

This command applies the service that you just received. The version vector table (VVT) is updated with all serviced parts and all necessary AUX files are generated on the alternate apply disk.

You must review the VMFAPPLY message log if you receive a return code (RC) of a 4, as this may indicate that you have local modifications that need to be reworked.

- 2** Review the apply message log (\$VMFAPP \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA System Messages and Codes*, or use on-line HELP.

vmfview apply

Note

If you get message VMFAPP2120W, re-apply any local modifications before building the new SSP V4R7 VM. Refer to Chapter 7 in *VM/ESA Service Guide*. Follow the steps that are applicable to your local modification.

The following substitutions need to be made:

esalcl should be **5654009E**

esa should be **5654009E**

compname should be **SSP** or **SSPSFS** (minidisk or SFS)

appid should be **5654009E**

fm-local should be the fm of 2C2

fm-applyalt should be the fm of 2A6

If you have changed any of the installation parameters through a PPF override, you need to substitute your changed values where applicable.

Keep in mind when you get to the "Rebuilding Objects" step in *VM/ESA Service Guide*, you should return to this program directory at 7.2.4, "Update the Build Status Table."

7.2.4 Update the Build Status Table

- 1 Update the Build Status Table with serviced parts.

vmfbld ppf 5654009E {SSP | SSPSFS} (status

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

This command updates the Build Status Table.

Note

If the \$PPF files have been serviced, you get the following prompt:

```
VMFBLD2185R The following source product parameter files
             have been serviced:
VMFBLD2185R 5654009E $PPF
VMFBLD2185R When source product parameter files are serviced,
             all product parameter files built from them must be
             recompiled using VMFPPF before VMFBLD can be run.
VMFBLD2185R Enter zero (0) to have the serviced source
             product parameter files built to your A-disk
             and exit VMFBLD so you can recompile your
             product parameter files with VMFPPF.
VMFBLD2185R Enter one (1) to continue only if you have already
             recompiled your product parameter files with VMFPPF.
```

0 Enter a 0 and complete the following steps before you continue.

```
VMFBLD2188I Building 5654009E $PPF
             on 191 (A) from level $PFnnnnn
```

vmfppf 5654009E {SSP | SSPSFS}

Note: If you created your own PPF override, use your PPF name instead of 5654009E.

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

**copyfile 5654009E \$PPF a = = d (olddate replace
erase 5654009E \$PPF a**

Note: **Do not** use your own PPF name in place of 5654009E for the COPYFILE and ERASE commands.

vmfblid ppf 5654009E {SSP | SSPSFS} (status

1 Re-issue VMFBLD to complete updating the build status table.
Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories. When you receive the prompt that was previously displayed, enter a 1 to continue.

- 2 Use VMFVIEW to review the build status messages, and see what objects need to be built.

vmfview build

7.2.5 Build Serviced Objects

- 1 Rebuild SSP V4R7 VM serviced parts.

vmfbld ppf 5654009E {SSP | SSPSFS} (serviced

Use **SSP** for installing on minidisks or **SSPSFS** for installing in Shared File System directories.

Note: If your software inventory disk (51D) is not owned by the MAINT user ID then make sure the VMSESE PROFILE reflects the correct owning user ID.

- 2 Review the build message log (\$VMFBLD \$MSGLOG). If necessary, correct any problems before proceeding. For information about handling specific error messages, refer to *VM/ESA System Messages and Codes*, or use on-line HELP.

vmfview build

7.3 Place the New SSP V4R7 VM Service Into Production

This section describes the procedure to place the new SSP V4R7 VM Service into production.

7.3.1 Copy the New SSP V4R7 VM Serviced Files Into Production

- 1 Log on to P654009E user ID. This user ID owns the disk that will contain the "production" level of the SSP V4R7 VM code.

a If installing using minidisks

access 400 e

access 401 f

vmfcopy * * e = = f2 (prodid 5654009E%SSP olddate replace

The VMFCOPY command will update the VMSES
PARTCAT file on the 401 disk.

b If installing using Shared File System

access P654009E.SSP.trun e

access P654009E.SSP.run f

vmfcopy * * e = = f2 (prodid 5654009E%SSP olddate replace

The VMFCOPY command will update the VMSES
PARTCAT file on the 401 disk.

You have finished servicing SSP V4R7 VM.

Appendix A. APARs Incorporated into this Program

The following SSP V4R6 APARs are incorporated into this program:

IR36501	IR37112
IR36507	IR37115
IR36559	IR37124
IR36617	IR37163
IR36622	IR37168
IR36658	IR37170
IR36749	IR37180
IR36751	IR37215
IR36753	IR37277
IR36755	IR37329
IR36758	IR37403
IR36806	IR37453
IR36846	IR37469
IR36858	IR37471
IR36859	IR37593
IR36902	IR37726
IR36924	IR37748
IR36971	IR37800
IR36979	IR37829
IR36987	IR37916
IR37005	IR37925
IR37007	IR37945
IR37038	IR37965
IR37070	IR38017
IR37073	IR38040
IR37076	IR38270

A.1 PTFs and APARs Incorporated into This Service Level

The following SSP V4R7 PTFs and their corresponding APARs are incorporated into this service level.

Figure 29 (Page 1 of 2). SSP V4R7 PTFs and Corresponding APARs for Service Level 9908

PTF	CORRESPONDING APAR(S)
UR50524	IR38808
UR50526	IR38810
UR50528	IR38813
UR50530	IR38816
UR50791	IR39171

Figure 29 (Page 2 of 2). SSP V4R7 PTFs and Corresponding APARs for Service Level 9908

PTF	CORRESPONDING APAR(S)
UR50803	IR39535
UR50821	IR39540
UR50831	IR39545
UR50841	IR39477
UR50877	IR39684
UR50883	IR38816 IR39689
UR50888	IR39695
UR50890	IR39709
UR50900	IR39653
UR50918	IR39755

Reader's Comments

Program Directory for System Support Programs Version 4 Release 7, Service Level 9908, for VM

You may use this form to comment about this document, its organization, or subject matter. IBM may use or distribute whatever information you supply, in any way it believes appropriate, without incurring any obligation to you. Please understand that IBM makes no promises to always provide a response to your feedback.

For each of the topics below, please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE						
very satisfied					very dissatisfied	not applicable
1	2	3	4	5		N

	Satisfaction						
Ease of product installation	1	2	3	4	5	N	
Time required to install the product	1	2	3	4	5	N	
Contents of program directory	1	2	3	4	5	N	
Readability and organization of program directory tasks	1	2	3	4	5	N	
Necessity of all installation tasks	1	2	3	4	5	N	
Accuracy of the definition of the installation tasks	1	2	3	4	5	N	
Technical level of the installation tasks	1	2	3	4	5	N	
Installation verification procedure	1	2	3	4	5	N	
Ease of customizing the product	1	2	3	4	5	N	
Ease of migrating the product from a previous release	1	2	3	4	5	N	
Ease of putting the system into production after installation	1	2	3	4	5	N	
Ease of installing service	1	2	3	4	5	N	

Did you order this product as an independent product or as part of a package?

Independent

Package

What type of package was ordered?

CustomPac

FunctionPac

SystemPac

System Delivery Offering (SDO)

Other - Please specify type: _____

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of VM products using VMSES/E?

Yes

How many years of experience do they have? _____

No

How long did it take to install this product? _____

If you have any comments to make about your ratings above, or any other aspect of the product installation, please list them below:

Please provide the following contact information:

Name and Job Title

Organization

Address

Telephone

Thank you for your participation.

Please send the completed form to the following address, or give to your IBM representative who will forward it to the System Support Programs V4R7 for VM Development group:

Design & Information Development
Dept. CGF/Bldg. 656
International Business Machines Corporation
PO Box 12195
RESEARCH TRIANGLE PARK NC 27709-9990

Tell Us What You Think!

**System Support Programs V4R7 for VM
VM/ESA**

Publication No. GI10-0990-01

We hope you find this publication useful, readable, and technically accurate, but only you can tell us! Your comments and suggestions will help us improve our technical publications. Please take a few minutes to let us know what you think by completing this form. If you are in the USA, you can mail this form postage free or fax it to us at 1-800-253-3520. Elsewhere, your local IBM branch office or representative will forward your comments or you may mail them directly to us.

Overall, how satisfied are you with the information in this book? Satisfied Dissatisfied

How satisfied are you that the information in this book is: Satisfied Dissatisfied

- Accurate
- Complete
- Easy to find
- Easy to understand
- Well organized
- Applicable to your task

Specific comments or problems:

Please tell us how we can improve this book:

Thank you for your comments. If you would like a reply, provide the necessary information below.

Name Address

Company or Organization _____

Phone No. _____

Tell Us What You Think!
GI10-0990-01

Cut or Fold
Along Line


Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

Design & Information Development
IBM Corporation
Software Reengineering
Department G71A/ Bldg 503
P.O. Box 12195
Research Triangle Park, NC 27709-9990



Fold and Tape

Please do not staple

Fold and Tape

GI10-0990-01

Cut or Fold
Along Line

Program Number: 5654-009 5700
5801
5802

Printed in U.S.A.

GI10-0990-01

