

z/VM



# DFSMS/VM Planning Guide

*version 5 release 3*



z/VM



# DFSMS/VM Planning Guide

*version 5 release 3*

**Note!**

Before using this information and the product it supports, read the information in "Notices" on page 33.

This edition applies to version 5, release 3, modification 0 of IBM z/VM (product number 5741-A05) and to all subsequent releases and modifications until otherwise indicated in new editions.

This edition replaces SC24-6089-00.

© **Copyright International Business Machines Corporation 1992, 2007. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>About This Book</b> . . . . .	v
Who Should Read This Book . . . . .	v
What You Should Know before Reading This Book . . . . .	v
What This Book Contains . . . . .	v
Where to Find More Information . . . . .	v
How to Send Your Comments to IBM . . . . .	vi
<b>Summary of Changes</b> . . . . .	vii
SC24-6089-01, z/VM Version 5 Release 3 . . . . .	vii
SC24-6089-00, z/VM Version 5 Release 1 . . . . .	vii
<b>Chapter 1. Before You Start to Plan for Your System</b> . . . . .	1
Space Management . . . . .	1
Minidisk Management . . . . .	1
Removable Media Services . . . . .	2
Interactive Storage Management Facility . . . . .	2
Migrating from a Previous Release of DFSMS/VM . . . . .	3
Planning Overview . . . . .	3
<b>Chapter 2. Analyzing Your System Environment</b> . . . . .	5
Planning Your New Space Management Environment . . . . .	6
Choosing Which SFS File Pools to Manage . . . . .	6
Deciding How DFSMS/VM Manages Files . . . . .	6
Defining Management Classes . . . . .	8
Choosing the ACS Process . . . . .	10
Choosing the ACS Method . . . . .	11
Deciding When and Where DFSMS/VM Migrates and Erases Files . . . . .	12
Using an Installation-Wide Exit for Migration and Erasure . . . . .	13
Placing Files under DFSMS/VM Control . . . . .	13
<b>Chapter 3. Authorizing Users</b> . . . . .	15
Using RACF Security Server for z/VM for Security . . . . .	15
Using the DFSMS Authorization File . . . . .	16
Using Other Security Facilities . . . . .	16
<b>Chapter 4. Planning for Installation</b> . . . . .	17
Verifying the DFSMS/VM Control File Defaults . . . . .	17
Setting Up Virtual Machines for DFSMS/VM to Use . . . . .	17
Setting Up a TSM Virtual Machine for ML2 . . . . .	18
Starting DFSMS/VM . . . . .	19
Generating Accounting Records . . . . .	19
Logging DFSMS/VM Messages . . . . .	20
Utilizing DFSMS/VM Migration Capabilities . . . . .	20
ML1 Considerations . . . . .	21
ML2 Considerations . . . . .	21
Example of Identifying Secondary Storage . . . . .	21
Defining Coordinated Resource Recovery . . . . .	23
Backing Up and Recovering Migrated Files . . . . .	24
Storage Requirements . . . . .	25
DFSMS/VM Product Code, Virtual Machines and Work Area . . . . .	25

ML1 Storage Requirements . . . . .	25
ML2 Storage Requirements . . . . .	26
Other DFSMS/VM Files . . . . .	26
<b>Appendix A. Planning Activities Checklist . . . . .</b>	<b>27</b>
<b>Appendix B. Planning for ACS and Management Classes . . . . .</b>	<b>29</b>
Sample of a ACS and Management Class Work Sheet . . . . .	30
ACS and Management Class Work Sheet . . . . .	31
<b>Notices . . . . .</b>	<b>33</b>
Programming Interface Information . . . . .	34
Trademarks . . . . .	34
<b>Glossary . . . . .</b>	<b>35</b>
<b>Bibliography . . . . .</b>	<b>37</b>
Where to Get z/VM Publications . . . . .	37
z/VM Base Library . . . . .	37
Overview . . . . .	37
Installation, Migration, and Service . . . . .	37
Planning and Administration . . . . .	37
Customization and Tuning . . . . .	37
Operation and Use . . . . .	37
Application Programming . . . . .	38
Diagnosis . . . . .	38
Publications for z/VM Optional Features . . . . .	38
Data Facility Storage Management Subsystem for VM . . . . .	38
Directory Maintenance Facility for z/VM . . . . .	39
Performance Toolkit for VM™ . . . . .	39
RACF® Security Server for z/VM . . . . .	39
RSCS Networking for z/VM . . . . .	39
Additional Publications . . . . .	39
<b>Index . . . . .</b>	<b>41</b>

---

## About This Book

Data Facility Storage Management Subsystem/Virtual Machine (DFSMS/VM®) is an IBM® z/VM® feature that improves productivity by providing storage management for Shared File System (SFS) storage and by easing the task of moving minidisks from one physical device to another.

---

## Who Should Read This Book

This book is a guide for system programmers and storage administrators who need to plan for the installation and use of DFSMS/VM Function Level 221.

---

## What You Should Know before Reading This Book

You should have an understanding of z/VM, SFS file pools, and SFS storage groups. If you have not already done so, you should read the *z/VM: General Information* and the *z/VM: CMS User's Guide* (especially the overview of SFS), and at least browse the SFS part of the *z/VM: CMS File Pool Planning, Administration, and Operation*.

---

## What This Book Contains

This book describes the following:

- Productivity tools for managing storage groups within the Shared File System (SFS), minidisks, and Removable Media Services (RMS), and also describing an Interactive Storage Management Facility (ISMF).
- Analyzing your system environment
- Authorizing users
- Planning for installation, including a planning activities checklist.

---

## Where to Find More Information

For information about related publications, refer to the “Bibliography” on page 37.

### Links to Other Online Books

If you are viewing the Adobe® Portable Document Format (PDF) version of this book, it may contain links to other books. A link to another book is based on the name of the requested PDF file. The name of the PDF file for an IBM book is unique and identifies the edition. The book links provided in this book are for the editions (PDF names) that were current when the PDF file for this book was generated. However, newer editions of some books (with different PDF names) may exist. A link from this book to another book works only when a PDF file with the requested name resides in the same directory as this book.

---

## How to Send Your Comments to IBM

IBM welcomes your comments. You can use any of the following methods:

- Complete and mail the Readers' Comments form (if one is provided at the back of this book) or send your comments to the following address:

IBM Corporation  
MHVRCFS, Mail Station P181  
2455 South Road  
Poughkeepsie, New York 12601-5400  
U.S.A.

- Send your comments by FAX:
  - United States and Canada: 1-845-432-9405
  - Other Countries: +1 845 432 9405
- Send your comments by electronic mail to one of the following addresses:
  - Internet: [mhvrcfs@us.ibm.com](mailto:mhvrcfs@us.ibm.com)
  - IBMLink™ (US customers only): IBMUSM10(MHVRCFS)

Be sure to include the following in your comment or note:

- Title and complete publication number of the book
- Page number, section title, or topic you are commenting on

If you would like a reply, be sure to also include your name, postal or e-mail address, telephone number, or FAX number.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.



---

## Summary of Changes

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

---

### **SC24-6089-01, z/VM Version 5 Release 3**

This edition supports the general availability of z/VM V5.3.

---

### **SC24-6089-00, z/VM Version 5 Release 1**

This edition supports the general availability of z/VM V5.1.



---

## Chapter 1. Before You Start to Plan for Your System

Data Facility Storage Management Subsystem/VM (DFSMS/VM) is a feature of z/VM, which improves productivity by offering tools for managing three aspects of storage in your system: storage groups within the Shared File System (SFS), minidisks, and Removable Media Services (RMS). With DFSMS/VM, you can manage system storage through DFSMS commands that run under CMS and through the Interactive Storage Management Facility (ISMF).

SFS is a CMS file system for sharing CMS files among users through the use of file pools. A *file pool* is a collection of minidisks that contains files for a number of users. DFSMS/VM manages user files within a file pool more efficiently than the users can themselves.

The RMS support of DFSMS/VM provides the interface to the IBM 3495 Tape Library Dataserver.

---

### Space Management

Through DFSMS/VM Function Level 221, the storage administrator can apply space management policies to files in SFS file pools by assigning management classes to SFS files and directories. Each management class contains a set of migration and expiration criteria which tell DFSMS/VM how to manage SFS files. When a file meets the expiration criteria of its management class, it becomes eligible for erasure by DFSMS/VM. When a file meets the migration criteria of its management class, it becomes eligible to be migrated (compacted and moved) to secondary storage. Secondary storage consists of migration level 1 (ML1) and if desired, migration level 2 (ML2). ML1 is an SFS file space. ML2 is a Tivoli Storage Manager (TSM) storage repository on DASD or tape.

DFSMS/VM assigns management classes automatically through the automatic class selection (ACS) process. Through this process, a file acquires a management class in one of three ways:

- It is assigned a specific management class.
- It inherits the management class of its parent directory.
- It inherits the system default management class.

Migrated files are recalled automatically whenever the file owner or an authorized user accesses the file. The automatic recall of a file can be suppressed by issuing the CMS SET RECALL command. A file can also be recalled by a DFSMS/VM command.

---

### Minidisk Management

DFSMS/VM also assists you in managing CMS minidisks by providing a fast, reliable data mover and minidisk checker. With DFSMS/VM, managing minidisks becomes an automated process that:

- Uses the DFSMS/VM high-performance data mover to move minidisks quickly and efficiently

## Before You Plan Your System

- Performs many preparatory, directory update, and cleanup tasks automatically, eliminating steps you would normally do manually
- Allows you to move data to new DASD during prime shift by performing directory updates in place and offering options that help you control and minimize the impact on VM users.

The minidisk checker included with DFSMS/VM evaluates the integrity of a CMS minidisk by checking its file structure and reporting the results to you.

---

## Removable Media Services

DFSMS/VM Function Level 221 provides a high-level interface to automated tape functions provided by the IBM 3495 Tape Library Dataserver. If you are installing an IBM 3495 in the VM environment, the RMS support of DFSMS/VM can be invoked by your tape management system to:

- Automate mounting and demounting of tape cartridges
- Establish and manage logical groups of cartridges for scratch pools and application data
- Associate logical groups of cartridges with the automatic cartridge loading capabilities of library tape drives
- Control input and output of IBM 3495 library cartridges
- Provide information about library resources and library requests that are being processed.

The interface to the IBM 3495 functions are provided as a subset of DFSMS/VM commands and as a set of the Callable Service Library (CSL) application programming interfaces. RMS support eliminates the need for your tape management system and users to be aware of the IBM 3495.

If you have an IBM 3495 installed, several types of planning are required. For example, the interaction of your tape management system with the interface must be defined, and the standard device configuration planning must take place. These tasks are described in the *z/VM: DFSMS/VM Removable Media Services*.

---

## Interactive Storage Management Facility

Most DFSMS/VM functions are available through the Interactive Storage Management Facility (ISMF) that is provided with the product. ISMF is designed to be easy to learn, incorporating operations familiar to ISPF users. It has many features and operations similar to its z/OS™ environment counterpart, providing a consistent user interface for storage management tasks in both environments. (You can also perform many DFSMS/VM functions independently, using commands that run under CMS.)

ISMF offers:

- Menus from which you choose the application you want to use or the task you want to perform.
- Entry panels that contain default values and prompts. On some entry panels, values you enter are saved, allowing you to use those panels again in last-use mode.

- List panels that display information in tabular format and allow you to initiate operations and your own user extensions against the list entries.

ISMF provides on-line information through the ISPF help facility. You can display help information from any ISMF panel simply by pressing a predefined PF key. You can obtain information related to the task you are currently performing, or you can use the help facility index to go directly to specific information you want to view.

---

### Migrating from a Previous Release of DFSMS/VM

If you are migrating from a previous release of DFSMS/VM, see the *Program Directory for DFSMS/VM Function Level 221* for instructions.

---

### Planning Overview

Thorough planning will help you to begin using the functions of DFSMS/VM Function Level 221 quickly and efficiently. This book suggests a planning process that includes the following steps:

1. Analyze your system environment.
2. Decide who to authorize as storage administrators and how to authorize them.
3. Plan how you will install DFSMS/VM within your existing system.

Work sheets, starting on page 27, are provided to help you track your progress.

## Before You Plan Your System

## Chapter 2. Analyzing Your System Environment

To plan effectively for the DFSMS/VM Function Level 221 functions, you need to understand your current environment and how you can use these functions on your system. Decisions about how you use the functions affect how you set up DFSMS/VM.

You need to ensure that you have the processors and programs required to use DFSMS/VM. You also need to consider if any of your non-IBM software or in-house software might conflict with DFSMS/VM.

DFSMS/VM Function Level 221:

- Operates on all processors supported by z/VM version 5 release 3. See *z/VM: General Information* for further information.
- Is supported on z/VM V5R3.0 and requires the VMSYS file pool.

If you choose to install the RMS, space management, or minidisk management functions of DFSMS/VM, you will need to install some of the following programs:

- Language Environment® support included with z/VM, if you plan to use the space management function of DFSMS/VM, or if other hosts on the network plan to use TCP/IP to communicate with DFSMS/VM for Removable Media Services support.
  - IBM Compiler for REXX/370 (program number 5695-013) and IBM Library for REXX/370 (program number 5695-014), if you plan to write and compile your own ACS REXX exit for space management.
  - PDF Version 3 Release 2.0 (program number 5684-123) or later release with applicable APARs, or BROWSE available with the CMS component of z/VM if you wish to browse or edit within the ISMF panels for space management or minidisk management.
  - If the Migration Level 2 (ML2) function of DFSMS/VM is used, Tivoli® Storage Manager Extended Edition for z/OS and z/VM, V5.2 (5698-A11), Tivoli Storage Manager for z/OS and z/VM, V5.2 (5698-A13), or Tivoli Storage Manager for VM (5697-TS9) is required.
- Note:** All three of these program numbers have been withdrawn from marketing, and service has been discontinued.
- TCP/IP Level 430, provided with z/VM, if you plan to access the IBM 3495 Tape Library Dataserver from processors capable of 3490/3490E tape operations but incapable of controlling 3495 tape library (foreign host support).
  - ISPF Version 3 Release 2.0 (program number 5684-043) or later to run the ISMF part of DFSMS/VM to support the minidisk and space management functions.
  - DirMaint FL410 provided with z/VM or an equivalent directory maintenance product, for the minidisk management functions of DFSMS/VM.
  - RACF Security Server for z/VM or an equivalent product, to control access to DFSMS/VM commands.

A different security program can be used, or you can choose not to use one. If you use a security program other than RACF Security Server for z/VM you may

need to modify an installation-wide exit. See “Using Other Security Facilities” on page 16 for more information.

---

## Planning Your New Space Management Environment

After you have analyzed your system environment, you need to take a closer look at how to manage your SFS files and directories in a space management environment. Careful planning now will make the installation easier and have you ready to start using the space management function sooner.

This section contains some guidelines on:

- Choosing which file pools to manage
- Deciding how to manage files
- Defining management classes
- Choosing the ACS process and method
- Deciding when and where DFSMS/VM should migrate and erase files
- Using an installation-wide exit to control migration and erasure
- Placing files under DFSMS/VM control

### Choosing Which SFS File Pools to Manage

You need to decide which file pools to manage with DFSMS/VM. Any file pool can be managed by DFSMS/VM; however, you will probably want to place file pools under DFSMS management one by one. The best candidates would be those file pools that have the least amount of space to spare.

DFSMS/VM can manage any file that you choose, with these restrictions:

- Only files in SFS file pools can be managed with DFSMS/VM.
- Files in a directory control (DIRCONTROL) directory cannot be migrated, but can be assigned expiration criteria by DFSMS/VM. To take full advantage of the DFSMS/VM functions, put your files in a directory with FILECONTROL attributes.
- Files in file spaces starting with “DFSMS” are not managed by DFSMS/VM.

In addition, you may have further restrictions unique to your system.

### Deciding How DFSMS/VM Manages Files

DFSMS/VM gives you flexibility in determining how it manages files and which files it manages for you. You need to decide on the criteria for low-activity files and expired files. You can have DFSMS/VM:

- erase expired files
- erase expired files and migrate low-activity files to secondary storage (either ML1 or ML2)
- move files from ML1 to ML2.

The details of how DFSMS/VM manages your files depends on a number of things that you should think about and plan for before you begin using DFSMS/VM. For example, you might consider an accounting month summary file to be a low-activity file only a week after its last use, whereas a file with more activity, such as the weekly payroll file, becomes a low-activity file a month or more after its last use.



### Choosing Which Files to Erase

DFSMS/VM helps you manage your storage space by erasing files when they meet your expiration criteria. This is part of the function of the **DFSMS MANAGE** command. As part of your planning for DFSMS/VM, decide which files, if any, will be eligible to be expired. You tell DFSMS/VM when to consider files expired through management classes assigned to the files.

Work with your users and your management to determine how you can match DFSMS/VM's ability to erase expired files with their needs. Have them help you to determine if they have files that:

- Should never be erased
- Can be erased after a number of days has passed since they were created
- Can be erased after a number of days has passed since they were last referenced (a file is *referenced* when it is read from or written to)
- Can be erased both after a number of days has passed since they were created, and after nonusage (*nonusage* is when a number of days has passed since the files were last referenced)

At the same time, gather information on how you can distinguish among these kinds of files. Factors such as the file owner, the file pool name, the file name, the file type, and the directory name are examples of how you may distinguish between them. These distinguishing characteristics are needed when you set up automatic class selection (ACS) processing for your system.

For example, a user may have files with a file type of TEMP that can easily be re-created from other files if they are ever needed again. Through ACS processing, you can have DFSMS/VM assign a management class with an expiration date that is one week after last use to files with the file type TEMP.

You need to decide whether DFSMS/VM can erase a file entirely when it expires, or whether it can erase only the file data and leave the file access structure intact. For example, suppose you are the owner of a file that a number of users access to deposit data for a quarterly status report. The other users access the file through aliases that they have created. After the status report has been completed for the quarter, the file is no longer needed. You could let DFSMS/VM erase the file, but then you have to create a new one for the next quarter and give the contributing users access to the file again. And then each of the users has to create an alias to access that file again.

For this kind of file, a better way might be to have DFSMS/VM erase only the *data* in the file. Even though the file contains no data, the file and its structure remain, and the users still have access to it. Using the *Expiration Disposition* field of the management class, you can tell DFSMS/VM what to erase. This means less work for you and your users, and it frees space on your DASD.

### Choosing Which Files to Migrate

DFSMS/VM helps you manage your storage space by migrating files when they meet your migration criteria. This function is done by the **DFSMS MANAGE** command. You need to decide when files are considered low-activity and can be migrated. DFSMS/VM uses the low-activity criteria described in the management classes that you assign to the files through ACS processing.

## Analyzing Your System Environment

Work with users and management to determine how to handle migration of files. Files are easily recalled from secondary storage, so most files can be migrated after a reasonable time. Understanding how users create and use their files can help you to determine what that reasonable time is. For example, perhaps a user creates a file one day, works with the file for a week, occasionally refers to it in the next few months, but seldom refers to it after six months. You can tell DFSMS/VM to migrate the file to ML1 when it is not used for a week, and then move it to ML2 after 4 months on ML1. Recalling files from tape takes longer than recalling files from DASD. Depending on the type of storage medium used, recall time will be affected.

The needs of your system also determine what files to migrate, and when and where to migrate them. Limits on DASD space within file pools or SFS storage groups may dictate a shorter time before a file is considered low-activity. Through the management class definition, you can permit or prevent migration of the file. If you permit migration of the file, you must specify when the file is to be considered a low-activity file and ready for migration. In doing so, you should also consider the following:

- When should the file be migrated?
- Should the file be migrated to ML1 or ML2?
- If the file is on ML1 should it be moved to ML2?
- If the file is being moved from ML1 to ML2, how long will the file be on ML1 before being moved to ML2?

As you did for files with different expiration requirements, gather information on how you can distinguish among files with different migration requirements. Factors such as the file owner, the file pool name, the file name, the file type, file size, and the directory name are again examples of how you might distinguish among them. These distinguishing characteristics are needed when you set up automatic class selection (ACS) processing for your system.

## Defining Management Classes

The key to how space management works is the management class. Every file to be managed by DFSMS/VM must have a management class assigned to it, must inherit one from the parent directory, or use the system default. Through the ISMF Management Class Application panel, a management class name is associated with migration and expiration characteristics that you define. Defining management classes is a required step towards having your storage managed by DFSMS/VM. You need to have a management class for each collection of files that have similar migration and expiration requirements. Define management classes to do any of the following:

- Identify old and unused files which can be erased from primary storage
- Migrate old or infrequently used files to secondary storage
- Allow certain files to migrate only by command to secondary storage
- Specify how long you want to keep the migrated files on secondary storage before erasing them
- Specify how long migrated files remain on ML1 before moving to ML2

For example, you might decide that all files on your system can be managed in one of the following ways:

- Do not expire the file, but migrate directly to ML2 after 90 days of nonusage.
- Do not migrate, migrate to ML2 after 30 days nonusage.
- Migrate the file to ML1 after 7 days of nonusage and never move to ML2. Expire 30 days from date of last reference.
- Expire 21 days from date of last reference but do not migrate.
- Expire 3 days after date of creation but do not migrate.
- Migrate to ML1 after 7 days of nonusage and move to ML2 after 1 month on ML1. Expire the file 1 year after date of last reference.
- Do not expire the file, but migrate it to ML1 after 14 days of nonusage and never move it to ML2.
- Do not expire the file, but migrate it to ML2 after 14 days of nonusage.
- Do not expire the file but migrate it to ML1 after 1 week of nonusage, and then move it to ML2 after 1 year on ML1.
- Expire after 200 days nonusage and after 365 days from the creation date.

You will need a separate management class for each of these and you will need to define them through ISMF. (See the *z/VM: DFSMS/VM Storage Administration* for more information on defining management classes.)

### Naming Management Classes

When you define the management classes, give them meaningful names that help you when you need to update your system's ACS processing scheme. A list of possible names is shown in Table 1 on page 10. Your management class names should describe the kind of files that DFSMS/VM is managing, and they should be broad enough to be meaningful even though the storage management requirements may change. Then the only change you have to make to the file is the management class attributes. For example, in Table 1 on page 10, the accounting department wants their files migrated after 90 days. Later, they decide to migrate after 30 days. You can easily meet their requirements by changing the attributes but the management class name still reflects the file owners.

## Analyzing Your System Environment

Table 1. Example of Management Class Names

Management Class Name	Comments
ACNTDEPT	These files describe the financial status of the company. Don't expire these files but migrate the data after 90 days; move to ML2 after 120 days.
PURCHASE	These files list the parts and supplies ordered by the company. Expire 600 days from date of last reference but migrate the data after 7 days of nonusage. Do not move to ML2.
MANUCTRL	These files contain the manufacturing schedules for the month. Expire 21 days after last reference and do not migrate.
ORDRDEPT	These files contain customer orders waiting to be filled. Expire after 12 months but migrate on command only to ML2.
BILLING	These files contain the customer billings waiting for payment. Do not expire but migrate to ML1 after 14 days of nonusage; then move to ML2 10 days later.
TAXDEPT	These files contain the federal, state, and local tax reports of the company and its employees. Do not expire but migrate to ML1 after 6 months of nonusage; migrate to ML2 60 months later.
TEMPREPT	These files contain daily reports. Expire them 3 days after creation and do not migrate.

## Choosing the ACS Process

Through ACS processing, DFSMS/VM assigns or changes the management classes for files and directories. ACS processing occurs whenever you (or a user):

- Create a file
- Create a directory
- Place a storage group under DFSMS/VM management by using the **DFSMS CONVERT** command
- Manage (with the **DFSMS MANAGE** command) a storage group that has files or directories without management classes
- Migrate by command a file without a management class
- Recall a file managed by DFSMS/VM

ACS has access to many of the characteristics of a file or directory, including the user ID of the owner of the file; the fully qualified file name; size, logical record length, record format, the file space, and the directory in which the file resides or is being created. By setting up the ACS process to use these characteristics, you allow ACS to make a knowledgeable choice for a management class for the file.

When you create a file, you may choose the way your system handles ACS processing for file creation by selecting one of the following options:

- Run ACS processing, which assigns the management class at time of file creation
- Defer ACS processing until the file is converted, managed, or migrated by command

- Assign the null management class to the file, which indicates that the management class of the directory or default management class is used (inherited) when it is processed by DFSMS/VM

### Choosing the ACS Method

You need to choose how DFSMS/VM does ACS processing for your system. DFSMS/VM offers you flexibility for doing that task. You can use any combination of the following methods:

- Write an ACS routine in ACS language
- Write an ACS REXX installation-wide exit
- Write an ACS module installation-wide exit

You should base your decision of which method to use on the needs of the system and on the experience of the storage administrator. The ACS routine is compatible with the z/OS™ ACS routine.

#### ACS Routine

Using the ACS routine allows you to use the facilities of the ACS language. ISMF applications help you to develop and to test the ACS routine. The ACS language provides control constructs and pattern matching, and you can validate the routine before it is placed into production.

The ACS routine cannot perform loops or call external routines. Using this routine minimizes the possibility of errors at run time, but decreases the flexibility of the routine.

The ACS routine language is the same in DFSMS/VM as it is in z/OS with new variables for VM. This allows z/OS users to apply their working knowledge of ACS in z/OS directly to VM. You can use a routine written for z/OS in DFSMS/VM although not all of the variables in the routine may have meaning in VM. Decisions based on variables that have no meaning in VM may need to be changed. Using the new VM variables should be considered for ACS processing. See the *z/VM: DFSMS/VM Storage Administration* for more information on writing ACS processing routines.

#### ACS REXX Exit

DFSMS/VM allows an installation-written ACS REXX exit to be used along with the ACS routine or instead of it. Using the ACS REXX exit allows you to use the set of operators, instructions, and built-in functions of REXX. This exit may issue CMS or CP commands and may call external routines. However, you must use caution to avoid infinite loops, calling of external routines that could end abnormally, and assignment of management classes that do not exist in the active configuration. Unlike the ACS routine, the ACS REXX exit cannot be validated. For better performance, plan to compile your ACS REXX routines. See the *z/VM: DFSMS/VM Storage Administration* for more information on writing ACS REXX exits.

#### ACS Module Exit

DFSMS/VM allows an installation-written ACS module exit to be used instead of the ACS routine and ACS REXX exit, or along with them. The ACS module exit must be written in assembler language. Using the ACS module exit, allows you to perform tasks that cannot be done by the ACS routine alone (however, these tasks can generally be performed by the ACS REXX exit). You can call the ACS routine again from this exit. However, you must use caution to avoid infinite loops, calling

of external routines that could end abnormally, and assignment of management classes that do not exist. Unlike the ACS routine, the ACS module exit cannot be validated. Because of its complexity and the possibility of error, other methods should be considered before using the module exit. See the *z/VM: DFSMS/VM Storage Administration* for more information on writing ACS module exits.

### Deciding When and Where DFSMS/VM Migrates and Erases Files

Using the **DFSMS MANAGE** command lets you control when the migration of files or the erasing of expired files occurs. Because this command can use substantial processing time, you need to plan a time to issue this command to minimize its effects on users. That does not mean, however, that you should seldom issue the command. Plan to use the **MANAGE** command on a regular basis so as to guarantee space for storage group activity.

The **levels** option on the **MANAGE** command lets you choose which migration level you want to migrate to ML1, ML2, or both. For example, this could be very helpful if you want to ensure that migration to ML2 tape occurs at a time when operators are available to mount tapes. You could have **MANAGE** migrate files to ML1 during times when operators are not available. Then during times when operators are available, use the **MANAGE** command to move the ML1 files to ML2 tape and, if you choose, primary storage to ML2 tape.

Little penalty is incurred by running the **MANAGE** command frequently. DFSMS/VM migrates or expires files only if the data in the SFS storage group occupies space at or above a high threshold value. But you need to decide what that threshold value should be. By setting the high and low threshold values, you are determining how much space you want to use in the SFS storage group.

For example, you might set the high threshold at 85% and the low threshold at 50%. If an SFS storage group is 75% full, DFSMS/VM takes no action when the **MANAGE** command is issued for this SFS storage group. But, if the SFS storage group is 90% full, DFSMS/VM erases all files that have expired and then checks the storage group space again. If the space being used is still above the low threshold (50%), then eligible files are migrated. Once DFSMS/VM starts migrating, it migrates files only until the space occupied by data in the SFS storage group is just below the low threshold.

If you issue the **MANAGE** command infrequently, set thresholds too high or too low, many more files may no doubt have expired or become eligible for migration. This means that more processing is required when the command is finally issued. If there is too much processing to do, the system may not have enough time to complete the commands during the time you have planned for it, for example, during hours of low usage. You also run the risk of SFS storage groups filling up with files that have expired and should have been erased or migrated. Therefore, to take full advantage of the capabilities of DFSMS/VM, you need to determine how often to run the **MANAGE** command and what the optimum thresholds are.

One way to ensure that you run the **MANAGE** command on a regular basis is to write an EXEC that issues the command on various days of the week, or at various times of the day. You can also use an automated tool, for example HMF, to ensure the **MANAGE** command is run regularly. Timers can be set up to start one **MANAGE** cycle each night. With REXX and a simple timer program, you can set up DFSMS/VM to process the **MANAGE** command at a time that has the least effect on the production systems.

## Using an Installation-Wide Exit for Migration and Erasure

During the processing of the **DFSMS MANAGE** command, files may be migrated or erased. DFSMS/VM provides an installation-wide exit, named FSMMECHK, to monitor this process and, if you wish, prevent migration or erasure from occurring. To ensure data availability, make sure that a backup copy of the file exists before the file is migrated or becomes eligible for erasure. Use this exit to check for a backup copy before having DFSMS/VM take any action against the file. You can write the exit so that if a backup does not exist, the file is not migrated or erased. (If you schedule file backup more frequently than file migration, you may never need to use this exit.) See the *z/VM: DFSMS/VM Customization* for more information on this exit.

## Placing Files under DFSMS/VM Control

Files that were created before installation of DFSMS/VM Function Level 220 or in file pools do not have management classes assigned to them and therefore are not managed by DFSMS/VM. Files in file pools that were not managed by DFSMS/VM Function Level 220 do not have management classes assigned to them. The **DFSMS CONVERT** and **DFSMS MANAGE** commands (introduced in DFSMS/VM Function Level 220) allows these files and directories to be converted for space management. These commands invoke the conversion process by initiating ACS processing for each file and each directory with no management class.

Use the **DFSMS CONVERT** command when you are converting a file pool to a DFSMS/VM managed file pool, or if you make significant changes to the way management classes are assigned. You may also use the **DFSMS MANAGE** command when you have files and directories that have no management class. This command automatically converts files and directories that have been created without management classes, in addition to expiring and migrating files.

If you have used the space management function in DFSMS/VM Function Level 220 and you want to take advantage of the ML2 capability, you need to analyze your system and determine what changes need to be made. If you change the way management classes are assigned, you will need to run the **CONVERT** command with the **REDETERMINE** option.

## Analyzing Your System Environment



---

## Chapter 3. Authorizing Users

You need to define a plan both for authorizing users and determining who needs to be authorized as a storage administrator. Since functions such as moving mini-disks and erasing expired files are potentially harmful to the integrity and security of your system, you must restrict their use to storage administrators. General users also need some access to DFSMS/VM, for example, to get information about the management classes set up on the system. Make sure that only those users with the knowledge of and the responsibility for certain DFSMS/VM functions perform those functions, while at the same time others can get the information they need.

You control who uses DFSMS/VM in one of the following ways:

- By using RACF Security Server for z/VM, which allows you to restrict the use of individual DFSMS/VM commands.
- By listing users authorized to perform storage administrator functions in the DFSMS authorization file.
- By using a different security method to authorize users.

### Migrating from DFSMS/VM Function Level 210 to 221

The DGTQAUTH EXEC used in DFSMS/VM 210 has been replaced with the FSMVAUTH CSL routine that was introduced in DFSMS/VM 220. If you have modified DGTQAUTH, you can continue to use DGTQAUTH by replacing the FSMVAUTH CSL routine. See *z/VM: DFSMS/VM Customization* for more information on the FSMVAUTH CSL routine.

---

## Using RACF Security Server for z/VM for Security

RACF® is a software security product that protects information by controlling access to it. RACF controls what users can do on the system and protects your resources. It provides this security by identifying and verifying users, authorizing users to access protected resources, and recording and reporting any attempts to access your information.

RACF Security Server for z/VM retains information about users, resources, and access authorities in profiles stored in a special RACF file. There are two types of profiles: *discrete* and *generic*. A discrete profile contains security information about a single file, user, or resource. A generic profile contains security information about multiple files, users, or resources that may have similar characteristics and therefore require a similar level of protection.

For DFSMS/VM, you define profiles in RACF's FACILITY resource class. You can create a single generic profile (STGADMIN.\*) to protect all DFSMS/VM commands. The RMS RACF *entities* are a subset of DFSMS/VM RACF *entities* and can be protected with a single generic profile (STGADMIN.RM.\*). The *z/VM: DFSMS/VM Customization* provides the RACF entities for DFSMS/VM.

You can also create discrete profiles to specify authorization command-by-command, user-by-user, if you need that flexibility. For example, suppose you have several people who have duties as storage administrators, and one who acts as the lead storage administrator. You may give all storage administrators the authority to issue **DFSMS MANAGE** commands, but only the lead storage adminis-

## Authorizing Users

trator authority to issue **DFSMS CONVERT** commands. You may give the system operator the authority only to issue the **DFSMS STOP** command.

For more information on using RACF, see the *Resource Access Control Facility (RACF) Security Administrator's Guide*, SC28-1340. For instructions on using RACF to protect DFSMS/VM, see the *z/VM: DFSMS/VM Customization*.

---

## Using the DFSMS Authorization File

The simplest and least sophisticated of your options for authorizing users is to decide who will be permitted to perform storage administrator functions, then list their user IDs in the DFSMS authorization file located in directory VMSYS:DFSMS.CONTROL. Users listed in the file can then perform functions allowed only for storage administrators. Users not listed are considered general users, and can perform only limited functions through DFSMS/VM. To keep your system under control, only a small number of users should be designated as storage administrators.

For instructions on how to use this file, see *z/VM: DFSMS/VM Customization*.

---

## Using Other Security Facilities

You can use a security facility other than RACF Security Server for z/VM. If you choose a security facility that uses the RACROUTE macro, as RACF Security Server for z/VM does, you simply install that program instead of RACF Security Server for z/VM. DFSMS/VM uses whatever program answers to the RACROUTE macro. For more information on this macro, see the *External Security Interface (RACROUTE) Macro Reference*.

If your security facility does not use the RACROUTE macro or if you choose to devise your own method, you must customize the authorization process by replacing the installation-wide exit, FSMVAUTH. For more information on how to use this installation-wide exit, see *z/VM: DFSMS/VM Customization*.

---

## Chapter 4. Planning for Installation

Planning for DFSMS/VM includes considering how to install DFSMS/VM with your existing system. One of the most obvious things to plan for is the DASD space for the DFSMS/VM product code, but there are other things as well. Here is what we suggest you plan for:

- Verifying the DFSMS/VM control file defaults
- Setting up DFSMS/VM server virtual machines to use
- Setting up a TSM virtual machine for ML2
- Starting DFSMS/VM
- Generating accounting records
- Logging DFSMS/VM messages
- Utilizing DFSMS/VM Migration Capabilities
- Defining Coordinated Resource Recovery
- Backing up and recovering migrated files
- Storage requirements

For more information on installing DFSMS/VM, see the *Program Directory for DFSMS/VM Function Level 221*.

---

### Verifying the DFSMS/VM Control File Defaults

A sample of the DFSMS/VM control file (DGTVCNTL DATA) is provided with the product. It contains a list of keywords, each with a value specified. You can use these values or change them to meet your system requirements.

---

### Setting Up Virtual Machines for DFSMS/VM to Use

Whenever you issue a DFSMS command or use ISMF, DFSMS/VM accomplishes that task through virtual machines that it controls. These virtual machines can be the DFSMS master and servers, minidisk servers, and the RMS master. DFSMS/VM uses these virtual machines to accomplish its work as follows:

- The DFSMS master handles both space management and minidisk management operations.
- The DFSMS servers called *DFSMS machines* handle the space management operations such as migration, recall, and expiration of SFS files.
- The minidisk servers, called *minidisk machines*, handle minidisk management operations, such as moving and checking minidisks, and the building of minidisk lists.
- The removable media services master handles all RMS-related requests such as mounting or demounting cartridges, assigning cartridge categories to library devices, and providing library information.

Before you install DFSMS/VM, you will need to decide which functions (space management, minidisk management, or removable media services) you want to use. You can use just one of them, all three, or any combination of the three. When you have decided which functions you will use, set up only the virtual machines you will need.

## Planning for Installation

Because DFSMS/VM in one system is independent of DFSMS/VM in any other, you must define the virtual machines in each system. For example, you could have the DFSMS virtual machines on one system and the RMS virtual machine on another. If you plan to install DFSMS/VM on multiple systems, you will need to define the virtual machines in each system.

If you do not already have a previous release of DFSMS/VM installed and want minidisk management, you need to think about how often and how much moving and checking of minidisks you will be doing. In the DFSMS/VM control file, the default is three minidisk server machines. If you are moving a large amount of data from old to new DASD, you may need more than three. You can initially define as many as you need and then, when you finish moving the data to the new DASD, reduce that number.

The DFSMS/VM control file default for the number of the DFSMS server machines needed for space management is three. How many server machines you need depends on a number of factors, including:

- Whether or not you invoke ACS processing each time a file is created
- The number of file pools you manage
- The number of and size of the files in the file pools
- How fast you want DFSMS/VM to respond to automatic recalls
- How many storage groups are being processed by the **MANAGE** command at a time.

The requirements for the master and server machines can be produced using VMSES/E. See *z/VM: DFSMS/VM Customization* for further information about using VMSES/E. User IDs for these machines are provided in the DFSMS/VM control file, but you may change them if you wish.

---

## Setting Up a TSM Virtual Machine for ML2

DFSMS/VM Function Level 221 uses the Tivoli Storage Manager for VM (TSM) server as the repository for ML2 data. In addition to being a data repository, the TSM server provides tape processing and inventory management.

An installation using DFSMS/VM Function Level 221 ML2 support must set up a TSM server as the ML2 repository. It is recommended that this TSM server be dedicated exclusively for use by DFSMS/VM to keep ML2 data separate from other client data. Also, this server must be installed on the same VM system as the DFSMS master and server machines.

It is also recommended that the ML2 repository in TSM be set up primarily as tape storage. However, an installation may want to add some intermediate DASD levels in TSM to be used as ML2 DASD staging areas to ML2 tape. DFSMS/VM is just another client to TSM, and ML2 data will be subject to normal TSM processing based on whatever storage levels are established.

If you decide to share the TSM server with other applications besides DFSMS/VM, no other application may use the node or owner 'DFSMS'.

And if you share the TSM server with non-DFSMS/VM applications, there may be a performance penalty if the other applications are active when DFSMS/VM is active.

TSM has much flexibility in its hierarchy of storage for data, allowing you a great amount of flexibility in configuring the hierarchy. Ultimately, keep in mind that the purpose of DFSMS/VM using DFDSM™ as a repository is to provide ML2 to tape capability.

DFSMS/VM will use TSM's database as the inventory for ML2 data. This TSM database must be protected just as a primary storage catalog (or inventory) would be. It should be backed up regularly, protected from unauthorized access, and probably mirrored. These processes are already associated with the TSM server, but they become even more critical with DFSMS/VM Function Level 221; with migrated data, TSM now contains the primary versions of many files.

The TSM server should be managed through its normal administrative interfaces. See *Tivoli Storage Manager Program Directory for DFSMS/VM Function Level 221* for more information.

---

### Starting DFSMS/VM

You need to define a logon process for the virtual machines. For DFSMS/VM to start working, the master and server virtual machines that perform DFSMS/VM functions must be logged on. The logon process can be automatic or manual. Automatically logging of the DFSMS master machine and the TSM server machine is recommended whenever the VM system is IPLed. If the DFSMS machines are not operating, you will not be able to recall your migrated data. It is important for machines to be operating to allow users to access data. You should also allow the master machine to log on its servers.

Manually logging on the master and servers can be done but it is not recommended as an alternative to the automatic process. However, if you choose this method, keep in mind that the master machine must have sufficient time to complete its initialization before you manually log on server machines. See *z/VM: DFSMS/VM Customization* for additional information about establishing a logon process.

---

### Generating Accounting Records

DFSMS/VM offers the ability to generate accounting records. Two kinds of records are generated: user records and system records. User records are generated for command processing (including automatic recall and ACS processing during file and directory creation). System records are generated for DFSMS/VM overhead tasks; for example, DFSMS/VM initialization and logging. DFSMS/VM accounting records include elapsed time, CPU time, command name, blocks moved (for migrate, move, recall, and erase) and cylinders moved (for minidisk move). You need to decide if you want to generate DFSMS/VM accounting records.

The generation of accounting records is controlled in two ways:

1. Use the DFSMS\_ACCOUNTING and RM\_ACCOUNTING keywords in the DFSMS/VM control file to indicate if accounting records should be generated at all.
2. Use an installation-wide exit to alter or suppress the generation of accounting records.

See *z/VM: DFSMS/VM Storage Administration* and *z/VM: DFSMS/VM Customization* for more information on DFSMS/VM accounting.

---

## Logging DFSMS/VM Messages

DFSMS/VM presents messages in four categories: severe, error, warning, and informational.

With the DFSMS/VM control file keywords `DFSMS_LOG_TO_CONSOLE`, `DFSMS_LOG_TO_FILE`, `RM_LOG_TO_CONSOLE`, and `RM_LOG_TO_FILE`, you specify where and on which level messages are logged. See *z/VM: DFSMS/VM Messages and Codes* for a description of message level codes. You must specify at the least, the logging of severe messages with one of these keywords. If you choose to log the messages to a file, you have to specify the file pool and file space where you want the message log to reside.

The following are meanings of the message categories:

Category	Meaning
Severe	A component of DFSMS/VM abends or otherwise terminates because of some condition.
Error	DFSMS/VM cannot perform a function because of a condition that DFSMS/VM does not expect.
Warning	DFSMS/VM has performed the function correctly, but the results may not be what the command issuer expects.
Informational	DFSMS/VM has performed the function correctly, and the results are what the command issuer expects.

Depending on the severity category you decide to use, logging to a file can take up a large amount of DASD space. However, it does provide you with a greater level of detail, such as date, time stamp, and request ID. If an error occurs while DFSMS/VM is logging to a file, then the messages are logged to the console. You may experience some performance penalties logging to files with the message level at four; however, there is little penalty when the message level is between zero and three.

Because the DASD space may fill up quickly, plan to have DFSMS/VM manage the log files for you. For example, define a management class to expire the log files after one day. If you do have DFSMS/VM manage the log files, don't use a directory ID that begins with DFSMS. DFSMS/VM will not manage a file space with an ID that begins with DFSMS. Also, consider placing the log files in a storage group by themselves. DFSMS/VM keeps the current day's log file open continuously. An open log file will prevent you from backing up the storage group containing that file while DFSMS/VM is running.

---

## Utilizing DFSMS/VM Migration Capabilities

If you choose to use the migration capabilities of DFSMS/VM, you must select a location for secondary storage. Secondary storage can be either ML1, or ML1 and ML2. The type of secondary storage you choose depends on your management class selection. For ML1, you need to set up an SFS file space, while ML2 requires a TSM repository. If only ML2 is used for storage, you must still specify a

file space for ML1, even though it will be of minimal size. Global resource ID and LU name combinations must be unique for all DFSMS/VM systems within the Transparent Services Access Facility (TSAF) collection. These are specified in the DFSMS/VM control file as GLOBAL\_RESOURCE\_ID and FULLY\_QUALIFIED\_LUNAME.

### ML1 Considerations

ML1 file space can be placed in either a local or a global file pool. A restriction is that the system file pool VMSYS cannot be specified as the file pool for ML1.

It is recommended that ML1 be in a file pool that is separate from the files being managed. Even though it is not recommended, you may place ML1 in the same file pool as the files being managed. If you choose to locate ML1 in the same file pool as the files that are migrated, you must place ML1 in its own SFS storage group within the file pool.

### ML2 Considerations

ML2 data can only be placed in a TSM repository. It is recommended that you dedicate a TSM server to DFSMS/VM whose repository holds only ML2 data.

TSM policies can be specified so that data stored in TSM archive and backup repositories can be erased. However, TSM policies should be specified so that active data stored in ML2 by DFSMS/VM is not erased. This ensures DFSMS/VM maintains control of its data.

### Example of Identifying Secondary Storage

The system environment shown in Figure 1 on page 22 illustrates some things to consider when identifying secondary storage.

In our example, two VM systems with DFSMS/VM are connected using the TSAF. Each system has four file pools, two of which are for user files. The VMSYS file pool on each system contains system data such as program product files; it does not contain user files. The VMSYSR file pool on each system is the file pool for the Coordinated Resource Recovery (CRR) server.

In System 1, the VMSYS, VMSYSR, and VMSYS1 file pools are local file pools. GLOBAL1 is a global file pool, meaning that it is known to both systems through the TSAF collection. Users on both systems can access files on GLOBAL1. The lines connecting the DFSMS master virtual machines with the file pools, indicates that DFSMS/VM manages the VMSYS1 and GLOBAL1 file pools.




Figure 1. Example of a System Environment

In System 2, all four file pools are local. Users on System 1 cannot access files stored in the file pools of System 2. Only VMSYS2 is managed by DFSMS/VM, so files in file pool VMSYS3 do not expire nor can they be migrated by DFSMS/VM.

For each system, you must identify the secondary storage holding the migrated files. For ML1, you have three choices: identify a file space in a local file pool, identify a file space in a global file pool, or identify no file space at all. The ID of these file spaces must start with the letters 'DFSMS'. For ML2, there are two choices: define ML2, or do not define ML2. Using Figure 1, we will see how you might do each of these.

**Reminder:** If only ML2 is used, you must still specify ML1 even though its size will be minimal.

- Identify a file space in a local file pool.

You might choose file pool VMSYS1 for ML1 in System 1, and VMSYS3 for ML1 in System 2. Even though VMSYS3 is not managed by DFSMS/VM, you *can* use it for ML1. You also need to decide on a name for the file space itself. For our example, we chose DFSMS01 for System 1, and DFSMS02 for System 2.

You tell DFSMS/VM the location of secondary storage in the control file (DGTVCNTL DATA) with the key word MIGRATION\_LEVEL\_1. So for System 1, you can specify:



```
MIGRATION_LEVEL_1 SFS VMSYS1:DFSMS01.
```

and for System 2:

```
MIGRATION_LEVEL_1 SFS VMSYS3:DFSMS02.
```

You can also give the same name to the file spaces for both systems, because DFSMS/VM can keep track of which data is from which system. For example, you can specify DFSMS01 for System 2, as well.

```
MIGRATION_LEVEL_1 SFS VMSYS3:DFSMS01.
```

- Identify a file space in a global file pool.

GLOBAL1 is the only global file pool in this TSAF collection. In this case, you can name the ML1 file space DFSMS, because DFSMS/VM in both systems uses the same file space. On both systems, you would specify the following in their control files:

```
MIGRATION_LEVEL_1 SFS GLOBAL1:DFSMS.
```

Placing ML1 in a global file pool can be useful when one or more of the systems in a TSAF collection has limited DASD resources. This allows you to migrate files from a system that lacks resources to a system that has the resources. However, you need to weigh the advantages of centralizing your migrated files against being able to reliably access those files. Using a global file pool for ML1 is not recommended if there is a potential for the communication links to fail. By using a global file pool for ML1, System 2 relies on System 1 to access its own migrated files. If System 1 is not available, DFSMS/VM on System 2 is not able to recall any migrated files because the data is physically located on System 1.

- Identify no file space.

If you do not want to migrate files, leave the following statement as a comment or delete it from the control file:

```
* MIGRATION_LEVEL_1 SFS
```

With no file space for ML1 specified, DFSMS/VM can only erase files that have expired. Any attempt to migrate a file will fail because there is no secondary storage available.

---

## Defining Coordinated Resource Recovery

The Coordinated Resource Recovery (CRR) server coordinates any work that occurs between two different file pools. You need to define a CRR if:

- Your work directory is not in the same file pool as the one being managed.
- You are installing other programs that require CRR.

See *z/VM: CMS File Pool Planning, Administration, and Operation* for further information about CRR.

---

### Backing Up and Recovering Migrated Files

Almost every storage group should be backed up regularly. The only ones that you would not back up are those that contain files that you can afford to lose at any time. Each time you back up SFS storage groups that are managed by DFSMS/VM, the files that have been migrated to secondary storage are also backed up.

**Note:** The SFS FILEPOOL BACKUP utility makes copies of data migrated to ML1; however, for ML2 it only makes copies of the ML2 entries in the DFDSM database. No copy is made of the data migrated to ML2 since ML2 data probably resides on tape. Backing up the ML2 entries provides you with the ability to recover ML2 data after a loss of the primary storage entry (either the whole storage group or the individual files can be recovered from a media failure or accidental erasure.) This type of support requires no tape mounts for either backup or recovery. It is recommended that DFSMS management class definitions be coordinated with installation backup procedures to guarantee every file is backed up before it is eligible to be migrated.

The following commands are available to back up and recover files that are in SFS storage groups: **FILEPOOL BACKUP**, **FILEPOOL RESTORE**, and **FILEPOOL FILELOAD**. These commands process the secondary storage files during backup and recovery of the primary storage group.

To issue these commands, you must have at least read-authority to the DFSMS control file and to the DFSMS/VM product disk. When you issue the **FILEPOOL BACKUP** command, all files that have been migrated to secondary storage are backed up. When you issue the **FILEPOOL RESTORE** command, all files that had been migrated and backed up are recovered to secondary storage in migrated status. When you issue the **FILEPOOL FILELOAD** command, all individual files are restored.

When deciding how to backup secondary storage, consider the location of the log files and work directory. Put the log files and work directory (because they do not require back up) in a storage group that is separate from other data. If they are put in the same storage group as data needing to be backed up, you cannot back up that data while DFSMS/VM is running because the log files and work directory files are open. Therefore, consider placing the log files and work directory in a storage group that is separate from other data, or plan to back up that storage group when DFSMS/VM is not running.

**Attention:**

If you already have another method for backing up and restoring storage groups, make sure that the migrated files are backed up and recovered at the same time as the primary files. Failure to do so may result in the loss of data.

## Storage Requirements

You need to plan how much storage space is required in order to install and use DFSMS/VM. This section provides some guidelines for determining space allocation for:

- DFSMS/VM product code and virtual machines
- Work area for DFSMS/VM
- ML1 storage requirements
- ML2 storage requirements
- Other DFSMS/VM files

## DFSMS/VM Product Code, Virtual Machines and Work Area

You can determine the storage requirements of the DFSMS/VM product code and virtual machines using the VMSES/E command VMFINS INSTALL. Refer to Table 2 for the minimum storage requirements. Using the VMFINS INSTALL command with the PLAN option creates a planning information file that lists the size (how many blocks) and the block sizes (2K, 4K) of the product code and of the DFSMS/VM virtual machines. You can then convert the size and block size to cylinders for your particular DASD type using the VMSES/E VMFCNVT command. See *z/VM: VMSES/E Introduction and Reference* for more information about these commands.

<i>Table 2. Minimum Requirements for DFSMS/VM</i>		
DFSMS/VM	4K blocks	3390 DASD
Product Code	28800	164
DFSMS Master	2	1
RMS Master	2	1
Work Area	4000	N/A
<b>Note:</b> The numeric value for 3390 DASD is in cylinders.		

**Note:** If you are running only minidisk and space management or if you are running only ATL (automated tape library), the number of blocks for the work area can be 2000. You may need to increase the number of blocks to handle your concurrent activity requirements.

The space required to install a language feature is included in the above figures.

## ML1 Storage Requirements

Ideally, to be more efficient, store less active files on less expensive, slower-speed DASD, and more active files on more expensive, higher-speed DASD. DFSMS/VM helps you attain this efficiency if you specify the system's slower DASD as the location of ML1.

Because ML1 is specified as an SFS file space, you cannot directly specify slower DASD as the location of ML1. However, you can do it indirectly by choosing an SFS storage group where the minidisks that make up the group are on slower DASD.

## Planning for Installation

How much DASD space you need for ML1 depends on your installation's data reference patterns and the management classes established. Use the following formula to estimate DASD space requirements for ML1:

$$\frac{\text{(Number of 4K blocks in all file pools to be managed)} \times \text{(Percentage of less active data expected to be stored on ML1)}}{3}$$

If you choose to migrate all files to ML2 (without any going to ML1), then your storage requirements for ML1 will be minimal.

## ML2 Storage Requirements

Because of its low cost, removability, and high capacity, tape should be your primary media for ML2 storage. Using tape as a storage resource frees up DASD space that can be used for ML1. You may migrate some files directly to ML2, bypassing ML1, depending on the management class assigned. Therefore, the minimum amount of space you need for ML2 should at least equal the storage requirements of ML1. However, if the TSM server is set up to use DASD as intermediate storage, plan to have enough DASD to hold the data before it is moved to tape. Some factors to consider are:

- When are operators available to mount tape?
- How long will you keep the data on ML2 DASD?
- Will there be an automated tape library available?

## Other DFSMS/VM Files

You need approximately 500 blocks of storage for DFSMS in the VMSYS file pool to hold the DFSMS/VM control file and other files that DFSMS/VM needs.

## Appendix A. Planning Activities Checklist

- 1. Analyze your system environment. Consider how you can use DFSMS/VM functions on your system in general.
- 2. Ensure your system environment is ready.
  - a. Hardware
  - b. Software

See the *Program Directory for DFSMS/VM Function Level 221* for detailed information about DFSMS/VM software requirements.
- 3. VMSYS file pool established.
- 4. Decide how to manage file pools.
  - a. Choose the file pools to manage.
  - b. Decide on management classes needed. Use Appendix B, "Planning for ACS and Management Classes" on page 29 to record your decisions and file selection criteria.
  - c. Choose method for ACS processing.
- 5. Decide if you want DFSMS/VM to issue accounting records.
- 6. Decide on a method to authorize users. The options are:
  - a. Use function level 530, or an equivalent product.
  - b. Use the authorization file DGTVAUTH DATA, a list of user IDs authorized to be storage administrators.
  - c. Use a security product that uses the RACROUTE MACRO.
  - d. Customize the installation-wide exit FSMVAUTH to use either a security product that does not use the RACROUTE MACRO, or an internally written method.
- 7. Plan for installing DFSMS/VM.
  - a. Decide on the number of server machines to set up for DFSMS/VM.
  - b. Ensure that space required for DFSMS/VM product code and files is available.
    - DFSMS/VM product files
    - Master and server virtual machines minidisks
    - Migration level 1 storage
    - Log files
    - Work directory
  - c. Decide on secondary storage (ML1, or both ML1 and ML2)
    - 1) Choose the location of ML1 (file pool and DASD).
    - 2) Estimate the DASD space needed for ML1.
 

Refer to "ML1 Storage Requirements" on page 25 for information on estimating storage requirements.
    - 3) Name a TSM server, if ML2 is used.
    - 4) Estimate the DASD/tape space needed for ML2.

## Planning Activities Checklist

Refer to “ML2 Storage Requirements” on page 26 for information on estimating storage requirements.

- d. Decide how to log on the master and server virtual machines to start DFSMS/VM. Modify execs, if appropriate.
- e. Use CRR file pool if DFSMS is supporting more than one file pool.
- 8. Schedule time to install and customize DFSMS/VM.
- 9. Order any supporting documentation you may need.

---

## Appendix B. Planning for ACS and Management Classes

The management class assigned to a file is the key to how DFSMS/VM manages that file for you. You need to carefully consider what management classes your system and your users need and how to assign them. You can have as many management classes as you feel are needed to manage your files and it is not necessary to use every field on the work sheet. A sample work sheet is on page 30.

A blank work sheet is also provided for you to record your decisions. You can make as many copies of the work sheet on page 31 as you need. After DFSMS/VM is installed, use the work sheet to define the management classes through the ISMF Management Class Application panel and to help when writing your ACS routine or exit. See “Backing Up and Recovering Migrated Files” on page 24 for more information on coordinating management class definitions with your installation’s backup procedures.

## Sample of a ACS and Management Class Work Sheet

<i>Table 3. Sample of ACS and Management Class Work Sheet</i>			
<b>Field</b>			
Management class name <i>File name:</i> 1–8 characters	ORDRDEPT	BILLING	TEMPREPT
Description 1–120 characters	Customer orders for WRIGHT Products INC.	Customer invoices to be billed	Anyone’s temporary files
Expire after days nonusage <i>Values allowed:</i> 1–9999 NOLIMIT	365	NOLIMIT	NOLIMIT
Expire since creation <i>Values allowed:</i> 1–9999 (days) NOLIMIT	NOLIMIT	NOLIMIT	3
Expiration disposition <i>Values allowed:</i> DATA (only file data is erased) ALL (entire file is erased)	All	All	All
Migrate to ML1 after days of non-usage <i>Values allowed:</i> 0–9999 NOLIMIT	NOLIMIT	14	
Move to ML2 after days on ML1 <i>Values allowed:</i> 0–9999 NOLIMIT	0	10	
Space management technique <i>Values allowed:</i> MIGRATE NONE	MIGRATE	MIGRATE	NONE
ACS Selection Criteria	Any directory with a top-level name of 'WRIGHT' and the lowest-level name of 'ORDER'.	The owner’s name starts with 'PROD' and the file name is not 'PAYROLL'.	The owner’s name does not start with 'PROD' and the file type is 'LISTING' or begins with 'TEMP'.



## ACS and Management Class Work Sheet

<i>Table 4. ACS and Management Class Work Sheet</i>			
<b>Field</b>			
Management class name <i>File name:</i> 1–8 characters			
Description 1–120 characters			
Expire after days nonusage <i>Values allowed:</i> 1–9999 NOLIMIT			
Expire since creation <i>Values allowed:</i> 1–9999 (days) NOLIMIT			
Expiration disposition <i>Values allowed:</i> DATA (only file data is erased) ALL (entire file is erased)			
Migrate to ML1 after days of non-usage <i>Values allowed:</i> 0–9999 NOLIMIT			
Move to ML2 after days on ML1 <i>Values allowed:</i> 0–9999 NOLIMIT			
Space management technique <i>Values allowed:</i> MIGRATE NONE			
ACS selection criteria			



---

## Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, New York 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106-0032, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes to the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Mail Station P300  
2455 South Road  
Poughkeepsie, New York 12601-5400  
U.S.A.  
Attention: Information Request

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities on non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information may contain sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

---

## Programming Interface Information

This book documents information NOT intended to be used as Programming Interfaces of z/VM.

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

DFDSM  
DFSMS/VM  
DirMaint  
eServer  
IBM  
IBMLink  
Magstar  
MVS  
Language Environment  
OpenExtensions  
OS/390  
Performance Toolkit for VM  
RACF  
SAA  
System z  
System z9  
Tivoli  
TotalStorage  
z/OS  
z/VM  
zSeries

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Adobe, Acrobat, PostScript and all Adobe-based trademarks are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.

---

## Glossary

For a list of z/VM terms and their definitions, see the *z/VM: Glossary* book.

The glossary is also available through the online HELP Facility. For example, to display the definition of “cms,” enter:

```
help glossary cms
```

You will enter the glossary HELP file and the definition of “cms” will be displayed as the current line. While you are in the glossary HELP file, you can also search for other terms.

If you are unfamiliar with the HELP Facility, you can enter:

```
help
```

to display the main HELP menu, or enter:

```
help cms help
```

for information about the HELP command.

For more information about the HELP Facility, see the *z/VM: CMS User's Guide*.



---

## Bibliography

This bibliography lists the publications in the IBM® z/VM® product library, and it may list other publications referenced in this publication. For abstracts of z/VM publications and information about current editions and available media, see *z/VM: General Information*.

---

## Where to Get z/VM Publications

z/VM publications are available from the following sources:

- IBM Publications Center at [www.ibm.com/shop/publications/order/](http://www.ibm.com/shop/publications/order/)
- z/VM Internet Library at [www.ibm.com/eserver/zseries/zvm/library/](http://www.ibm.com/eserver/zseries/zvm/library/)
- *IBM Online Library: z/VM Collection (CD-ROM)*, SK2T-2067
- *IBM Online Library: z/VM Collection on DVD*, SK5T-7054

---

## z/VM Base Library

### Overview

- *z/VM: General Information*, GC24-6095
- *z/VM: Glossary*, GC24-6097
- *z/VM: License Information*, GC24-6102

### Installation, Migration, and Service

- *z/VM: Guide for Automated Installation and Service*, GC24-6099
- *z/VM: Migration Guide*, GC24-6103
- *z/VM: Service Guide*, GC24-6117
- *z/VM Summary for Automated Installation and Service (DVD Installation)*, GA76-0406
- *z/VM Summary for Automated Installation and Service (Tape Installation)*, GA76-0407
- *z/VM: VMSES/E Introduction and Reference*, GC24-6130

## Planning and Administration

- *z/VM: CMS File Pool Planning, Administration, and Operation*, SC24-6074
- *z/VM: CMS Planning and Administration*, SC24-6078
- *z/VM: Connectivity*, SC24-6080
- *z/VM: CP Planning and Administration*, SC24-6083
- *z/VM: Getting Started with Linux on System z*, SC24-6096
- *z/VM: Group Control System*, SC24-6098
- *z/VM: I/O Configuration*, SC24-6100
- *z/VM: Running Guest Operating Systems*, SC24-6115
- *z/VM: Saved Segments Planning and Administration*, SC24-6116
- *z/VM: TCP/IP LDAP Administration Guide*, SC24-6140
- *z/VM: TCP/IP Planning and Customization*, SC24-6125
- *eServer zSeries 900: Planning for the Open Systems Adapter-2 Feature*, GA22-7477
- *System z9 and eServer zSeries: Open Systems Adapter-Express Customer's Guide and Reference*, SA22-7935
- *System z9 and eServer zSeries 890 and 990: Open Systems Adapter-Express Integrated Console Controller User's Guide*, SA22-7990
- *z/OS and z/VM: Hardware Configuration Manager User's Guide*, SC33-7989

## Customization and Tuning

- *z/VM: CP Exit Customization*, SC24-6082
- *z/VM: Performance*, SC24-6109

## Operation and Use

- *z/VM: CMS Commands and Utilities Reference*, SC24-6073
- *z/VM: CMS Pipelines Reference*, SC24-6076
- *z/VM: CMS Pipelines User's Guide*, SC24-6077
- *z/VM: CMS Primer*, SC24-6137
- *z/VM: CMS User's Guide*, SC24-6079
- *z/VM: CP Commands and Utilities Reference*, SC24-6081

- *z/VM: System Operation*, SC24-6121
- *z/VM: TCP/IP User's Guide*, SC24-6127
- *z/VM: Virtual Machine Operation*, SC24-6128
- *z/VM: XEDIT Commands and Macros Reference*, SC24-6131
- *z/VM: XEDIT User's Guide*, SC24-6132
- *CMS/TSO Pipelines: Author's Edition*, SL26-0018

## Application Programming

- *z/VM: CMS Application Development Guide*, SC24-6069
- *z/VM: CMS Application Development Guide for Assembler*, SC24-6070
- *z/VM: CMS Application Multitasking*, SC24-6071
- *z/VM: CMS Callable Services Reference*, SC24-6072
- *z/VM: CMS Macros and Functions Reference*, SC24-6075
- *z/VM: CP Programming Services*, SC24-6084
- *z/VM: CPI Communications User's Guide*, SC24-6085
- *z/VM: Enterprise Systems Architecture/Extended Configuration Principles of Operation*, SC24-6094
- *z/VM: Language Environment User's Guide*, SC24-6101
- *z/VM: OpenExtensions Advanced Application Programming Tools*, SC24-6104
- *z/VM: OpenExtensions Callable Services Reference*, SC24-6105
- *z/VM: OpenExtensions Commands Reference*, SC24-6106
- *z/VM: OpenExtensions POSIX Conformance Document*, GC24-6107
- *z/VM: OpenExtensions User's Guide*, SC24-6108
- *z/VM: Program Management Binder for CMS*, SC24-6110
- *z/VM: Reusable Server Kernel Programmer's Guide and Reference*, SC24-6112
- *z/VM: REXX/VM Reference*, SC24-6113
- *z/VM: REXX/VM User's Guide*, SC24-6114
- *z/VM: Systems Management Application Programming*, SC24-6122
- *z/VM: TCP/IP Programmer's Reference*, SC24-6126
- *Common Programming Interface Communications Reference*, SC26-4399

- *Common Programming Interface Resource Recovery Reference*, SC31-6821
- *z/OS: Language Environment Concepts Guide*, SA22-7567
- *z/OS: Language Environment Debugging Guide*, GA22-7560
- *z/OS: Language Environment Programming Guide*, SA22-7561
- *z/OS: Language Environment Programming Reference*, SA22-7562
- *z/OS: Language Environment Run-Time Messages*, SA22-7566
- *z/OS: Language Environment Writing ILC Applications*, SA22-7563
- *z/OS MVS Program Management: Advanced Facilities*, SA22-7644
- *z/OS MVS Program Management: User's Guide and Reference*, SA22-7643

## Diagnosis

- *z/VM: CMS and REXX/VM Messages and Codes*, GC24-6118
- *z/VM: CP Messages and Codes*, GC24-6119
- *z/VM: Diagnosis Guide*, GC24-6092
- *z/VM: Dump Viewing Facility*, GC24-6093
- *z/VM: Other Components Messages and Codes*, GC24-6120
- *z/VM: TCP/IP Diagnosis Guide*, GC24-6123
- *z/VM: TCP/IP Messages and Codes*, GC24-6124
- *z/VM: VM Dump Tool*, GC24-6129
- *z/OS and z/VM: Hardware Configuration Definition Messages*, SC33-7986

---

## Publications for z/VM Optional Features

### Data Facility Storage Management Subsystem for VM

- *z/VM: DFSMS/VM Customization*, SC24-6086
- *z/VM: DFSMS/VM Diagnosis Guide*, GC24-6087
- *z/VM: DFSMS/VM Messages and Codes*, GC24-6088
- *z/VM: DFSMS/VM Planning Guide*, SC24-6089
- *z/VM: DFSMS/VM Removable Media Services*, SC24-6090



- *z/VM: DFSMS/VM Storage Administration*, SC24-6091

## Directory Maintenance Facility for z/VM

- *z/VM: Directory Maintenance Facility Commands Reference*, SC24-6133
- *z/VM: Directory Maintenance Facility Messages*, GC24-6134
- *z/VM: Directory Maintenance Facility Tailoring and Administration Guide*, SC24-6135

## Performance Toolkit for VM™

- *z/VM: Performance Toolkit Guide*, SC24-6156
- *z/VM: Performance Toolkit Reference*, SC24-6157

## RACF® Security Server for z/VM

- *z/VM: RACF Security Server Auditor's Guide*, SC24-6143
- *z/VM: RACF Security Server Command Language Reference*, SC24-6144
- *z/VM: RACF Security Server Diagnosis Guide*, GC24-6145
- *z/VM: RACF Security Server General User's Guide*, SC24-6146
- *z/VM: RACF Security Server Macros and Interfaces*, SC24-6147
- *z/VM: RACF Security Server Messages and Codes*, GC24-6148
- *z/VM: RACF Security Server Security Administrator's Guide*, SC24-6142
- *z/VM: RACF Security Server System Programmer's Guide*, SC24-6149
- *z/VM: Security Server RACROUTE Macro Reference*, SC24-6150

## RSCS Networking for z/VM

- *z/VM: RSCS Networking Diagnosis*, GC24-6151
- *z/VM: RSCS Networking Exit Customization*, SC24-6152
- *z/VM: RSCS Networking Messages and Codes*, GC24-6153
- *z/VM: RSCS Networking Operation and Use*, SC24-6154
- *z/VM: RSCS Networking Planning and Configuration*, SC24-6155

---

## Additional Publications

This section lists other publications that you may find helpful.

*IBM SAA® AD/Cycle® C/370™ V1.2 Programming Guide for LE/370 V1.3*, SC09-1840

*ISPF for VM Dialog Management Guide*, SC34-4009

*Tivoli® Storage Manager for OS/390® Edition: VM Server Program*, GI10-0556

*Tivoli Storage Manager for VM Program Directory*, GI10-0557

*IBM Enhanced 3490E Model F Tape Subsystem Installation, Planning, and Operator's Guide*, GG32-0378

*IBM TotalStorage™ Enterprise Automated Tape Library (3494) Introduction and Planning Guide*, GA32-0448

*IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*, GA32-0449

*IBM Magstar® Virtual Tape Server: Implementation Guide*, SG24-2229

*IBM Magstar 3494 Tape Libraries: A Practical Guide*, SG24-4632

*Lights Out! Advanced Tape Automation Using VM/ESA*, GG24-4347

*IBM Compiler and Library for SAA REXX/370 User's Guide and Reference*, SH19-8160



---

# Index

## A

- accounting records 19
- ACS
  - See automatic class selection (ACS) processing
- active configuration
  - See configuration
- allowing access to DFSMS/VM 15
- analyzing system
  - environment 5
  - machine requirements 5
  - preparing your system 5
  - program requirements 5
- authorization file
  - list of storage administrators 16
  - location 26
  - migrating from DFSMS/VM Function Level 210 15
  - storing 26
- authorizing users
  - choosing storage administrators 15
  - CSL routine FSMVAUTH 15
  - file 16
  - listing storage administrators in a file 16
  - other security facility (not RACF Security Server for z/VM) 16
  - planning user authorizations 15
  - using RACROUTE macro 16
- automatic class selection (ACS) processing
  - assigning management classes 10
  - choosing the method
    - ACS routine 11
    - module exit 11
    - REXX exit 11
  - choosing the process 10
  - determining expiration date 7
  - determining migration frequency 8
  - example of management classes 9
  - frequency of 10
  - identifying file expiration requirements 7
  - identifying file migration requirements 8
  - language 11
  - methods of 11
  - null management class 10
  - through ISMF 11
  - using the DFSMS CONVERT command 13
  - using the DFSMS MANAGE command 13
  - z/OS, compatibility with DFSMS/VM 11
- automatic logon of DFSMS/VM virtual machines 19

## B

- backup of secondary storage
  - CSL routines 24
  - FILEPOOL BACKUP command 24
  - FILEPOOL RESTORE command 24
  - if you have another method 24
  - migrated files 24
- backup, exit to check for 13

## C

- calculating ML1 requirements 26
- categories, of DFSMS/VM messages 20
- checking minidisks 1
- checklist for planning activities 27
- choosing secondary storage location, example 21
- choosing SFS file pools 6
- choosing the ACS method 11
- choosing the file pool for ML1 20
- CMS product 5
- commands
  - See DFSMS/VM commands
- configuration
  - automatic class selection processing 10
  - defining management classes 8
- control file
  - changing defaults 17
  - location 26
  - storing 26
- controlling access to DFSMS/VM 15
- controlling file migration and erasure (expiration) 12
- CONVERT command
  - assigning management classes 13
  - placing files under DFSMS/VM Function Level 221 control 13
- Coordinated Resource Recovery 23
- CSL routines
  - backup and recovery process 24
  - FSMMECHK 13
  - FSMVAUTH (authorizing users) 15

## D

- DASD requirements
  - calculating ML1 requirements 26
  - DFSMS/VM product code 25
  - migration level 1 25
  - migration level 2 26
  - other DFSMS/VM files 26
  - virtual machines 25
- data files, storing 26

- data mover 1
- defining management classes 8
- determining storage requirements 25
- DFSMS control file
  - See control file
- DFSMS/VM commands
  - ACS processing 10
  - assigning management classes 13
  - controlling file migration and erase 12
  - CONVERT 13
  - MANAGE 12, 13
  - MANAGE command processing 12
  - minimizing effects on system 12
  - processing time 12
  - telling DFSMS/VM to migrate and erase files 12
- DFSMS/VM control file
  - See control file
- DGTVAUTH DATA file
  - See authorizing users
- DGTVCNTL DATA file
  - See control file
- DIRCONTROL directory 6
- directory maintenance software 5
- DirMaint software 5
- disposition of expired files 7

**E**

- environment, system 5
- erasing expired files 7
- erasure of expired of files, controlling 12
- error, message category 20
- examples of
  - choosing secondary storage location 21
  - management class work sheet 30
  - management classes 9
- exit
  - See installation-wide exit
- expired files
  - choosing which ones are 7
  - criteria of 7
  - erasing 7
  - erasing files, controlling 12
  - erasing only file data 7

**F**

- file expiration (erasure), controlling 12
- file migration, controlling 12
- file pool management 6
- FILECONTROL directory 6
- FILEPOOL BACKUP command 24
- FILEPOOL RESTORE command 24
- files created before installation of DFSMS/VM Function Level 221, placing 13

- files without management classes, converting 13
- files, erasing expired 7
- files, migrating low-activity 7
- FSMMECHK CSL routine 13
- FSMVAUTH CSL routine 15
- functions of DFSMS/VM 1

## G

- global file pool, for ML1 23
- glossary information 35

## H

- how should files be managed 6

## I

- identifying file space 22
- informational, message category 20
- installation of DFSMS/VM Function Level 221
  - choosing file pool for ML1 20
  - Coordinated Resource Recovery 23
  - DFSMS/VM control file default verification 17
  - logging DFSMS/VM messages 20
  - migrating from previous releases 3
  - other DFSMS/VM files 26
  - placement of log files 20
  - product code placement 25
  - setting up virtual machines 17
  - space for virtual machines 25
  - starting DFSMS/VM 19
  - storage requirements 25
  - using VMSES/E to obtain requirements 25
- installation-wide exit
  - accounting 19
  - ACS module exit 11
  - ACS REXX exit 11
  - backup, to check for 13
  - erasure, to check for 13
  - FSMMECHK 13
  - FSMVAUTH (authorizing users) 15, 16
  - migration 13
  - security facility (not RACF Security Server for z/VM) 16
- Interactive Storage Management Facility
  - entry panels 2
  - functions of 2
  - list panels 2
- ISMF
  - See Interactive Storage Management Facility
- ISPF software 5

## L

- language, for ACS routine 11

- limiting access to DFSMS/VM commands 15
- local file pool, for ML1 22
- location of ML1 20
- logging messages
  - categories of 20
  - control file keywords 20
  - placement considerations 20
  - severity of 20
- logon of DFSMS/VM virtual machines 19
- low-activity files 6
- low-activity files, migrating 7

## M

- machine requirements 5
- MANAGE command
  - assigning management classes 12
  - controlling migration and erasure 12
  - expiring files 12
  - placing files under DFSMS/VM Function Level 221
    - control 13
  - threshold levels 12
  - using LEVELS option 12
- management class
  - assigning with ACS processing 10
  - changing with ACS processing 10
  - choosing the ACS method
    - ACS routine 11
    - module exit 11
    - REXX exit 11
  - choosing the ACS process 10
  - defining 8
  - examples of 9
  - expiration of files 7
  - files created before DFSMS/VM 13
  - naming considerations 9
  - null management class 10
  - planning ACS selection 29
  - sample work sheet 30
  - setting up management classes 29
  - work sheet 31
  - working with users 8
- managing SFS file space 1
- master virtual machine
  - general description 17
- message categories, logging 20
- message severity, logging 20
- messages
  - categories of 20
  - control file keywords 20
  - severity of 20
- migrating files
  - cause of failure 23
  - controlling 12
  - working with users 8

- migrating from DFSMS/VM Function Level 210 15
- migration
  - controlling 12
  - low-activity files 7
  - MANAGE command 7
- migration level options 12
- minidisk management
  - move and check function 18
  - virtual machines 18
- minidisk management, functions of 1
- minimizing effects of MANAGE commands on system 12
- ML1 storage requirements 25
- ML2 storage requirements 26
- module exit, ACS 11
- moving minidisks 1

## N

- naming management classes 9
- null management class 10

## P

- PDF 5
- placing DFSMS/VM data files 26
- placing DFSMS/VM product code 25
- planning tasks
  - activities checklist 27
  - analyzing environment 5
  - authorizing users 15
  - backing up and recovering migrated files 24
  - choosing SFS files pools to manage 6
  - defining management classes 8
  - file management
    - erasing files 7
    - migrating files 7
    - naming management classes 9
  - how should files be managed 6
  - installation of DFSMS/VM 17
  - location of ML1 20
  - overview 3
  - placement of log files 20
  - preparing your system 5
  - restrictions, managing files 6
  - storage requirements 25
- preparing your system
  - machine requirements 5
  - program requirements 5
  - security requirements 5
- preventing file migration to secondary storage 23
- programming interface information 34
- programming requirements 5
- protecting DFSMS/VM commands 15

## R

- RACF for VM
  - creating discrete profiles 15
  - defining profiles 15
  - entities 16
  - names for resources in DFSMS/VM 16
  - providing security for DFSMS/VM 15
  - using with DFSMS/VM 5
- RACROUTE macro 16
- recommended log on process 19
- recovery of secondary storage
  - See backup of secondary storage
- removal media services
  - accounting records 19
  - functions of 2
  - logging of messages 20
- requirements for DFSMS/VM
  - DASD 25
  - machine 5
  - other programs 5
  - program 5
  - storage 25
  - tape library support 5
- restrictions, managing files with DFSMS/VM 6
- REXX exit, ACS 11

## S

- secondary storage
  - DASD space required for ML1 25
  - global file pool for ML1 23
  - identifying file space 22
  - local file pool 22
  - restriction on placing 21
  - specifying no file space for 23
- server virtual machine
  - changing number 18
  - deciding on number needed 18
  - default 18
  - general description 17
- setting up a virtual machine for ML2 18
- setting up virtual machines for DFSMS/VM 17
- severe, message category 20
- SFS
  - See Shared File System
- Shared File System
  - file pool management 6
  - space management function 1
- SMS function, virtual machines 18
- software
  - CMS Utilities Feature 5
  - migration level 2 support 5
  - PDF 5
  - requirements for DFSMS/VM 5
  - REXX Compiler 5

- software (*continued*)
  - security 5
  - tape library support 5
- source configuration
  - See configuration
- space management, functions of 1
- specifying no file space for ML1 23
- specifying no file space for secondary storage 23
- starting DFSMS/VM 19
- storage requirements
  - calculating ML1 requirements 26
  - DFSMS/VM product code 25
  - migration level 1 25
  - migration level 2 26
  - other DFSMS/VM data files 26
  - using VMSES/E to determine 25
- storing data files 26
- summary of functions of DFSMS/VM 1
- system environment 5

## T

- threshold levels
  - controlling MANAGE command 12
  - levels of 12
  - MANAGE command processing 12
- Tivoli Storage Manager
  - programming support 5
  - storage repository 18

## V

- virtual machine
  - changing number of servers 18
  - defining master and server machines 18
  - determining storage requirements 25
  - DFSMS/VM usage 17
  - for SFS file management operations 18
  - logging on to start DFSMS/VM 19
  - master 17
  - minidisk management operations 18
  - product code requirements 25
  - server 17
  - setting up, for DFSMS/VM 17
  - setting up, for ML2 18
  - used by DFSMS/VM 17
- VMSYS file pool
  - size requirements 26

## W

- warning, message category 20
- which SFS file pools to manage 6
- work sheets
  - checklist for planning activities 27
  - management class 30, 31



---

# Communicating Your Comments to IBM

z/VM  
DFSMS/VM Planning Guide  
version 5 release 3  
Publication No. SC24-6089-01

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM. Whichever method you choose, make sure you send your name, address, and telephone number if you would like a reply.

Feel free to comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. However, the comments you send should pertain to only the information in this manual and the way in which the information is presented. To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

If you are mailing a readers' comment form (RCF) from a country other than the United States, you can give the RCF to the local IBM branch office or IBM representative for postage-paid mailing.

- If you prefer to send comments by mail, use the RCF at the back of this book.
- If you prefer to send comments by FAX, use this number:
  - United States and Canada: 1-845-432-9405
  - Other Countries: +1 845 432 9405
- If you prefer to send comments electronically, use this network ID:  
mhvrcfs@us.ibm.com

Make sure to include the following in your note:

- Title and publication number of this book
- Page number or topic to which your comment applies.



---

# Readers' Comments — We'd Like to Hear from You

z/VM

DFSMS/VM Planning Guide  
version 5 release 3

Publication No. SC24-6089-01

**Overall, how satisfied are you with the information in this book?**

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

**How satisfied are you that the information in this book is:**

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

**Please tell us how we can improve this book:**

Thank you for your responses. May we contact you?  Yes  No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

\_\_\_\_\_  
Name

\_\_\_\_\_  
Address

\_\_\_\_\_  
Company or Organization

\_\_\_\_\_  
Phone No.




Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES



# BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
MHVRCFS, Mail Station P181  
2455 South Road  
Poughkeepsie, New York 12601-5400



Fold and Tape

Please do not staple

Fold and Tape





Program Number: 5741-A05



Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

SC24-6089-01





z/VM

# DFSMS/VM Planning Guide