

SoftCopy Librarian



User's Guide

V4.2 for Windows

SoftCopy Librarian



User's Guide

V4.2 for Windows

Sixteenth Edition (July 2007)

This edition applies to Version 4.2 of the IBM SoftCopy Librarian (SCL) and to all subsequent releases and modifications until otherwise indicated in new editions.

This edition replaces GC23-3414-14.

© **Copyright International Business Machines Corporation 1997, 2007. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates.

Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, 500 Columbus Avenue Thornwood, NY 10594, U.S.A.

Trademarks

The following terms, denoted by an asterisk (*), in this publication are trademarks or service marks of the IBM Corporation in the United States or other countries or both.

IBM
IBMLink
MVS/ESA
OS/390
S/390
VM/ESA
z/OS

The following terms, denoted by a double asterisk (**), in this publication, are trademarks or service marks of other companies.

Java is a trademark of Sun Microsystems, Inc.

Microsoft, Windows, Windows 2000, and Windows XP are trademarks or registered trademarks of the Microsoft Corporation in the United States and other countries.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Contents

Notices	v
Trademarks	v
About This Book	xi
What's Changed in This Book	xi
Publishing History	xi
Changes Made in the Sixteenth Edition	xii
Changes Made in Previous Editions	xii
Chapter 1. Introducing the SoftCopy Librarian	1
What the SoftCopy Librarian Can Do for You	1
Some Terms You Should Know	3
Overview of Setting Up the SoftCopy Librarian	4
Overview of Using the SoftCopy Librarian	4
Chapter 2. Hardware and Software Requirements	5
Hardware and Software Requirements for Your Workstation	5
Hardware and Software Requirements for Your OS/390 or z/OS Host Repository	5
Hardware and Software Requirements for a Unix-like Repository	6
Hardware and Software Requirements for Your PC or LAN Repository	6
Chapter 3. Planning for Your Repositories	7
What Does the SoftCopy Librarian Manage?	7
How Many Repositories Might I Need?	7
Where Can I Locate My Repositories?	8
What Information Must I Gather before I Can Define a Repository	8
Take the Next Step	9
Chapter 4. Installing the SoftCopy Librarian	11
Locating the SoftCopy Librarian installation package	11
Determining If a Later Version Is Available for Download	11
Checking for a Later Version Automatically	11
Checking for a Later Version Manually	12
Installing the SoftCopy Librarian on a Windows Workstation	12
Chapter 5. Starting the SoftCopy Librarian	15
Starting the SoftCopy Librarian From a Windows Workstation	15
How You Can Use the SoftCopy Librarian Main Window	16
The Menu Bar	16
Using the Windows	18
The SCL - Getting Started Window	18
The Messages Window	18
The Sources and Repositories Window	18
The Source - source-name Window	19
The Repository - repository-name Window	21
What to Do Next	24
Chapter 6. Setting Up Your Connection to the Internet	25
Setting Up an Internet Connection	25

Chapter 7. Migrating from Previous Versions of the SoftCopy Librarian	27
Migrating from V3.x to V4.1	27
Migrating from V3.x to V4.2	28
Migrating from V4.1 to V4.2	28
Chapter 8. Setting Up a z/OS or OS/390 Host Repository Using Sequential Data Sets	29
Considerations for Setting Up Your Repository Using Sequential Data Sets	29
Setup Required at Your z/OS or OS/390 Host	30
Defining a z/OS or OS/390 Host Repository	30
Chapter 9. Setting Up a z/OS or OS/390 Host Repository Using the Unix System Services HFS	35
Considerations for Setting Up a Repository in Hierarchical Files	35
Information You Must Gather about Your Repository	36
Defining a z/OS or OS/390 UNIX System Services Host Repository	36
Chapter 10. Setting Up a Unix-like Repository	39
Considerations for Setting Up Your Repository	39
Defining a Unix Server Repository	39
Chapter 11. Setting Up a PC/LAN Repository	43
Considerations for Setting Up Your Repository	43
Setup Required for Your Repository	43
Defining a PC or LAN Server Repository	43
Chapter 12. Creating and Recreating the Catalog for Your Repository	47
Updating Your Catalog Automatically	47
Creating or Recreating the Catalog Manually	48
When and How to Erase the Cache That the SoftCopy Librarian Uses	49
Chapter 13. Identifying the Sources of Bookshelves That You Want to Transfer	51
Identifying a CD Reader or Hard Drive as the Source for Bookshelves	51
Chapter 14. Maintaining Your Repositories	53
Transferring Shelves to a Repository	53
Maintaining a Repository	55
Maintaining a Repository	55
Replacing or Excluding Associated Files	57
Replacing Missing Books	57
Excluding Missing Books	58
Removing Orphaned Associated Publications	58
Cloning a Repository (Not Available)	59
Synchronizing Repositories (Not Available)	60
Chapter 15. Creating/Managing Your Own Softcopy and Associated Publications	61
Naming Your Files So the SoftCopy Librarian Can Manage Them	61
Background	61
How Files Are Named	61
What If Your Old Shelf Names Do Not Work with the New Conventions	63
Creating an Exception File	63
Creating Your Own Shelves and Books with BookManager	65

Appendix A. Permitting More Than One Person to Maintain Your Repositories	67
Appendix B. Changing the Definition of Your Repository	69
Changing the Attributes of Your Repository	69
Appendix C. Deleting a Repository	71
Appendix D. Managing Changes to Your Repository	73
Unloading or Copying Softcopy Files from Tape or other Sources	73
Shelf Changes in Your Repository	73
Appendix E. Summary of Changes Made in Previous Editions	75
Changes made to the Sixteenth Edition	75
Changes made to the Fifteenth Edition	75
Changes made to the Fourteenth Edition	75
Changes made to the Thirteenth Edition	75
Changes made to the Twelfth Edition	75
Changes Made in the Eleventh Edition	75
Changes Made in the Tenth Edition	76
Changes Made in the Ninth Edition	76
Changes Made in the Eight Edition	76
Changes Made in the Seventh Edition	76
Changes Made in the Sixth Edition	76
Changes Made in the Fifth Edition	77
Changes Made in the Fourth Edition	77
Changes Made in the Third Edition	77
Changes Made in the Second Edition	78
Index	79
Do You Have Questions, Problems, or Comments?	81

About This Book

This book describes how to set up and use IBM SoftCopy Librarian. The SoftCopy Librarian (SCL, program number 5648-032) lets you transfer shelves, Books, PDFs and other publications to a repository and manage them there. One or more repositories can be set up on:

- A z/OS host running IBM TCP/IP FTP
- An OS/390 host running IBM TCP/IP FTP
- A Unix-like server, accessible through FTP
- A LAN hard drive, accessible using Copy commands
- A local PC hard drive, accessible using Copy commands

The SoftCopy Librarian runs on a Windows 2000 or XP workstation.

To use the SoftCopy Librarian, you would do the following:

1. Set up at least one repository for softcopy files that you want to manage.
2. Create a catalog for that repository.
3. Transfer files from a CD, from a local hard drive on your workstation, from the IBM PUBLIB Web site, or from any other Web site that can support the SoftCopy Librarian.

When you transfer files from any of these sources to your repository, the SoftCopy Librarian compares what you want to transfer with the catalog.

4. The SoftCopy Librarian then lists the items that you do not have in your repository and the items that have changed since the last time you updated the repository.
5. You can select and transfer only those items that you do not have or that have been updated.

The SoftCopy Librarian lists everything that is in your repository and lets you delete objects that have been replaced or that are no longer needed.

What's Changed in This Book

This section summarizes the major changes made in the current edition of the *SoftCopy Librarian: User's Guide*.

Publishing History

The following table shows the publication history of this manual:

Table 1. Publication History

Product Version/Release Service Level	Book		
	Edition	Date	Order Number
V4.2	Sixteenth	July, 2007	GC23-3414-15
V4.2	Fifteenth	September, 2004	GC23-3414-14
V4.2	Fourteenth	June, 2004	GC23-3414-13
V4.2	Thirteenth	October, 2003	GC23-3414-12
V4.2	Twelfth	August, 2003	GC23-3414-11
V4.1	Eleventh	December, 2002	GC23-3414-10
V4.1	Tenth	July, 2002	GC23-3414-09
V4.1	Ninth	September 2001	GC23-3414-08
V4.0C	Eight	March 2001	GC23-3414-07
V3.5B	Seventh	September 2000	GC23-3414-06
V3.5	Sixth	June 2000	GC23-3414-05
V3.4	Fifth	December 1999	GC23-3414-04
V3.2D	Fourth	September 1999	GC23-3414-03
V3.2	Third	June 1999	GC23-3414-02
V3.1	Second	March 1999	GC23-3414-01
V3.0	First	September 1998	GC23-3414-00

The current edition is listed **first**.

Changes Made in the Sixteenth Edition

New Information

Updated the IBM Web site for downloading the latest version of SoftCopy Librarian. Also included are miscellaneous editorial updates.

Changes Made in Previous Editions

For a summary of the changes made in the previous editions of this book, refer to Appendix E.

Chapter 1. Introducing the SoftCopy Librarian

This chapter introduces and summarizes:

- What the IBM SoftCopy Librarian can do for you
- How to install the IBM SoftCopy Librarian
- How to set up a repository
- How to create a catalog for your repository
- How to upload shelves and books
- How to maintain your repository

What the SoftCopy Librarian Can Do for You

The IBM SoftCopy Librarian V4.2 provides you with the ability to manage softcopy shelves and associated publications. These can either be provided by IBM or built using the IBM BookManager shelf architecture and BookManager Build or Builder application for softcopy publications.

The SoftCopy Librarian provides these capabilities:

- Manages the following types of BookManager files and file types (MVS and Local Unix)
 - Books (BOOK and .BOO files)
 - Shelves (BKSHELF or .BKS files)
 - Extended Shelves (XKSHELF or .XKS files)
 - Shelf Indexes (BKINDEX or .BKI files)
 - PDFs (PDF files)
- Active Management, in addition to transferring files, also includes:
 - Maintaining a catalog of the contents for each of your repositories
 - Comparing what's currently in your repositories with new sources of shelves, Books, PDFs and other publications
 - Providing you with the comparative status of the items in the source in relation to the contents of your current repositories
 - Updating the catalogs whenever you transfer new shelves, Books, PDFs and other publications to your repositories
 - Identifying items in your repositories that can be removed because there are newer versions of these items also in your repositories
- Set up and maintain repositories using a variety of sources. You can obtain and transfer shelves and associated publications from:
 - CD collections from IBM
 - OEM (Original Equipment Manufacturers) CD Collections
 - The IBM PUBLIB Web site (over the Internet)
 - A local hard disk
 - Other Web sites (that provide support for the SoftCopy Librarian)

Note: In general, using the Internet to obtain shelves and associated publications from IBM might be slower than using CDs. We recommend that you use the IBM CD-ROM collections for the normal quarterly refreshes, and use the Internet only for updating your repositories between quarters with latest releases.

- Tracking of New and Updated shelves and associated publications

The SoftCopy Librarian keeps a catalog of all the shelves and associated publications that you send to your repository from any level of a CD, from your local hard drive, from the IBM PUBLIB Web site, or any other Web site that supports the SoftCopy Librarian. When a new level of a shelf arrives, on a new CD or downloaded from a Web site, the SoftCopy Librarian compares it and its contents with the catalog and shows you whether it's brand new or whether it's changed since the last level you received. You now have a way to see at a glance which shelves on a CD or on a supported Web site are currently in your host repository.

- Support for OS/390 and z/OS Repositories

The SoftCopy Librarian supports repositories in sequential data sets. You can use BookManager READ/MVS to access the books, shelves and other publications on your OS/390 or z/OS host. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.
- BookManager READ/MVS requires service for APAR PQ75262 when, or before you upload extended shelves (XKS files).

- Support for OS/390 and z/OS Unix System Services Repositories

The SoftCopy Librarian supports repositories in either hierarchical file systems or sequential data sets. You can use BookManager BookServer for z/OS or OS/390, or Library Server for z/OS V1R5 to access the books, shelves and other publications on your z/OS or OS/390 host or server. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.

- Support for Unix-like Repositories

The SoftCopy Librarian supports repositories on Unix-like servers. You can use BookManager BookServer/Library Center for AIX to access the books, shelves, PDFs and other publications on your Unix-like server. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.

- Support for PC/LAN Repositories

The SoftCopy Librarian supports repositories on LAN server or local personal computer hard drives that can be accessed as a drive letter on Windows systems. The drive must be a valid target for a Copy command. You can use the BookManager Softcopy Reader to access the shelves, books, PDFs and other publications on your LAN server or PC workstation.

- Support for PDF files

The SoftCopy Librarian supports PDF files and Extended Shelves to organize them, obtained from either the "PUBLIB" web site, or the Collection "CD."

- READ/MVS requires service for APAR PQ75262, if you place extended shelves in a z/OS or PS/390 sequential dataset repository.

- Managing Your Own and Other Manufacturer's Books, PDFs, and other publications

The SoftCopy Librarian will let you track shelves, Books, PDFs and other publication that you create or that you might receive with product from companies other than IBM.

Note: CD Collections of softcopy shelves and associated publications from others - OEM (Original Equipment Manufacturers) - must be built using the IBM BookManager shelf architecture (for shelves containing books), or the extended shelf architecture (for shelves containing PDFs) and BookManager Build or builder application for the softcopy publication. Use IBM BookManager Softcopy Reader or Shelf Organizer to build extended shelves.

- Available on all IBM Online Library CDs and from the IBM Web Site

The SoftCopy Librarian is available, at no cost, on all IBM Online Library collections and on other IBM product CDs.

The latest version of the SoftCopy Librarian is also available and can be downloaded from the following IBM Web site:

<http://www-306.ibm.com/software/applications/office/bkmgr/librarian.html>

Some Terms You Should Know

Here are some SoftCopy Librarian terms with which you should become familiar:

Source. Is the place from where you can obtain the shelves and associated publications that you want to place into your repositories. Sources can include:

- CD drive for CD collections from IBM or other manufacturers
- The Internet for connection to IBM's online library or other online libraries
- A local hard drive or server for shelves and associated publications you can create

Repository. Is the place where your softcopy items are stored. During SoftCopy Librarian setup, you specify where the repository is located and how to access it. You can define multiple repositories in these locations:

- OS/390 or z/OS host sequential data sets - identified by a high-level qualifier
- OS/390 or z/OS Unix System Services hierarchical file system - identified by an HFS directory,
- A Unix-like server - identified by a Unix-like directory
- A hard drive on a local PC or LAN server - identified by a PC directory

Catalog. Is a SoftCopy Librarian file that lists the softcopy items contained in a SoftCopy Librarian repository. You can create a catalog when you set up a new, empty repository. However, the catalog is automatically updated every time you use the SoftCopy Librarian to update your repository. The SoftCopy Librarian builds a catalog by querying the contents of the directory or the high-level qualifier (HLQ) specified during the setup of the repository and then builds the catalog information.

Overview of Setting Up the SoftCopy Librarian

In general, the steps that you must plan for are:

- 1** Determine whether your hosts and workstations meet the hardware and software requirements for using the SoftCopy Librarian. Refer to Chapter 2.
- 2** Install the SoftCopy Librarian on your workstation. Refer to Chapter 4.
- 3** Set up one or more repositories. For OS/390 or z/OS repositories in sequential data sets, refer to Chapter 8.
For OS/390 or z/OS repositories in OS/390 or z/OS Unix System Services hierarchical files, refer to Chapter 9.
For a Unix-like repositories, refer to Chapter 10.
For a PC or LAN repositories, refer to Chapter 11.
- 4** Create a catalog for each repository. Refer to Chapter 12.
- 5** Transfer shelves and associated publications to your repositories. Refer to Chapter 14.
- 6** Maintain the repositories by identifying, replacing and/or deleting softcopy items. Refer to Chapter 14.

Overview of Using the SoftCopy Librarian

After you have installed and set up the SoftCopy Librarian, you can use it to help you:

- Compare the contents of any source (that is, a CD you received, the contents of a supported Web site, or the hard drive of a server) with the catalog for any of your repositories.

This comparison will show you which shelves, Books, PDFs and associated publications on that source are new, updated, installed, partial, or downlevel.

- Upload only new, updated, or partial shelves to your repository.

This saves you time and DASD space and still keeps your repository up to date. The catalog is updated automatically whenever you upload to the repository.

- Maintain your host repository.

The SoftCopy Librarian shows you which shelves in your repository can be replaced by the new and updated ones that you just transferred.

You can:

- List the Books, PDFs or other publications in a Shelf
- See which Books, PDFs or other publications if any, are missing from any of the shelves
- See which Books, PDFs, and other publications are “orphaned,” that is, not in any shelf.

All this makes it easy for you to delete the shelves, Books, PDFs or other publications that have been replaced or are no longer needed.

Chapter 2. Hardware and Software Requirements

This Chapter describes the hardware and software required to install and use the SoftCopy Librarian on your hosts and workstations.

Hardware and Software Requirements for Your Workstation

This section describes the software and hardware requirements for the workstation on which you will do the following:

- Install the SoftCopy Librarian.
- Create a catalog of softcopy that resides in your repositories.
- Transfer softcopy shelves, Books, PDFs and other publications to your repository.

It must have the following hardware and software:

A workstation that consists of:

- A 1GHz equivalent or faster processor.
- One of the following operating systems:
 - Windows 2000 or XP
- To use OS/390 or z/OS repositories, a TCP/IP link that supports FTP communications with your host.
 - Current support is for IBM TCP/IP FTP only.
- To use LAN server repositories, a network connection which allows you to access the LAN server as a drive letter.
- To use local PC repositories, no additional requirements.
- To use CD-ROM collections as a source, a CD-ROM drive.
- To use the Internet as a source or to check for updates to the SoftCopy Librarian, an Internet connection.
- A minimum of 100MB of space on your hard drive.

Hardware and Software Requirements for Your OS/390 or z/OS Host Repository

This section describes the software and hardware requirements for an OS/390 or z/OS host on which you will maintain one or more softcopy repositories.

Your host must have the following hardware and software:

A Host system that consists of:

- One of the following operating systems:
 - z/OS
 - OS/390
 - MVS
- A TCP/IP link that supports FTP communications from your workstation

Current support is for IBM TCP/IP FTP only.

Your destination host must be inside your firewall, the SoftCopy Librarian does not provide proxy support for this transfer.

- Sufficient DASD space for the shelves, Books, PDFs and other publications that will reside in your repositories.
- If you plan to:
 - Use sequential dataset repositories, and
 - store extended shelves in them, and
 - allow your users to use READ/MVS

Then you must install service for READ/MVS APAR PQ75262, to prevent READ/MVS from listing Extended Shelves in its List of Shelves (READ/MVS does not currently support extended shelves).

Hardware and Software Requirements for a Unix-like Repository

This section describes the software and hardware requirements for a Unix-like server on which you will maintain one or more softcopy repositories.

Your server must have the following hardware and software:

- One of the following operating systems:
 - AIX
 - Linux
 - Any other Unix type operating system
- A TCP/IP link that supports FTP communications from your workstation

Current support is for IBM TCP/IP FTP only.

Your destination server must be inside your firewall, the SoftCopy Librarian does not provide proxy support for this transfer.

- Sufficient DASD space for the shelves, Books, PDFs and other publications that will reside in your repositories.

Hardware and Software Requirements for Your PC or LAN Repository

This section describes the software and hardware requirements for a PC or LAN on which you will keep your softcopy repositories.

- You must be able to access the repository's directory as a drive letter.
- Sufficient DASD space for the shelves, Books, PDFs and other publications that will reside in your repositories.

If you meet the requirements for installing and using the SoftCopy Librarian, when you are ready, you can continue with the information in Chapter 3 to help plan your repositories.

Chapter 3. Planning for Your Repositories

This chapter discusses what you will need to know and some of the decisions that you must make in preparation for setting up your own repositories of shelves, Books, PDFs and other publications.

Note: In addition to, or instead of, setting up your own repositories, you can access the IBM Online Library on the Internet at this URL:

<http://www.ibm.com/shop/publications/order>

You need only a browser to access the entire z/OS, OS/390, z/VM, VM, and VSE libraries.

What Does the SoftCopy Librarian Manage?

The SoftCopy Librarian actively manages the following types of files:

- BookManager files and file types (MVS and Local UNIX)
 - Books (BOOK or .BOO files).
 - Shelves (BKSHELF or .BKS files).
 - Extended Shelves (XKSHELF or .XKS files).
 - Shelf indexes (BKINDEX or .BKI files).
- PDFs (PDF files).

Active management involves not just transferring files to your repositories, it also includes:

- Maintaining a catalog of the contents for each of your repositories.
- Comparing what's currently in your repositories with new sources of shelves, Books, PDFs and other publications.
- Providing you with the comparative status of the items in the source in relation to the contents of your current repositories.
- Updating the catalogs whenever you transfer new shelves, Books, PDFs and other publications to your repositories.
- Identifying items in your repositories that can be removed because there are newer versions of these items also in your repositories.

How Many Repositories Might I Need?

The simplest arrangement is one repository that anyone can access. You must define at least one repository for the SoftCopy Librarian to function.

You might need more than one repository depending upon several factors, which can include:

- All your users do not have access to the same host or server.
- Even if they are on the same host they may not have access to the same LPAR.

- You have a large number of Books, PDFs and other publications that are easier to manage in unique sets, for example, IBM and non-IBM.
- If you are migrating from one version or release of a system to another, you might want to keep the Books, PDFs and other publications in separate repositories to make it easier to delete the older set.
- If you are running a test release of your system along with your production release, you might want to keep the two separate from each other.

Where Can I Locate My Repositories?

You can set up one or more host repositories of softcopy shelves, Books, PDFs and other publications in any of the following places:

- On z/OS or OS/390 hosts:
 - In sequential data sets
 - In the hierarchical files (HFS) of Unix System Services
- On Linux, AIX or other Unix-like servers
- On LAN servers
- On local workstations

What Information Must I Gather before I Can Define a Repository

You must provide the following information when you define your repository:

- The arrangement of your repositories.
 - How many you plan to have
 - What they will contain
 - Where they will be located
- **For all repositories:** A name for each new repository.
Note: This name can be anything you want. It is the name that the SoftCopy Librarian uses on your workstation to identify your repositories.
- **For host and Unix-like repositories only:** The name or IP address and the user ID and password you use to access your host or server.
- **For all repositories:** High-level qualifiers or directories, which will contain these files:
 - Book (.BOOK or .BOO)
 - Index (.BKINDEX or .BKI)
 - PDF (.PDF)
 - Shelves (BKSHELF or .BKS)
 - Extended Shelves (.XKSHELF or .XKS)

Note: **High Level Qualifiers** and directories can be used for all file types.

Note: **For host repositories in sequential data sets only:** Your shelves and books do not require unique HLQs. For example, if your BookManager code is installed under IBMBK, then the shelves and related publications could be installed under IBMBK.SOFTCOPY.

- **For host repositories in sequential data sets only**
 - A high-level qualifier for the SoftCopy Librarian's shelf list.
 - The type of DASD device you are using
 - The block size for that DASD device (provided)
 - The volume in which the data sets will reside
 - **For SMS users only:** The applicable data, management, and storage classes that you are using
- **For host, Unix-type, and LAN server repositories only** Any FTP commands required by your location to transfer the shelves and associated publications from the workstation to your host or server.

Take the Next Step

When you are ready to create your repositories, continue with the instructions in Chapter 8, Chapter 9, Chapter 10, or Chapter 11.

Chapter 4. Installing the SoftCopy Librarian

This chapter describes:

- Where you can find the SoftCopy Librarian installation package.
- How to determine which version is available for download.
- How to determine whether an updated version is available.
- How to install the SoftCopy Librarian on Microsoft Windows 2000 or XP workstation.

Locating the SoftCopy Librarian installation package

The installation package is located on the CD-ROM containing tools, which is part of the IBM Online Library collections. The package is also located on the DVD, which is part of the IBM Online Library DVD collections. The package, in a file named EBRSCWJ.EXE, is in the SCL directory.

`\SCL\EBRSCWJ.EXE`

The latest version of the install package for Windows is also available at this Web address:

<http://www.ibm.com/software/applications/office/bkmgr/librarian.html>

Determining If a Later Version Is Available for Download

From time-to-time, an updated version of the SoftCopy Librarian is made available for download from the IBM SoftCopy Librarian Web site. If you are using a Windows workstation, you can check automatically or manually if a later version than the one you currently have installed on your workstation is available. You might want to do either of these checks occasionally.

Checking for a Later Version Automatically

To check automatically, do the following:

- 1** On the SoftCopy Librarian's menu bar, select Help.
- 2** In the Help pull-down menu, select Check for Updates (automatic).
The Check for Updates (automatic) choice will compare the version that you have installed with the version that is currently available at the IBM PUBLIB Web site.
- 3** If there is a later version available at the Web site, you will be asked if you want to download it. If you do, click **OK**.
If you choose to download it, you will also be asked if you want to install it.
- 4** If you want to install the new version, click **OK**.
If you choose to install it, follow the instructions in "Installing the SoftCopy Librarian on a Windows Workstation" on page 12.

Note: If, because of your firewall, the SoftCopy Librarian cannot perform the automatic check, you can use the manual check described below.

Checking for a Later Version Manually

To check manually, do the following:

- 1** Locate the Check for Updates (manual) choice. Do one of the following:
 - **From the Windows Start Menu:**
 - a. Go to the Start menu.
 - b. Select Programs.
 - c. From the Programs menu, select IBM SoftCopy Librarian V4.
 - d. From the Service menu, select Check for Updates (manual).
 - **From the SoftCopy Librarian Help Menu:**
 - a. On the SoftCopy Librarian's menu bar, select Help.
 - b. In the Help pull-down menu, select Check for Updates (manual).

The Check for Updates (manual) choice, presents you with an HTML page containing a link to the SoftCopy Librarian's Readme file.

- 2** Click on the link to the Readme file and look at the version listed.

The first line of the Readme contains the version number.
- 3** Compare the version listed in the Readme with the version that you have installed.

The Readme also explains how to determine which version you have installed.
- 4** If there is a later version available on the Web site, you can download the Windows version of the SoftCopy Librarian install package.

Installing the SoftCopy Librarian on a Windows Workstation

To install the SoftCopy Librarian on a Windows workstation, do the following:

- 1** Locate the install package EBRSCWJ.EXE and invoke it from Windows Explorer, the Start->Run prompt, or a command prompt.

The InstallShield Wizard window appears. When the SoftCopy Librarian code is unpacked, the Choose Destination Location window appears in the IBM SoftCopy Librarian Setup screen.
- 2** In the Choose Destination Location window, you can accept the default destination C:\Program Files\IBM\IBM SoftCopy Librarian V4 or choose another. When you are ready, press the **Next>** button.

The Start Copying Files window appears to confirm your choices.
- 3** In the Start Copying Files window, press the **Next>** button.

A progress indicator shows the SoftCopy Librarian files being installed. When the installation is complete, the Installation Wizard Complete window appears.

4 In the Installation Wizard Complete window, press the **Finish** button.

After you have installed the SoftCopy Librarian code, you are ready to start the SoftCopy Librarian and prepare your host or server for setting up a repository. Continue with the instructions in Chapter 5.

Chapter 5. Starting the SoftCopy Librarian

This chapter describes how to start the SoftCopy Librarian on a Windows workstation.

Starting the SoftCopy Librarian From a Windows Workstation

To start the SoftCopy Librarian, do the following:

- 1** Go to the Start menu.
- 2** In the Start menu, select the Programs choice.
- 3** In the Programs menu, select the IBM SoftCopy Librarian V4 choice.
- 4** In the IBM SoftCopy Librarian menu, select the SoftCopy Librarian choice.

The SoftCopy Librarian window appears.

If you are starting the SoftCopy Librarian for the first time: The SCL - First Time Usage window will also open. In the SCL - First Time Usage window, do the following:

- a. If you have been using a previous version (3.x) of the SoftCopy Librarian:** and you want to continue to use repositories you have already set up, you can migrate your source and repository definitions to the new librarian by clicking on the **Migrate** button.

Your existing definitions will be migrated to the new librarian.

Note: If you have host repositories that require FTP connections, you must do the following before you can use them:

- Open the repository properties window.

You can open this window by doing one of the following:

– **In the repository window:**

- 1)** Click on the File choice.

– **In the Sources and Repositories window.**

- 1) Click on the repository in the list.**

- 2) Click on the File choice.**

- In the File menu, select Properties.
- In the Properties window, click on the **Next** button to go to the FTP Logon tab.
- Reenter the user ID and password.
- Click the **OK** button.

- b. Setup a default source for your CD-ROM drive:** type the drive letter for your CD-ROM drive in the CD-ROM Drive field.

The SoftCopy Librarian will create a default source using your CD-ROM drive.

- c. Click on the **Define CD Source** button.

The default source will be named CD-ROM - x\ drive.

If you have previously installed and set up the SoftCopy Librarian and know how to use it, you can continue with the instructions in Chapter 14.

If you are not familiar with the SoftCopy Librarian window and how to use it, you can continue reading “How You Can Use the SoftCopy Librarian Main Window” below for a description of the main window and what you can do next.

How You Can Use the SoftCopy Librarian Main Window

The SoftCopy Librarian main window contains a menu bar and several windows. The following descriptions will help you become familiar with the location and contents of the items in the main window.

The Menu Bar

The menu bar contains the following choices:

- File

This selection contains the following choice:

- Exit

This closes the SoftCopy Librarian.

- Settings

This selection contains the following choice:

- Proxy

This permits you to define the type of Internet connection that you are using:

- Direct - without a firewall
- Proxy - with a firewall

- Trace

For debugging purposes only: Do not select this choice unless instructed do to so by an IBM support person.

- Window

This selection always contains the following choices:

- Tile

This arranges the open windows in a “tiled” arrangement, that is, all the windows are open and fit side-by side in the available space.

- Cascade

This arranges the open windows in a “cascaded” arrangement, that is, all the windows are placed on top of each other with at least their titles showing.

- Minimize all

This temporarily hides each open window from view. A button that will redisplay each window appears at the bottom of the main window.

- Maximize all

This redisplay any windows that were minimized and returns them to view. Each window occupies the entire area of the main window. You can bring any window to the top with its choice in this list.

- Messages

This redisplay only the Messages window if it was previously minimized and always makes it the active window.

- Sources and repositories

This redisplay only the Sources and Repositories window if it was previously minimized and always makes it the active window.

This selection also contains an additional entry, by title, for each source or repository window that you currently have open.

- Source - *source-title*

This redisplay only the source window named if it was previously minimized and always makes it the active window.

- Repository - *repository-title*

This redisplay only the repository window named if it was previously minimized and always makes it the active window.

- Help

This selection contains the following choices:

- Getting Started

This is your online help. It provides brief descriptions to help you understand the contents of the windows and the choices available

- User's Guide

This is the SoftCopy Librarian User's Guide. It contains a complete description of the SoftCopy Librarian.

- Migrate V3.x files

If you have been using a previous version of the SoftCopy Librarian (V3.x), this permits you to migrate your current repository definitions to the new version.

- About

This gives you a brief description of the SoftCopy Librarian program and identifies the version.

- Reporting a problem

This provides a way to report any problems that you encounter with the SoftCopy Librarian directly to IBM.

- Hints and tips

This contains suggestions and guidelines from the developers concerning the operation and configuration of SoftCopy Librarian.

- Check for updates (auto and manual)

This permits you to check the IBM SoftCopy Web site for the latest updates to the SoftCopy Librarian as they become available.

Using the Windows

You will also see several windows in the SoftCopy Librarian window.

If you have just installed the SoftCopy Librarian: the following windows will appear:

The SCL - Getting Started Window

This is the online help that is available to you from the Help choice on the menu bar. If you no longer need it open all the time, close the **Getting Started** window, then exit SoftCopy Librarian. The program will remember not to open the **Getting Started** window when you initiate SoftCopy Librarian in the future.

The Messages Window

This records status and errors messages as they are produced by the SoftCopy Librarian.

The Sources and Repositories Window

This window usually lists all the sources and repositories that are currently available to you. You can open any source or repository listed by double clicking on it in the list. At this point, this window will contain only two default sources - a default CD-ROM drive and a default Internet connection to the IBM Online Library Web site.

The Column Headings in the Sources and Repositories Window: This window lists the following:

- Type

The type of the entry: Source or Repository.

- Title

The titles of the sources and repositories.

Note: You can change the alphanumeric order of each column from ascending to descending and back by clicking on the heading of the column that you want to reorder.

The Menu Bar: The menu bar contains the following choices:

- File

This selection contains the following choices:

- New

This lets you define a new source or repository.

- Print

This lets you print the list of sources and repositories.

- Synchronize (not available)

This lets you synchronize or merge the contents of two or more repositories. That is, any file in any repository that is not in any of the other repositories is added to them. All the repositories will be identical to each other.

- Open

This opens the window of the selected source or repository.

- Create Catalog (Repositories only)

- This creates or recreates the catalog for the selected repository.
 - Delete
 - This deletes the selected source or repository.
 - Properties
 - This opens the Repositories Properties - *title* or the Source Properties - *title* window for updating the selected source or repository.
 - Update Status: Compared to (Sources only)
 - This updates the status column for the items on this source in comparison with the contents of one of your repositories.
 - Erase Cache (Repositories only)
 - This lets you erase the cache if you have made changes to this repository by hand outside of the SoftCopy Librarian.
- Help
 - This selection contains the following choices:
 - Getting Started
 - This opens the Getting Started window if it is closed.
 - User's Guide
 - This opens the complete SoftCopy Librarian User's Guide.

The Source - source-name Window

If you have set up sources or if you have migrated them from a previous version of the SoftCopy Librarian, one or more source windows might appear. This window contains a source of publications that you have defined regardless of where it is located. The title that you assigned to it appears in the title of the window. There is one source window for each source to which you currently have access.

You can open a source window by selecting it from the list in the Sources and Repositories window.

The Column Headings in a Source Window: This window lists the following:

- Title
 - The titles of the shelves available on this source.
 - Status
 - The status of each Shelf compared to the contents of one of your repositories.
- Note:** If you do not have any repositories defined, the status is “New.” for all items listed.

The status of a shelf can be:

- New** One of the following occurred:
- This is the first time that this shelf appears on any CD or supported Web site from this manufacturer, and is, therefore, not currently in your repository.
- Note:** This status can apply to all IBM CDs and might apply to the CDs of other manufacturer's who take notice of their previous CDs.

- This shelf appeared on a previous CD; you did not choose to transfer it previously and is, therefore, not currently in your repository.

You can transfer this shelf now.

Updated An earlier version of this shelf is currently in your repository. You can transfer this later version now.

Note: If you upload this later version, it will not automatically replace an earlier version. You can choose to delete the earlier version or keep both versions.

Installed This shelf is currently in your repository. You cannot transfer this shelf.

Downlevel A later version of this shelf is currently in your repository. This earlier version is not in your repository. You can transfer the earlier version now, if you want it. It will not replace the later version.

Note: This can happen if the filename of the shelf does not conform to the naming conventions for IBM softcopy files, or if you are currently using a CD that is older than a previous CD from which you transferred this shelf.

Partial This shelf is currently in your repository. However, your repository is missing one or more files. This is transferrable.

- **Filename**

The names of the shelf files.

- **Date**

The date the shelf file was built.

- **Size**

The total size of all the files in the shelf in MB (megabytes).

- **Files**

The number of files in the shelf.

Note: You can change the alphanumeric order of each column from ascending to descending and back by clicking on the heading of the column that you want to reorder.

The Menu Bar in a Source Window: The menu bar contains the following choices:

- **File**

This selection contains the following choices:

- **Print**

This prints a copy of the table that appears in this window.

- **Save As**

This saves to a file a copy of list that appears in this window

- **Update Status: Compare to**

This updates the status of the items on this source in comparison with one of your repositories.

- Open

This opens the shelf and displays a list of the associated files (publications) contained in it.
- Send to

This lets you send any of the shelves that you have selected to one of your repositories.
- Refresh

This refreshes the list if you change sources and automatically does an Update Status to the default repository.
- Close

This closes this window.

- Edit

This selection contains the following choices:

- Find First

This lets you search for any text string in the list.
- Find Next F3

This finds the next occurrence of the text string.

- Options

This selection contains the following choices:

- Select All

This selects all the items in the list.
- Deselect All

This deselects any items that you selected.
- Show New/Updated Ctrl+K

This shows only the items in that list that have a status of “New” or “Updated.”
- Show All

This shows all the items in the list.

The Repository - repository-name Window

If you have set up repositories or if you have migrated them from a previous version of the SoftCopy Librarian, one or more repository windows might appear. This window contains one of the repositories that you have defined regardless of its location. The title that you assigned to it appears in the title of the window. There is one repository window for each repository to which you currently have access.

If you had a repository window open previously, it will be open when you start the SoftCopy Librarian. You can open a repository window by selecting it from the list in the Sources and Repositories window.

The Column Headings in a Repository Window: This window lists the following:

- Under the Shelves tab:
 - Title

The titles of the shelves currently in this repository

Note: If a shelf appears in “red,” then it is missing one or more associated publication’s files.

– Filename

The names of the files that contain the shelves.

– Replaced by

The filename of a newer version of this shelf that can replace it .

• Under the Files tab:

– Title

The titles of the shelves and associated publications currently in this repository

Note: If a file appears in “red,” then it is missing from one or more shelves.

– Filename

The names of the files that contain the shelves and associated publications.

– Replaced by

The filename of a newer version of this shelf and associated publications that can replace it.

– Filetype

The filetype of this shelf and associated publications.

Filetypes can be:

BOOK Book

BKSHELF Shelf

XKSHELF Extended Shelf

BKINDEX Shelf index

PDF PDF file

– Count

The reference count of this shelf index and associated publications.

Positive Indicates how many shelves currently include these associated publications.

Negative (-) Indicates how many shelves are missing these associate publications (shown in red), or without an accompanying number indicates a single shelf.

Zero (0) Indicates an “orphaned” file that in not part of any shelf.

Note: To save space, repositories managed by the SoftCopy Librarian contain only one copy of a associated publications that are part of more than one shelf.

Note: You can change the alphanumeric order of each column from ascending to descending and back by clicking on the heading of the column that you want to reorder.

The Menu Bar in a Repository Window: The menu bar contains the following choices:

Note: These choices apply to both the Shelves and Files tabs unless otherwise indicated.

- Create Catalog - Creates a catalog for the selected repository.

- File

This selection contains the following choices:

- Erase Cache

This lets you erase the cache if you have made changes to this repository by hand outside of the SoftCopy Librarian.

- Print

This prints a copy of the table that appears in this window.

- Save As

This saves to a file a copy of the table that appears in this window

- Update shelves

For z/OS and OS/390 repositories only: If you update a z/OS or OS/390 host repository directly from tape or change it manually, after you make these changes, this updates the data set names in the shelves so the SoftCopy Librarian will recognize them. (For users who typically install files from tape, this choice replaces the BKSADD EXEC.) The Update Shelves function is done automatically whenever you run the Create Catalog function.

- Exclude from Shelf (Files tab only)

This excludes “missing” files from a shelf permanently.

Note: Missing files appear in “red” in the list of shelves and in the list of files.

- Download from Internet (Files tab only)

This obtains replacement copies from the IBM Internet Library for any files that are missing from a shelf in your repository.

- Delete

On the Shelves tab: This deletes any shelves that you select.

On the Files tab: This deletes any file that you select. **Warning:** You should only delete files with a reference count of “0” (orphan books).

If you delete a file with a reference count higher than “0,” you will create one or more partial shelves that are missing the book you delete.

- Details

This describes the shelf.

- Edit Title (Shelves tab only)

This lets you change the title of any of the shelves that appear in this list.

- Open (Shelves tab only)

This opens the shelf and displays a list of the associated publications in it.

- Send to

This lets you send any of the shelves or publications that you have selected to one of your repositories.

- Close

This closes this window.

- Edit

This selection contains the following choices:

- Find First

This lets you search for any text string in the list.

- Find Next F3

This finds the next occurrence of the text string.

- Options

This selection contains the following choices:

- Select All

This selects all the items in the list.

- Deselect All

This deselects any items that you selected.

- Sort Shelves by Missing Files

Sorts all shelves with missing files to the top.

What to Do Next

If you have just installed the SoftCopy Librarian, and this is the first time that you have started it, you will need to do the following before you can begin to use it:

- If you want to use the Internet as a source, you must define your Internet connection to the SoftCopy Librarian. Refer to Chapter 6 for instructions.
- If you did not choose to migrate your previous source and repository definitions, but you want to continue to use them, you can migrate them at a future time. Refer to Chapter 7 for instructions.
- If you want to define new repositories, you must create definitions for them. For instructions, refer to Chapter 8 (for repositories in z/OS or OS/390 sequential data sets), Chapter 9 (in z/OS or OS/390 Unix System Services hierarchical files), Chapter 10 (on a Unix-like server), or Chapter 11 (on a LAN server or personal computer).

If you have previously installed the SoftCopy Librarian, and completed all the necessary set up, you are ready to use it. Refer to Chapter 14 for instructions.

Chapter 6. Setting Up Your Connection to the Internet

This chapter describes how to set up the SoftCopy Librarian to connect to the Internet or your intranet. You might want the SoftCopy Librarian to be able to use the Internet:

- As a source from the IBM PUBLIB or other Web sites
- To check for and download newer versions of the SoftCopy Librarian from IBM.

Note: If you are accessing repositories on hosts or local servers and you not using an intranet or the Internet to access them, you do not need a connection to the Internet. However, if you want to check for updates to the SoftCopy Librarian, you will need an Internet connection.

The SoftCopy Librarian supports these connections to the Internet:

- Direct connections

For connections to an intranet inside a firewall or for connections to the Internet without a firewall.

Recommendation: We strongly recommend that you set up a firewall between your server and the Internet.

- Manual proxy configurations
 - HTTP servers as proxies
 - SOCKS V4 servers as proxies

For connections to the Internet through a firewall.

- Autoproxy configurations

For connections to the Internet through a firewall.

Note: If you are connecting to the Internet through a firewall, your server must already be configured for access through your firewall.

Your selection of a type of connection and a URL provided for your proxy should match the specifications in your Web browser.

Note: Please be aware that SoftCopy Librarian does not provide user-id/password support when using Proxy Configuration.

Setting Up an Internet Connection

Reminder: You can check for the type of connection you are using as follows:

Start -> Setting -> Control Panel -> Internet Options ->
Connections -> LAN Settings

To set up an Internet connection, do the following:

- 1** Start the SoftCopy Librarian.
- 2** On the menu bar in the SoftCopy Librarian window, select Settings.
- 3** In the Settings pull-down menu, select Proxies.

The Proxy Settings window appears.

4 In the Proxy Settings window, do the following:

a. Select the type of connection. Do one of the following:

- **For a Direct Connection:** Select the Direct connection to the Internet button.
- **For a Manual Proxy Configuration:** Select the Manual proxy configuration button and supply the path to your proxy and a port number.
- **For an Auto Proxy Configuration:** Select the Auto proxy configuration button and make sure that the URL shown points to the correct automatic configuration script.

b. Click on the **OK** button.

After you have set up your Internet connection, if needed, you are ready to set up your repositories. You have two possibilities:

- If you are a new user, you are ready to define the repositories that you intend to use. Continue with the instructions in Chapter 8 (for host repositories using sequential data sets), Chapter 9 (for host repositories using hierarchical files), Chapter 10 (for Unix-like repositories), or Chapter 11 (for PC or local repositories).
- If you have been using a previous version of the SoftCopy Librarian (V3.x or V4.1.x) you can migrate your existing repository definitions to the new version. Continue with the instructions in Chapter 7.

Chapter 7. Migrating from Previous Versions of the SoftCopy Librarian

This chapter describes how to migrate from an older, previous version of the SoftCopy Librarian to the most current version. After you install the current version of the SoftCopy Librarian, you can migrate your existing repository and source definitions that you used with an older version of the SoftCopy Librarian. Migrating these definitions will make them available to the current version of the SoftCopy Librarian, and you will not need to redefine them.

Usually, you would have migrated your repository and source definitions when you started the SoftCopy Librarian V4 for the first time. Then, you were given the opportunity to migrate these files. **Warning:** If you have already migrated your existing repositories, do **not** attempt to migrate them again. Any changes you made to your repository definitions will be lost.

If for some reason, you chose not to migrate at that time, you can do it at any other time that is convenient for you.

Migrating from V3.x to V4.1

To migrate from V3.x to V4.1, do the following:

- 1** Start your old version of the SoftCopy Librarian.
- 2** Click on Setup -> Share work files.
- 3** Make note of the path that is displayed in the Share Work Files window.
- 4** Shut down the old version of the SoftCopy Librarian.
- 5** Start the current version of the SoftCopy Librarian.
The SoftCopy Librarian window appears.
- 6** In the SoftCopy Librarian window, select Help from the menu bar.
- 7** In the Help pull-down, select Migrate V3.x Files.
The SCL - Migrate window appears.
- 8** In the SCL - Migrate window, do the following:
 - a.** Enter the path to the work directory that you obtained in the old librarian in the work directory field.
Note: The default path is shown in the field.
 - b.** Click on the **Migrate** button.
- 9** You must also recreate the catalogs for these repositories. Refer to Chapter 12 for instructions.

10 For host and Unix-like repositories only: You must reenter the FTP user ID and password for each repository that you migrated. Refer to Chapter 8, Chapter 9, or Chapter 10. for instructions.

If you do not intend to set up new repositories in addition to those you migrated, continue with the instructions in Chapter 13.

If you want to set up new repositories in addition to any that you migrate, you can continue with the instructions in Chapter 8 (for host repositories using sequential data sets), Chapter 9 (for host repositories using hierarchical files), Chapter 10 (for Unix-like repositories), or Chapter 11 (for PC or local repositories).

Migrating from V3.x to V4.2

To migrate from V3.x to V4.2, uninstall and delete all files associated with SoftCopy Librarian V3.x, then install V4.2 and redefine all sources and repositories.

Migrating from V4.1 to V4.2

To migrate from V4.1 to V4.2, do the following:

- 1** Install V4.2
- 2** Using the **Properties** function, update each repository adding XKS and PDF information.
- 3** Initiate an **Erase Cache** with a **Catalog Create** for each repository defined.

Chapter 8. Setting Up a z/OS or OS/390 Host Repository Using Sequential Data Sets

You must define at least one host repository for the SoftCopy Librarian to be able to manage your softcopy files. You can set up one or more host repositories using z/OS or OS/390 sequential data sets. This type of repository is intended for use with BookManager READ/MVS accessed from a 3270-like terminal or through a 3270-like emulator session from a workstation. The definition for this type of repository tells the SoftCopy Librarian where to look for the shelves and what FTP commands to use to access the repository. You can define this type of repository whether or not you already have softcopy files installed on your host.

This chapter describes:

- Considerations to keep in mind before setting up your repository
- Instructions for preparing your host
- Defining the repository to the SoftCopy Librarian

Considerations for Setting Up Your Repository Using Sequential Data Sets

Here are some things you need to know about repositories on a z/OS or OS/390 host in sequential data sets:

- You can define your repositories in several ways. For example:
 - Define a single repository under one HLQ, into which you would put all your softcopy data sets.
 - Define a single repository under multiple HLQs.
You can put your softcopy
 - All shelf file types must be under the same HLQ.
 - File types can be either under a separate HLQ or combined under an HLQ.
 - Define multiple repositories, provided they are each under separate HLQs from each other.
- If you already have a shelf or shelves (.BKSHELF and .XKSHELF) data sets for a repository installed under multiple HLQs, you must delete them and reinstall them under a single HLQ.
- You can place non-softcopy items under HLQs managed by the SoftCopy Librarian. The SoftCopy Librarian will ignore them.

- If you add or remove softcopy items from your repository without using the SoftCopy Librarian, you must recreate the catalog.

The SoftCopy Librarian will not recreate it automatically for you, and, therefore, it will not be able to recognize your changes.

- The SoftCopy Librarian creates a shelf list in the HLQ you specify when you set up your repository. Do **not** make any changes to this list. This list is replaced whenever the SoftCopy Librarian adds or removes data sets, so your changes will be lost.

Setup Required at Your z/OS or OS/390 Host

To set up a repository on your host, you must do the following:

- 1** Edit the BookManager Shelf list (.BKLSHELF) on your host. Do the following:
 - a. Make a backup copy of your BookManager Shelf list (the default is EOY.BKLSHELF).
 - b. Edit the original copy of the EOY.BKLSHELF Shelf list.
 - c. Delete any shelves that you want the SoftCopy Librarian to manage.
 - d. Include an entry for the SoftCopy Librarian's Shelf list:

```
INCLUDE h1q.BKLSHELF
```
- 2 For System Managed Storage Users:** You can define separate storage classes for the data sets containing shelves and associated publications. However, ensure that the Shelf data sets in your host repository are **not** migrated from DASD to tape.

Note: If you do migrate your data sets to tape, you must issue an HRECALL command to recall the data sets before you attempt to create your catalog.

You are now ready to define a host repository. Continue with the instructions in "Defining a z/OS or OS/390 Host Repository."

Defining a z/OS or OS/390 Host Repository

To define a host repository, do the following:

- 1** On your workstation, start the SoftCopy Librarian. (Refer to Chapter 5.)
- 2** In the Sources and Repositories window in the SoftCopy Librarian window, do the following:
 - a. Click on File on the task bar.
 - b. In the pull-down window that appears, click on the New choice.
 - c. In the pop-up window that appears, click on the Repository choice.The Repository Properties - New Repository window appears.
- 3** In the Repository Properties - New Repository window, do the following:
 - a. Type a name for this new repository in the Repository Title field.

Note: The name you type here can be anything you want. It is the name that the Softcopy Librarian uses on your workstation to refer to your host repository.
 - b. Select the Location and method of accessing your repository.
 - z/OS or OS/390 - Sequential Data Sets via FTPThis is the default.
 - c. Click on the FTP Logon Information tab or the **Next>** button.The FTP logon information window appears.

- 4** In the FTP logon information window, do the following:
- a. In the Host: field, type the host name or IP address of your host.
 - b. In the Port: field, type a port number, if you know that you must use a non-standard port number to connect to your host. Otherwise, leave this field blank.
 - c. In the UserID field, type your user ID on your host.
 - d. In the Password field, type your password for this host, if you have a password.
 - e. Optionally, Click on the Save Password box.
By saving your password, you will not need to enter your password whenever you start the SoftCopy Librarian. If you do not save your password, you must enter it every time you start the SoftCopy Librarian.
 - f. In the FTP site commands field, enter defaults for any other type FTP site commands that your installation requires. Enter a complete command, for example:

```
SITE DCB=xxx
```

These site commands are typically used for allocating data sets. Type one command per line.
 - g. Click on the File types tab or the **Next>** button.
The File types window appears.

- 5** In the File types window, do the following:
- a. If you want to set the same defaults for your SMS classes, DASD units and volumes, or additional FTP commands that apply to all file types, select the DEFAULT - Applies to all filetypes choice from the list at the top of the window.
Note: All defaults are optional. If you do not provide a value for of any of the items in this window except SMS classes, no defaults will be set. For SMS classes, if you do not set a default here, any host settings that are in effect will be used.
If you specify any of these values for the BOOK, BKINDEX, BKSHELF, or Bk1shelF choices, those values will override the defaults you set here for the DEFAULT choice.
If you do not want to set the same defaults for your SMS classes, DASD units or volumes, or additional FTP commands that will apply to all file types, continue with step 6.
 - b. In the SMS Data Class field, enter a data class for all file types.
 - c. In the SMS Management Class field, enter a management class for all file types.
 - d. In the SMS Storage Class field, enter a storage class.
 - e. In the Unit field, enter a default DASD device for your high-level qualifiers.
 - f. In the Volume field, enter a default volume ID for your high-level qualifiers.

- g.** In the Additional FTP commands field, enter any additional FTP commands.
- h.** Continue with the next step to define the high-level qualifiers and block sizes for your repository and any defaults that you want to apply only BOOK files.

6 Click on the Book choice in pull-down list or the **Next** button.

7 Do the following:

- a. Required:** In the High-level qualifier field, type one or more high-level qualifiers for the books in your repository.

You do not need to include single quotes; they will be provided for you, for example, if you type:

```
library.ibmbooks  
library.ourbooks
```

It will appear as:

```
'library.ibmbooks'  
'library.ourbooks'
```

- b. Required:** In the Blocksize pull-down menu, select the blocksize for the DASD device you are using for your BOOK data sets.
- c. Optional:** If you want to assign separate defaults for SMS classes, devices, or FTP site commands for your BOOK data sets, you can specify values in the remaining fields on this tab. Otherwise, the defaults that you specified for the DEFAULT choice will be used for these data sets.

8 Click on the BKINDEX choice in pull-down list or the **Next** button.

9 Do the following:

- a. Required:** In the High-level qualifier field, type the high-level qualifier for the shelf indexes in your repository.

You do not need to include single quotes; they will be provided for you, for example, if you type:

```
library.ibmindex
```

It will appear as:

```
'library.ibmindex'
```

- Note:** Make sure that the data sets under this high-level qualifier contains only softcopy items.
- b. Required:** In the Blocksize pull-down menu, select the blocksize for the DASD device you are using for your BKINDEX data sets.
- c. Optional:** If you want to assign separate defaults for SMS classes, devices, or FTP site commands for your BKINDEX data sets, you can specify values in the remaining fields on this tab. Otherwise, the defaults that you specified for the DEFAULT choice will be used for these data sets.

10 Click on the BKSHELF choice in pull-down list or the **Next** button.

11 Do the following:

- a. **Required:** In the High-level qualifier field, type the high-level qualifier for the shelves in your repository.

You do not need to include single quotes; they will be provided for you, for example, if you type:

```
library.ibmshelf
```

It will appear as:

```
'library.ibmshelf'
```

- b. **Required:** In the Blocksize pull-down menu, select the blocksize for the DASD device you are using for your BKSHELF data sets.
- c. **Optional:** If you want to assign separate defaults for SMS classes, devices, or FTP site commands for your BKSHELF data sets, you can specify values in the remaining fields on this tab. Otherwise, the defaults that you specified for the DEFAULT choice will be used for these data sets.

12 Click on the BKLSHELF choice or the **Next** button.

13 Do the following:

- a. **Required:** In the HLQ field, provide the high-level qualifier for the shelf list that you included in EOY.BKLSHELF.
- b. **Optional:** If you want to assign separate SMS classes, devices, or FTP site commands for your shelf list data set, you can specify values for the remaining fields on this tab. Otherwise, the defaults that you specified on the DEFAULT choice will be used for this data set.

14 Click on the PDF choice in pull-down list or the **Next** button.

15 Do the following:

- a. **Required:** In the High-level qualifier field, type one or more high-level qualifiers for the PDFs in your repository.

You do not need to include single quotes; they will be provided for you, for example, if you type:

```
library.ibmPDFs
```

It will appear as:

```
'library.ibmPDFs'
```

- b. **Required:** In the Blocksize pull-down menu, select the blocksize for the DASD device you are using for your PDF data sets.
- c. **Optional:** If you want to assign separate defaults for SMS classes, devices, or FTP site commands for your PDF data sets, you can specify values in the remaining fields on this tab. Otherwise, the defaults that you specified for the DEFAULT choice will be used for these data sets.

16 Click on the XKSHELF choice in pull-down list or the **Next** button.

17 Do the following:

- a. **Required:** In the High-level qualifier field, type the high-level qualifier for the shelves in your repository.

You do not need to include single quotes; they will be provided for you, for example, if you type:

```
library.ibmxxks
```

It will appear as:

```
'library.ibmxxks'
```

- b. **Required:** In the Blocksize pull-down menu, select the blocksize for the DASD device you are using for your XKSHELF data sets.
- c. **Optional:** If you want to assign separate defaults for SMS classes, devices, or FTP site commands for your XKSHELF data sets, you can specify values in the remaining fields on this tab. Otherwise, the defaults that you specified for the DEFAULT choice will be used for these data sets.

18 Click on the **OK** button.

The SoftCopy Librarian window reappears with the following changes:

- The Sources and Repositories window now lists the repository that you just defined.
- A new Repository - *repository-name* window for the repository will not appear, but you can open it from the Sources and Repositories window.

You are done defining your repository. You can define additional repositories by repeating these instructions for each new repository.

When you have finished defining all your repositories, you are ready to create the catalog for your repositories. Continue with the instructions in Chapter 12.

Chapter 9. Setting Up a z/OS or OS/390 Host Repository Using the Unix System Services HFS

You must define at least one repository for the SoftCopy Librarian to be able to manage your softcopy files. You can set up one or more host repositories of softcopy files using the hierarchical file system of z/OS or OS/390 Unix System Services. This type of repository is intended for use with either:

- BookManager READ/MVS accessed from a 3270-like terminal or through a 3270-like emulator session from a workstation
- BookManager BookServer/Library Server accessed from a workstation through a Web browser

The definition for this type of repository tells the SoftCopy Librarian where to look for the softcopy shelves and what FTP commands to use to access the repository. You can define this type of repository whether or not you already have softcopy installed on your host.

This chapter describes:

- Considerations to keep in mind before setting up your repository
- Information about your repository that you will need when you set up the SoftCopy Librarian on your workstation
- Instructions for preparing your host
- Defining the repository to the SoftCopy Librarian

Considerations for Setting Up a Repository in Hierarchical Files

Here are some things you need to know about repositories in the z/OS or OS/390 Unix System Services hierarchical files:

- You can define your repositories in several ways. For example:
 - Define a single repository in a single directory, into which you would put all your shelves and associated publications.
 - Define a single repository in multiple directories.
 - All shelf file types must be in the same directory.
 - File types can be either in separate directories or in combined directories.
 - Define multiple repositories, provided they are each in separate directories from each other.
- If you already have Shelf (.xks) files for a repository installed in multiple directories, you must delete them and reinstall them in a single directory.
- If you add or remove softcopy items from your repository without using the SoftCopy Librarian, you must recreate the catalog.

The SoftCopy Librarian will not recreate it automatically for you, and, therefore, it will not be able to recognize your changes.

- File names for softcopy items are transferred by the SoftCopy Librarian in lower case.

Information You Must Gather about Your Repository

You must provide the following information when you define the repository:

- A name by which the repository will be known on your workstation.
- The host name or IP address and your host user ID and password.
- One or more directories that will contain the softcopy files.
- Any FTP commands are required by your location to transfer the associated file types from the workstation to your host.

Defining a z/OS or OS/390 UNIX System Services Host Repository

To define a host repository, do the following:

- 1** On your workstation, start the SoftCopy Librarian. (Refer to Chapter 5.)
- 2** In the Sources and Repositories window in the SoftCopy Librarian window, do the following:
 - a. Click on File on the task bar.
 - b. In the pull-down window that appears, click on the New choice.
 - c. In the pop-up window that appears, click on the Repository choice.

The Repository Properties - New Repository window appears.

- 3** In the Repository Properties - New Repository window, do the following:
 - a. Type a name for this new repository in the Repository Title field.

Note: The name you type here can be anything you want. It is the name that the SoftCopy Librarian uses on your workstation to refer to your host repository.
 - b. Select the Location and method of accessing your this repository by clicking on the **z/OS or OS/390 - Unix System Service HFS via FTP** button.
 - c. Click on the FTP Logon Information tab or the **Next** button.

The FTP logon information window appears.

- 4** In the FTP logon information window, do the following:
 - a. In the Host: field, type the host name or IP address of your host.
 - b. In the Port: field, type a port number, if you know that you must use a non-standard port number to connect to your host. Otherwise, leave this field blank.
 - c. In the UserID field, type your user ID on your host.
 - d. In the Password field, type your password for this host, if you have a password.
 - e. Optionally, click on the Save Password box.

By saving your password, you will not need to enter your password whenever you start the SoftCopy Librarian. If you do not save your password, you must enter it every time you start the SoftCopy Librarian.

- f. In the FTP site commands field, enter defaults for any other type FTP site commands that your installation requires. Enter a complete command, for example:

```
SITE DCB=xxx
```

These site commands are typically used for allocating data sets. Type one command per line.

- g. Click on the File types tab or the **Next** button.

The File types window appears.

- 5** In the File types window, do the following:

- 6** Click on the B00 choice pull-down list or the **Next** button.

- 7** Do the following:

- a. **Required:** In the Directories containing books field, type the path to the directory in your HFS that contains your books. For example:

```
/u/your-ID/books
```

- 8** Click on the BKI choice in pull-down list or the **Next** button.

- 9** Do the following:

- a. **Required:** In the Directory containing indexes field, type the path to the directory in your HFS that contains your indexes. For example:

```
/u/your-ID/indexes
```

Note: This can be the same directory that contains your books.

- 10** Click on the BKS choice in pull-down list or the **Next** button.

- 11** Do the following:

- a. In the Directory containing shelves field, type the path to the directory in your HFS that contains your shelves. For example:

```
/u/your-ID/shelves
```

- b. Click on the **OK** button.

- 12** Click on the PDF choice pull-down list or the **Next** button.

- 13** Do the following:

- a. **Required:** In the Directories containing PDFs field, type the path to the directory in your HFS that contains your books. For example:

```
/u/your-ID/PDFs
```

- 14** Click on the XKS choice in pull-down list or the **Next** button.

- 15** Do the following:

- a. In the Directory containing shelves field, type the path to the directory in your HFS that contains your XKS shelves. For example:

```
/u/your-ID/xkshelves
```

b. Click on the **OK** button.

16 The SoftCopy Librarian window reappears with the following changes:

- The Sources and Repositories window now lists the repository that you just defined.
- A new Repository - *repository-name* window appears with the name you assigned.

You are done defining your repository. You can define additional repositories by repeating these instructions for each new repository.

When you have finished defining all your repositories, you are ready to create the catalog for your repositories. Continue with the instructions in Chapter 12.

Chapter 10. Setting Up a Unix-like Repository

You must define at least one repository for the SoftCopy Librarian to be able to manage your softcopy files. This type of repository is intended for use with BookManager BookServer accessed from a workstation through a Web browser. The repository definition tells the SoftCopy Librarian where to look for softcopy and what FTP commands to use to access the repository. You can define a repository whether or not you already have softcopy files installed.

This chapter describes:

- Considerations to keep in mind before setting up your repository
- Defining the repository to the SoftCopy Librarian

Considerations for Setting Up Your Repository

Here are some things you need to know about your repository on UNIX server hard drives:

- You can define your repositories in several ways. For example:
 - Define a single repository in a single directory, into which you would put all your softcopy files.
 - Define a single repository in multiple directories.
 - All shelf file types must be in the same directory.
 - File types can be either in separate directories or in combined directories.
 - Define multiple repositories, provided they are each in separate directories from each other.
- Ensure you have read/write access to the necessary directories.
- If you already have files for a repository installed in multiple directories, you must delete them and reinstall them in a single directory.
- If you add or remove softcopy items from your repository without using the SoftCopy Librarian, you must recreate the catalog.

The SoftCopy Librarian will not recreate it automatically for you, and, therefore, it will not be able to recognize your changes.

Defining a Unix Server Repository

To define a repository on a Unix server, do the following:

- 1** On your workstation, start the SoftCopy Librarian. (Refer to Chapter 5.)
- 2** In the Sources and Repositories window in the SoftCopy Librarian window, do the following:
 - a.** Click on File on the task bar.
 - b.** In the pull-down window that appears, click on the New choice.
 - c.** In the pop-up window that appears, click on the Repository choice.

The Repository Properties - New Repository window appears.

3 In the Repository Properties - New Repository window, do the following:

a. Type a name for this new repository in the Repository Title field.

Note: The name you type here can be anything you want. It is the name that the SoftCopy Librarian uses on your workstation to refer to your repository.

b. Select the Location and method of accessing your this repository by clicking on Other UNIX-like via FTP button.

c. Click on the FTP Logon Information tab or the **Next>** button.

The FTP logon information window appears.

4 In the FTP logon information window, do the following:

a. In the Host: field, type the IP address of your server.

b. In the Port: field, type a port number, if you know that you must use a non-standard port number to connect to your server. Otherwise, leave this field blank.

c. In the UserID field, type your user ID on your server.

d. In the Password field, type your password for this server.

e. Optionally, click on the Save Password box.

By saving your password, you will not need to enter your password whenever you start the SoftCopy Librarian. If you do not save your password, you must enter it every time you start the SoftCopy Librarian.

f. In the FTP site commands field, enter defaults for any other type FTP site commands that your installation requires. Enter a complete command, for example:

```
SITE DCB=xxx
```

These site commands are typically used for allocating data sets. Type one command per line.

g. Click on the File types tab or the **Next>** button.

The File types window appears.

5 In the File types window, do the following:

6 Click on the B00 choice in the pull-down list or the **Next** button. Do the following:

a. **Required:** In the Directories containing books field, type the one or more paths to the directory that contain your books. For example:

```
/u/your-ID/books
```

7 Click on the BKI choice in the pull-down list or the **Next** button. Do the following:

a. **Required:** In the Directory containing indexes field, type the path to the directory that contains your indexes. For example:

`/u/your-ID/indexes`

Note: This can be the same directory that contains your books.

8 Click on the BKS choice in the pull-down list or the **Next** button. Do the following.

- a. In the Directory containing shelves field, type the path to the directory that contains your shelves. For example:

`/u/your-ID/shelves`

- b. Click on the **OK** button.

9 Click on the PDF choice in the pull-down list or the **Next** button. Do the following:

- a. **Required:** In the Directories containing PDFs field, type the one or more paths to the directory that contain your PDFs. For example:

`/u/your-ID/PDFs`

10 Click on the XKS choice in the pull-down list or the **Next** button. Do the following:

- a. In the Directory containing extended shelves field, type the path to the directory that contains your extended shelves. For example:

`/u/your-ID/xkshelves`

- b. Click on the **OK** button.

11 The SoftCopy Librarian window reappears with the following changes:

- The Sources and Repositories window now lists the repository that you just defined.
- A new Repository - *repository-name* window appears with the name you assigned.

You are done defining your repository. You can define additional repositories by repeating these instructions for each new repository.

When you have finished defining all your repositories, you are ready to create the catalog for your repositories. Continue with the instructions in Chapter 12.

Chapter 11. Setting Up a PC/LAN Repository

You must define at least one repository for the SoftCopy Librarian to be able to manage your softcopy files. This type of repository is intended for use with BookManager BookServer accessed from a workstation through a Web browser. The repository definition tells the SoftCopy Librarian where to look for softcopy. You can define a repository whether or not you already have bookshelves and books installed.

This chapter describes:

- Considerations to keep in mind before setting up your repository
- Instructions for preparing your PC or LAN server
- Defining the repository to the SoftCopy Librarian

Considerations for Setting Up Your Repository

Here are some things you need to know about your repository on LAN server or PC hard drives:

- You can define your repositories in several ways. For example:
 - Define a single repository in a single directory, into which you would put all your softcopy files.
 - Define a single repository in multiple directories.
 - All the shelf file types must be in the same directory.
 - File types can be either in separate directories or in combined directories
 - Define multiple repositories, provided they are each in separate directories from each other.
- If you already have files for a repository installed in multiple directories, you must delete them and reinstall them in a single directory.
- If you add or remove softcopy items from your repository without using the SoftCopy Librarian, you must recreate the catalog.

The SoftCopy Librarian will not recreate it automatically for you, and, therefore, it will not be able to recognize your changes.

Setup Required for Your Repository

If the repository is on a LAN, ensure you have read/write access to the necessary directories.

Defining a PC or LAN Server Repository

To define a repository on a PC or LAN server, do the following:

- 1** On your workstation, start the SoftCopy Librarian. (Refer to Chapter 5.)

2 In the Sources and Repositories window in the SoftCopy Librarian window, do the following:

- a. Click on File on the task bar.
- b. In the pull-down window that appears, click on the New choice.
- c. In the pop-up window that appears, click on the Repository choice.

The Repository Properties - New Repository window appears.

3 In the Repository Properties - New Repository window, do the following:

- a. Type a name for this new repository in the Repository Title field.

Note: The name you type here can be anything you want. It is the name that the SoftCopy Librarian uses on your workstation to refer to your repository.

- b. Select the Location and method of accessing your this repository by clicking on the **Local or network drive via COPY commands** button.
- c. Click on the File types tab or the **Next>** button.

The File types window appears.

4 In the File types window, do the following:

5 Click on the B00 choice in the pull-down list or the **Next** button. Do the following:

- a. **Required:** In the Directories containing books field, type the one or more paths to the directory that contain your books. For example:

`\u\your-ID\books`

6 Click on the BKI choice in the pull-down list or the **Next** button. Do the following:

- a. **Required:** In the Directory containing indexes field, type the path to the directory that contains your indexes. For example:

`\u\your-ID\indexes`

Note: This can be the same directory that contains your books.

7 Click on the BKS choice in the pull-down list or the **Next** button. Do the following:

- a. In the Directory containing shelves field, type the path to the directory that contains your bookshelves. For example:

`\u\your-ID\shelves`

- b. Click on the **OK** button.

8 Click on the PDF choice in the pull-down list or the **Next** button. Do the following:

- a. **Required:** In the Directories containing PDFs field, type the one or more paths to the directory that contain your PDFs. For example:

`\u\your-ID\PDFs`

- 9** Click on the XKS choice in the pull-down list or the **Next** button. Do the following:
- a. In the Directory containing extended shelves field, type the path to the directory that contains your extended shelves. For example:
`\u\your-ID\xkshelves`
 - b. Click on the **OK** button.

- 10** The SoftCopy Librarian window reappears with the following changes:
- The Sources and Repositories window now lists the repository that you just defined.
 - A new Repository - *repository-name* window appears with the name you assigned.

You are done defining your repository. You can define additional repositories by repeating these instructions for each new repository.

When you have finished defining all your repositories, you are ready to create the catalog for your repositories. Continue with the instructions in Chapter 12.

Chapter 12. Creating and Recreating the Catalog for Your Repository

This chapter describes:

- How the SoftCopy Librarian updates the catalog for your repository automatically when you use it to:
 - Transfer softcopy files to the repository
 - Perform routine maintenance on your repository.
- When and how you must erase the cache that the SoftCopy Librarian uses
- How you must create or recreate the catalog manually for your repositories after you:

- Set up the repository for the first time
- Make manual changes to the contents of your repositories

For example, you might have:

- Unloaded shelves, books, and indexes from tape directly into your repository
- Copied softcopy files manually into your repository
- Deleted softcopy files manually from your repository
- Change the definition of a repository
- Erased the cache used by the SoftCopy Librarian
- Receive certain errors that can cause a mismatch between the catalog and its repository.

Note: If you haven't already defined a repository on your host, you must define one before you can create a catalog for it. Refer to Chapter 8, Chapter 9, Chapter 10, or Chapter 11, for instructions before you continue.

If you are creating a catalog for the first time or recreating it after you have made manual changes to your repository, you can continue with the instructions in “Creating or Recreating the Catalog Manually” on page 48 below.

If you are routinely transferring shelves and associated publications to your repository or maintaining it, refer to “Updating Your Catalog Automatically.”

Updating Your Catalog Automatically

After you have set up your repository and created its catalog for the first time, you are ready to transfer shelves routinely as you receive them on CDs or as they appear on the IBM Web site.

When you transfer shelves using the SoftCopy Librarian, the catalog is updated automatically to reflect the changes the transfer made to the repository. You do not need to recreate the catalog. For routine transfers to your repositories, refer to Chapter 14 for instructions.

When you maintain your repositories using the SoftCopy Librarian, the catalog is also updated automatically for you. You do not need to recreate it. The SoftCopy Librarian allows deletion of old and out-dated files from your repositories. For day-to-day maintenance of your host repository, refer to Chapter 14 for more information.

Creating or Recreating the Catalog Manually

There are times when you must create or recreate a catalog manually for your repositories:

- If you are creating a catalog for the first time
- If you have made any manual changes to your repository or its contents.

To create a catalog for your new host repository or to recreate it, do the following:

- 1** On your workstation, start the SoftCopy Librarian.
- 2** In the Sources and Repositories window, do the following:
 - a. Select the repository for which you want to recreate its catalog.
 - b. Select the File option on the task bar.
 - c. In the File menu, select the Create catalog.

The creation of the catalog may take quite a while if there are many files in the repository. As the catalog is created or recreated, you will see several messages appear in the SoftCopy Librarian Messages window. The ones you may notice are:

```
⋮  
125 List started OK.
```

```
⋮  
Analyzing directory ...
```

The following set of messages appear for each shelf that is processed:

```
Processing shelf 0000 dataset-name ...  
⋮  
Adding shelf filename to catalog
```

A pop-up window appears with a message that the catalog has been created.

- 3** Click on the **OK** button.

The catalog is created and the SoftCopy Librarian window reappears.

In general, catalog creation:

- Lists in the catalog all files specified by the high-level qualifiers and directories.

- Reads the shelves to determine their contents.
Each time an index file is used in a shelf, the reference count for that file is incremented by 1. A file's reference count indicates how many shelves contain that file.
- Writes into the catalog, the list of files, and other information that is stored on the workstation.
- **For OS/390 Sequential Data Sets Only:** Creates a shelf list (BKLSHELF data set) and stores it on the host using the high-level qualifier you specified. This list contains the names of all the shelves that are being managed by the SoftCopy Librarian.

After you have created or recreated the catalog for your repository, you should define a default location from which you will be transferring softcopy files. Refer to the instructions in Chapter 13.

When and How to Erase the Cache That the SoftCopy Librarian Uses

A copy of each of your shelves is kept in the cache directory on your workstation. When the SoftCopy Librarian reads a Shelf, it reads it from the cache directory rather than transferring it from the repository. This saves accessing time.

If changes are made to the Shelf files in your repository, you must also erase the cache that the SoftCopy Librarian uses and then recreate the catalog for the repository. Otherwise, the SoftCopy Librarian will not be aware of the changes made and will read an older copy from the cache. These changes include:

- Editing a Shelf file to change the title.
Note: If you want to edit the title of the Shelf, you should use the `Edit Title` choice under the `Edit` option in the `Shelf` view.
- Rebuilding the Shelf without changing its file name

To help the SoftCopy Librarian keep track of these changes, do the following:

- 1** Start the SoftCopy Librarian.
- 2** In the `Sources` and `Repositories` window, do the following:
 - a. Select the repository you modified.
 - b. Select the `File` option on the task bar.
 - c. In the `File` menu, select the `Erase cache`.
 - d. Select the `File` option again on the task bar.
 - e. In the `File` menu, select the `Create catalog`.

Chapter 13. Identifying the Sources of Bookshelves That You Want to Transfer

Before you can transfer softcopy to your repository for the first time, you must identify their source to the SoftCopy Librarian. This chapter describes how to identify the sources from which you plan to transfer to your repositories routinely. The SoftCopy Librarian lets you define any of the following sources, which you can change at any time. You can define:

- A CD-ROM drive (for transferring from CD collections)
- An Internet Web site that supports the SoftCopy Librarian (for transferring from IBM PUBLIB and other Web sites)
- A LAN server hard drive (for transferring softcopy that was created or collected by various means)
- A local PC hard drive (for transferring softcopy that you created).

Note: Transferring from an Internet site is only available from Windows workstations, it is not available with OS/2 workstations.

Use the SoftCopy Librarian's Automatic check for updates function. This is available from the SoftCopy Librarian, choice in the Start menu or in the SoftCopy Librarian's Help. With this, you should be able to download from the Internet.

Identifying a CD Reader or Hard Drive as the Source for Bookshelves

To identify a source from which you want to transfer, do the following:

- 1** On your workstation, start the SoftCopy Librarian.
- 2** In the Sources and Repositories window, do the following:
 - a. Click the File choice on the task bar.
 - b. In the File menu, click New.
 - c. In the New menu, click Source.

The Source Properties - New Source window appears.

- 3** In the Source Properties - New Source window, do the following:
 - a. Type a name in the Source title field.

This can be any name you choose. The SoftCopy Librarian uses this name to identify this source on your workstation.
 - b. Identify the type of the source you want to use. Do one of the following:
 - **If you want to use a CD-ROM or hard drive as a source**, select the **Install softcopy from a CD or hard drive** button, supply the path to the drive in the Softcopy file path field.
 - **If you want to use an Internet site as a source**, select the **Install softcopy files from the Internet** button, and supply the URL of the Internet site in the URL address of Internet site field. The default

URL (<http://publib.boulder.ibm.com>) shown is the address of the IBM PUBLIB Web site.

Note: We do not generally recommend that you routinely use a Web site to maintain your repositories. Depending upon the speed of your Internet access, downloading can take substantially longer than transferring from CDs or a local hard drive.

If your Internet access is relatively slow, we recommend that you continue to use the IBM CD collections to set up your repositories initially and for your normal quarterly refreshes, and use the Internet only as follows:

- Between quarters to obtain any softcopy files that might have missed the collections.
- Near the end of the quarter to obtain a few critical softcopy files early prior to their release on the CD collections
- If you do not have access to the CD collections.

If you have high-speed Internet access, you can try maintaining your repositories each quarter from a Web site.

c. Click the **OK** button.

You are now ready to transfer from your CD reader, a hard drive, or the Internet to your repository. Continue with the instructions in Chapter 14

Chapter 14. Maintaining Your Repositories

This chapter describes how to transfer shelves, Books, PDFs and other publications to your repositories and maintain them.

You can:

- Maintain one or more repositories separately

You can transfer new and updated softcopy files to each repository and manually delete from each repository files that have newer replacements.

- Maintain one repository and several identical copies

If you need to create and maintain several, identical repositories, you can:

- Transfer to one repository and maintain it as a model so that you can transfer files to one or more repositories independently of each other, maintain them separately, but “synchronize” their contents.

Transferring Shelves to a Repository

You can update your repositories separately. That means you must go to each repository and make any changes that you want.

To begin the process of maintaining a repository, you should decide when it is appropriate to transfer to a repository.

You could choose to update a repository when you:

- Receive a new CD-ROM collection
- Notice that new or updated versions of softcopy files appear on your source Internet site

Note: If you have not defined the sources or repositories that you intend to use, refer to the instructions in Chapter 13 to define your sources or Chapter 8, “Setting Up a z/OS or OS/390 Host Repository Using Sequential Data Sets” on page 29 for more information, Chapter 9, Chapter 10, or Chapter 11 to define your repositories before you can continue. After you have defined your sources and repositories, return here and continue with these instructions.

When you are ready to update your repositories, you can do the following:

- 1** If you are using a CD-ROM source, insert the correct CD in your CD reader.
- 2** Start the SoftCopy Librarian.
- 3** The Source and Repositories window should appear.
If you had previously opened any of your source or repository windows, those windows will also be open.
- 4** Select the source from which you want to update your repository. Do one of the following:
 - **If the source window you want is not already open**, you can:

- a. Select it from the Sources and Repositories window by doing one of the following:

- Double click on the source you want to open
- Single click on the source you want to open and select Open from the File menu on the task bar.

The SCL Repository List window will appear with a list of your current repositories.

- b. In the SCL Repository List window, select the repository that you want to update from the source selected.

The SoftCopy Librarian will compare the contents of the source you selected with the repository you select in this window and will update the status of the items in the source. The updated status in the source window will indicate which items are potential candidates for updating the repository.

The source window you selected will open with updated status.

- **If your source window is already open, you can:**

- a. In the Source - *title* window, select Update Status: Compared to from the File menu.
- b. Select the repository that you want to update from the list of your current repositories.

The SoftCopy Librarian will compare the contents of that source with the repository you select and will update the status of the items in the source window. The updated status in the source window will indicate which items are potential candidates for updating the repository.

The source window you selected will open with updated status.

- 5** In the Source - *title* window, identify the items that you want to transfer to your repository.

You can filter the list to only show the items that are new or changed. Use the Show New/Updated choice in the Options menu in the source window.

You can sort the list so that all new and updated entries are clustered together. Single click on the heading of the Status column. The contents of the status column will be sorted alphabetically. All the “Updated,” “New,” “Installed,” and so on, entries to be grouped together in the same order (ascending or descending) as the Title column is sorted. If you click on the heading a second time it will change the sort to the opposite sort order. You can sort any of the other columns in the same way.

- 6** Select the items you want to transfer.

You can select and deselect shelves in several ways:

- **Select a single item:** Left click on any item.
This will deselect any other items that have been selected.
- **Select several items:** Press and hold the **Ctrl** key and left click on the items you want.

You can deselect in the same way.

- **Select all the items:** Use the `Select All` choice in the `Options` menu.
This choice is handy if you have filtered the list first to show only new and updated items.
- You can deselect all that you have selected with the `Deselect All` choice in the `Options` menu in the source window.

7 When you are satisfied with your selections, transfer the shelves that you selected to the repository you want to update.

You can transfer in the following ways:

- Use the `Send to` choice in the `File` menu in the source window
- Right click in the source window, select the `Send to` choice, and the repository that you want to update.

Note: If you have selected several, you must not release the **Ctrl** key before you right click or your choices will be deselected.

The `Repository - title` window for the repository you selected appears. The items you transferred now appear.

After you have transferred to a repository you can perform maintenance on the contents, that is, you can remove any old softcopy files that were replaced by new versions.

Maintaining a Repository

After you have transferred to your repositories, you can:

- Maintain each repository by removing old versions for which there are new replacements
- Maintain one repository as a model and transfer copies of the model to identical repositories.

Maintaining a Repository

When you are ready to maintain a repository, you can do the following:

1 In the `Repository - title` window, make sure that you are using the `Shelves` view.

Note: We recommend that you work from the `Shelves` view, and always delete books by deleting their shelves.

When you delete associated publications, if the reference count goes to 0, those associated publications are automatically deleted along with the shelf.

We recommend that you only use the `Files` to locate and delete “orphaned” associated publications. Orphans have a reference count of “0” in the list.

2 In the `Repository - title` window, identify the shelves that you want to delete.

Items that are potential candidates for deletion are identified by the filename of their newer version in the `Replaced by` column. For example:

Title	Filename	Replaced by
DB2 for OS/390 V5	dsnsh0f2	
QMF V3R1.1 for MVS	dsqms004	dsqms006
QMF V3R2 for MVS	dsqms006	dsqms007
QMF V3R3 for MVS	dsqms007	
DITTO V2 for MVS	dutba00	
⋮		
DataHub for OS/2 V2R1.0	emqsh003	
dpAccounting Manager/MVS R1.2	eoubks01	eoubks02
dpAccounting Manager/MVS	eoubks02	
OPC/ESA R2.0	eqq2bs00	eqq2bs02
OPC/ESA R2.1	eqq2bs02	
OPC/ESA R1R3.1	eqq3bs04	
CallPath CICS/MVS	eqzmsh00	

You can analyze the candidates in one of two ways:

- Simply sort the list so all shelves that can be replaced are clustered together. Single click on the heading of the Status column. The contents of the status column will be sorted alphabetically. All the “Replaced by” entries will be grouped together in the same order (ascending or descending) as the Title column is sorted. If you click on the heading a second time it will change the sort to the opposite sort order. You can sort any of the other columns in the same way. This method works; however, it may miss some shelves which do not follow the file naming conventions.
- We recommend that you use this, more thorough method. Sort on the Filename column. Scroll down to a row that has a filename in the Replaced by column. The filename in the Replaced by column should match the filename in the Filename column in the next row. For example:

Title	Filename	Replaced by
⋮		
dpAccounting Manager/MVS R1.2	eoubks01	eoubks02
dpAccounting Manager/MVS	eoubks02	

If the names in the Title column match, the newer file is actually a replacement for the older one. If the titles do not match, the file name of the apparent “newer” shelf probably does not conform to the file naming conventions and is not an actual replacement.

3 Select the items that you want to delete.

You can select and deselect in several ways:

- **Select a single item:** Left click on any item.
This will deselect any other items that have been selected.
- **Select several items:** Press and hold the **Ctrl** key and left click on the shelves you want.
You can deselect items out in the same way.
- **Select all the items:** Use the Select All choice in the Options menu.
- **Deselect all the items:** Use the Deselect All choice in the Options menu.

4 When you are satisfied with your selections, delete what you selected.

You can delete in the following ways:

- Use the Delete choice in the File menu in the repository window.
- Right click in the repository window and select the Delete choice.

Note: If you have selected several items, you must not release the **Ctrl** key before you right click or your choices will be deselected.

A confirmation window will appear.

5 In the confirmation window, click the **Yes** button.

The items you selected are removed from the repository.

After you have maintained your repository, you can use this repository as a model to create identical repositories.

Replacing or Excluding Associated Files

Occasionally, a Shelf in one of your repositories might be missing a Book. If that happens, you might see any of the following:

- A Shelf listed in one of your source windows has a status of “Partial” when compared to one of your repositories. The corresponding shelf in your repository is missing an associated file.
- A Shelf listed on the Shelves tab of one of your repositories appears in “red.” The Shelf is missing one or more books.
- A file listed on the Files tab of one of your repositories appears in “red.” The file is missing from its Shelf.

The reference count for a missing associated file is negative and the number indicates the number of shelves that are missing that file.

Title	Filename	Replaced by	Filetype	Count
⋮				
OS/390 V2R10 AS Configuration	asumwa20		BOOK	-2

Note: The shelves that are missing the book appear in “red” on the Shelves tab.

You can replace the missing associated files from the IBM PUBLIB server on the Internet or you can exclude the missing associated file permanently. Excluding a file here actually removes it from the Shelf. It will not be listed in your repository, and BookManager will not be able to find it in the Shelf.

Replacing Missing Books

To replace a missing associated file from the IBM PUBLIB server on the Internet, do the following:

- 1** Click on the Files tab.
- 2** Highlight the file (shown in red) that you want to replace.

- 3** Click on the Files choice on the menu bar.
- 4** In the Files menu, select Download from Internet.
The associated file is replaced and it and its shelf will no longer appear in “red.”

Excluding Missing Books

To exclude a missing associated file from its shelf, do the following:

- 1** Click on the Files tab.
- 2** Highlight the associated file that you want to exclude.
- 3** Click on the Files choice on the menu bar.
- 4** In the Files menu, select Exclude from shelf.
It will no longer appear in the list and the shelf will not appear in “red.”

Removing Orphaned Associated Publications

You might also want to identify and eliminate orphans. Orphaned documents files are not part of any shelf and, therefore, do not show up in a list when you want to locate and view files. They also take up space in your repository that you might need.

Note: While you can leave orphans in your repository, you can only view by opening them specifically by their filename.

To remove orphans, do the following:

- 1** Start the SoftCopy Librarian.
- 2** Open the Repository - *title* window for the repository that you want to review.
- 3** Click on the Files tab.
- 4** Look for books with a “0” reference count:

Title	Filename	Replaced by	Filetype	Count
⋮				
OS/390 V2R7 Encina Bookshelf	asumya10		BKSHELF	-
OS/390 V2R8 LANRES Install Gd	ewx1c205		BOOK	0
⋮				
IBM Softcopy Reader User's Gd	hlcrug01		BOOK	1

You can scroll down the list or you can sort the Count column in the list. Sorting will bring books with a reference count of 0 to the top of the list.

- 5** Highlight the orphans.
- 6** Click on the File choice on the menu bar.

7 In the File menu, choose Delete.

A confirmation window appears.

8 In the confirmation window, click the **Yes** button.

Cloning a Repository (Not Available)

You can use the ability to “clone” a repository to maintain identical copies of one repository that you are using as a model.

To clone, do the following:

1 Decide which repository that you want to use as the model.

2 Make sure that it contains the files you want in the clones.

3 Decide which repositories that you want as the clones.

You can:

- Use repositories that already exist and contain files.
- New repositories that do not contain any files.

Note: If any of your potential clones do not exist, you must define them first. Refer to Chapter 8, Chapter 9, Chapter 10, or Chapter 11 for instructions.

4 Select the model. Do one of the following:

- **If the repository window for the model is not already open**, you can select it from the Sources and Repositories window by single clicking on the repository you want and selecting Clone from the File menu on the task bar.
- **If your repository window is already open**, you can select Clone from the File menu in the repository window.

The SCL - Clone Repositories window will appear.

5 In the SCL - Clone Repositories window, select the repositories that you want to as the clones from the list of your current repositories.

6 Click the **OK** button.

A confirmation window appears.

7 In the confirmation window, click the **OK** button.

As you update your model, you can use the same process to “re-clone” your other repositories and keep them updated along with the model.

Synchronizing Repositories (Not Available)

You can use the ability to “synchronize” several repositories with each other. Synchronizing is useful if several individuals are maintaining different repositories and you must ensure that all their changes appear in all the repositories.

To synchronize repositories, do the following:

- 1** Decide which repositories that you want to synchronize.
- 2** Make sure that they contain the files you want in the all the repositories.
- 3** In the Sources and Repositories window, select Synchronize from the file menu.
The SCL - Repository List appears.
- 4** In the SCL - Repository List, select the repositories that you want to synchronize from the list of current repositories.
- 5** Click the **OK** button.

The contents of the repositories will be merged and they all will contain the same files.

Chapter 15. Creating/Managing Your Own Softcopy and Associated Publications

This chapter describes how you can create your own softcopy shelves and associated publications and manage them with the SoftCopy Librarian. It describes how to:

- Name your files so the SoftCopy Librarian can manage them
- Create an exception file if you need one to resolve naming differences
- Create shelves and associated publications
- Transfer from a non-IBM CD to your host repository
- Transfer from your hard drive to your host repository

Naming Your Files So the SoftCopy Librarian Can Manage Them

Background

IBM developed and uses a file naming convention as a way to produce and distribute softcopy files that would have unique names.

This naming scheme has three purposes.

1. It prevents us from overwriting our own files that we ship to you.
2. It helps to ensure that IBM files don't overwrite your files
3. It provides enough file information so the SoftCopy Librarian can manage shelves and associated publications.

As you know, IBM has reserved file names beginning with the letters A-I and Q for the files that we distribute. These conventions apply to both software and softcopy files. You are free to use the remaining letters for your filenames without fear that we will interfere with them. To ensure that this happens, all IBM software products are assigned a 3- or 4-character product ID. Hardware product and non-product related documents are assigned IDs reserved specifically for that purpose and these IDs serve the same function as product software product IDs. For example:

AFB VS FORTRAN

ADM GDDM

DSN DB2

IEA OS/390 MVS

How Files Are Named

All that having been said as background, the current naming scheme for softcopy documents is as follows:

PPP	BBB	R	S
-----	-----	---	---

 Or

PPPP	BB	R	S
------	----	---	---

Where:

- PPP or PPPP** Is the product ID or site assigned ID. This remains for the life of a version and is changed when there is a new product version. This is usually not applicable to non-product related documents, which usually retain their original for entire the life of the document.
- BBB or BB** Is the publication ID, which is unique in the product library. This remains for the life of the publication. When there is a new product version, this ID can be changed as well.
- Note:** The first 6 characters must remain unchanged for the life of the publication. For our product, the life begins with a new version of the product and ends when that version is replaced.
- R** Is a release identifier that denotes the release of the product. This number begins at 0 and is incremented by 1 up to 9 then to A and by one letter up to Z **each time the release number of the product is incremented.** This number or letter need not correspond with number of the release, it just needs to start at 0 and increment each time a new release is made available. This would not apply to non-product-related publications. For non-product publications this identifier should be set to 0 initially and should remain at 0 unless it is incremented because an older edition should remain available and may be updated along with the newer version.
- S** Is the sequence number that denotes level. This number begins at 0 and is incremented by 1 up to 9 then to A and by one letter up to Z each time the publication is updated.

This scheme is designed to prevent an older publication ending up with a higher sequence number than a newer one. It provides for up to 36 levels for any single release and for up to 36 releases of a product. Hopefully, this will accommodate most situations.

Note: Some older publications might follow an earlier naming scheme as follows:

PPP	BBB	SS	Or	PPPP	BB	SS
-----	-----	----	----	------	----	----

Because these filenames are currently created, maintained, and processed manually by the owners and the IBM Softcopy Center, over time and for various reasons, exceptions have crept into the practice of file naming. For example:

- Some filenames incorporate a release indicator somewhere in the book ID, which changes the ID over the life of the publication.
- Some filenames do not strictly increment the sequence number each update, resulting in a discontinuous series of numbers.
- Some filenames use only 7 character positions instead of 8.
- Some filenames only increment the last digit of the sequence number using the next to last for some other purpose.
- Some filenames for updates to older levels have ended up with a higher sequence number than the newer level.
- And some other variations.

What If Your Old Shelf Names Do Not Work with the New Conventions

Over time and for various reasons, your practice of naming your shelves might have created file names that are incompatible with the SoftCopy Librarian's conventions.

You might also have file naming exceptions for the following reasons:

- You are combining two or more shelves into one
- You are splitting a shelf into two or more shelves.

We strongly recommend that you convert your file names to the SoftCopy Librarian's conventions. If you are converting from your current naming convention, and, if for any reason, you have file names that cannot conform, you can create an exception file to identify which new file names replace the old file names. The SoftCopy Librarian uses this exception file to reconcile any naming differences when your customers transfer to their repository.

In general, you will need an exception file, whenever you have two related shelves, usually where one is a later version of the other, and:

- The first six characters of their file names do not match
The later file will appear to the SoftCopy Librarian as if it were unrelated to the earlier one.
- The first six characters match, but the last two characters (the sequence number or the "RS" value) of later file name are not numerically higher than the earlier one
The later file will appear to be older than the earlier one.

If you need an exception file, continue with the instructions in "Creating an Exception File."

Otherwise, continue with the instructions in "Creating Your Own Shelves and Associated Publications."

Creating an Exception File

You might need to create an exception file for any of the following reasons:

- **You have old file names that cannot be reconciled** with the new conventions, and you want to convert them.

The SoftCopy Librarian cannot determine from the file names that an updated Shelf is related to an older one that it replaces. For example:

Old Name	New Name
BAD1NAME.BKS	OKNAME00.BKS

The entry in the exception file would look like this:

```
OKNAME00.BKS BAD1NAME.BKS
```

Note: The first entry on each line is the file name of the new file. The second entry is the file name of one or more files that are replaced by the new Shelf. Each entry is separated by at least one blank character.

- **You are combining two or more shelves into one.**

The SoftCopy Librarian cannot decide which shelves are being replaced by the combined bookshelf. For example:

Old Names	New Name
ONEBKS02.BKS	UNIBKS00.BKS
TWOBKS02.BKS	

The entry in the exception file would like this:

```
UNIBKS00.BKS ONEBKS02.BKS TWOBKS02.BKS
```

You could, in this case, retain one of the old names for new file. For example, you could name the new file:

Old Names	New Name
ONEBKS02.BKS	ONEBKS03.BKS
TWOBKS02.BKS	

Then, your exception file would need an entry for only one of the old files. The entry in the exception file would like this:

```
ONEBKS03.BKS TWOBKS02.BKS
```

- **You are splitting a shelf into two or more files.**

The SoftCopy Librarian cannot decide which Shelf is being replaced by the new, separated shelves. For example:

Old Name	New Names
OLDBKS03.BKS	NEWONE00.BKS
	NEWTW000.BKS

The entries in the exception file would like this:

```
NEWONE00.BKS OLDBKS03.BKS  
NEWTW000.BKS OLDBKS03.BKS
```

You could, in this case, retain the old name for one of the two new files. For example, you could name them as:

Old Name	New Names
OLDBKS03.BKS	OLDBKS04.BKS
	NEWONE00.BKS

Then, your exception file would need only one entry for the Shelf with a completely new name. The entry in the exception file would like this:

```
NEWONE00.BKS OLDBKS03.BKS
```

To create an exception file, do the following:

- 1** Using an appropriate text or word processor, create a simple flat-text file with the name:

EBRSCL.EXC

Each line in this file represents the naming exception for one shelf.

- 2** For multiple shelves, enter each exception on a separate line.

The first entry on each line is the file name of the new Shelf. The second entry is the file name of one or more that are replaced by the new Shelf. Separate each entry by at least one blank character.

Your exception file might look like this:

```
OKNAME00.BKS BAD1NAME.BKS
UNIBKS00.BKS ONEBKS02.BKS TWOBKS02.BKS
NEWONE00.BKS OLDBKS03.BKS
NEWTWO00.BKS OLDBKS03.BKS
```

The entries in this example represent the changes:

- On the first line of the example, a new version of a file (OKNAME00.BKS) replaces an old version with an incompatible name (BADNAME1.BKS).
- On the second line of the example, two old files (ONEBKS02.BKS and TWOBKS02.BKS) have been combined into a single new file (UNIBKS00.BKS), and the new file replaces both older ones.
- On the third and fourth lines of the example, an old file (OLDBKS03.BKS) has been split into two new files (NEWONE00.BKS and NEWTWO00.BKS), and both new files replace the old one.

3 For workstation users: Copy the exception file that you want on the media to the \SCRT\EXCEPT directory.

For host terminal users: Download the exception file to the \SCRT\EXCEPT directory on the workstation you will use to create the media.

Note: You must download the exception file as an ASCII file.

You are now ready to build the BookManager versions of the files you intend to distribute and to create shelves and indexes for them.

Creating Your Own Shelves and Books with BookManager

To create BookManager books and shelves, do the following:

- 1** Create a naming scheme for your books, shelves, and indexes that generally conforms to the file naming conventions described in “Naming Your Files So the SoftCopy Librarian Can Manage Them” on page 61.
Note: You can use any first six characters you choose. Ensure that the first character does not conflict with the letters that IBM uses. You must adhere to the conventions for the last two characters.
- 2** Using an appropriate text or word processor, create source files for your books that are acceptable to a BookManager BUILD program. Refer to the BookManager BUILD for Windows manuals for the source coding that is acceptable.
- 3** Format your books for viewing using a BookManager BUILD program. Refer to the BookManager BUILD for Windows manuals for instructions on building books.
- 4** Decide how you are going to organize your books into shelves.
- 5** Create a Shelf and Index for each set of books you want in a separate Shelf.
- 6** Use the same filename for the Shelf and the Shelf Index. Refer to the BookManager BUILD for Windows manuals for instructions on creating shelves and indexes.

7 Use Softcopy Reader Organizer or Library Server to build a Shelf containing the new Books and Index.

For BUILD for Windows users: After you have built your books and created your shelves and indexes, you are ready to transfer them to your host repository. Refer to Chapter 13 and Chapter 14 for instructions on setting your default source location and transferring your files.

For BUILD/MVS users: If you built you books, shelves, and indexes on your OS/390 host and you are using a host repository, you can copy your files directly into host repository. Refer to Appendix D for instructions on manually updating your host repository and recreating its catalog.

Appendix A. Permitting More Than One Person to Maintain Your Repositories

Installing SoftCopy Librarian on a server allows several customers, through shared access, the ability to maintain the same repositories.

- 1** Install the SoftCopy Librarian in a directory which is on a drive shared by all customers with whom you want to be able to maintain your repositories.
All customers must have read/write access and authorized IDs to the shared drive.
- 2** Have one of the customers access the shared directory and do the following:
 - a. Start the SoftCopy Librarian.
 - b. In the *First time* window, if there are any files to be migrated, migrate them now.
 - c. Define their (the customer's) CD-ROM drive letter.
- 3** Have each of the other customers, start the SoftCopy Librarian.
- 4** In the *First time* window, do not attempt to migrate any repositories, but have your customers define their default CD-ROM drive letter.
- 5** For any repositories that will require FTP for processing, have your customers update the *Repositories Properties - FTP Logon Information* window with their userid and password. This information will be maintained at the individual workstation level.

Each customer will have their own sources but will be able to share access to and maintain the same repositories. They each can create new repositories, and the repositories will be accessible to everyone.

Because there is no file locking, only one customer should work with a repository at a time. This is a manual enqueue/dequeue procedure.

Appendix B. Changing the Definition of Your Repository

You can change the definition of a repository for several reasons:

- You may want to change the following attributes of your repository:
 - High-level qualifiers or directories
 - SMS classes
 - DASD device
 - DASD volume
 - FTP site commands
- You may want to share the administration of your repository with others

Changing the Attributes of Your Repository

To change any of the attributes of a host repository that you previously defined, do the following:

- 1** Start the SoftCopy Librarian.
- 2** From the Sources and Repository window - select a Repository to update.
- 3** Select File, then Properties.
- 4** The Repository Properties - Repository Name window appears.
 - Make your changes in the windows and select **OK**.
- 5** If you change the following items in the definition of your repository:
 - The location of the repository (HLQs or directories)

Then in the SoftCopy Librarian panel, you must recreate the catalog for your repository:

- From the Sources and Repository window - select a Repository to update.
- Select File, then Create Catalog.

Appendix C. Deleting a Repository

To delete the softcopy files and the repository definition, do the following:

- 1** Start the SoftCopy Librarian.
- 2** From the Sources and Repositories window:
 - a** Select a repository to delete.
 - b** Select File, Open
- 3** In the Repository - Title window:
 - a** Select options, select ALL to highlight all the shelves
 - b** Select File, Delete.
 - c** In the Confirmation window, select **Yes**

The shelves and files should disappear from the Repository - Title window.

- 4** Return to the Sources and Repositories window and do the following:
 - a** Select the repository to delete.
 - b** Select File, Delete
 - c** In the confirmation window, select **Yes**.

The repository will disappear from the Sources and Repositories window.

To delete only the repository definition, do the following:

- 1** Start the SoftCopy Librarian.
- 2** From the Sources and Repositories window:
 - a** Select a repository to delete.
 - b** Select File, Delete
 - c** In the confirmation window, select **Yes**.

The repository will disappear from the Sources and Repositories window.

Appendix D. Managing Changes to Your Repository

This appendix explains how the SoftCopy Librarian can help you manage:

- Shelves and associated publications that you unload from tape or copy directly into your repository.
- Changes made to the shelves in your repository.

Unloading or Copying Softcopy Files from Tape or other Sources

When unloading softcopy files from tape or other sources, complete the following steps so that these files can be managed by SoftCopy Librarian.

- 1** Make sure that you have followed the procedures for setting up your host and defining your host repository to the SoftCopy Librarian described in Chapter 8, "Setting Up a z/OS or OS/390 Host Repository Using Sequential Data Sets" on page 29.
- 2** Unload the tapes or copy the files to the HLQ or directory that you are using for your repository.
- 3** Start the SoftCopy Librarian.
- 4** In the SoftCopy Librarian window, do the following:
 - a. In the Sources and Repository window, select the repository you updated.
 - b. Select File, create catalog.

When the catalog has been created, the update is complete.

Shelf Changes in Your Repository

If any additions or changes to the files in your repository are made outside of SoftCopy Librarian, then you must erase the cache that the SoftCopy Librarian uses and recreate the catalog for the repository.

To help the SoftCopy Librarian keep track of these changes, do the following:

- 1** Start the SoftCopy Librarian.
- 2** In the Sources and Repository window, select the repository to be updated.
- 3** Select File, erase cache.
 - At the Confirm Dialog window, select **Yes**.Cache will be erased and the Catalog Function will be performed.

When the catalog has been created, the update is complete.

Appendix E. Summary of Changes Made in Previous Editions

This appendix summarizes the major changes made in the previous editions.

Changes made to the Sixteenth Edition

Updates made to the following areas:

- Updated the IBM Web site for downloading the latest version of SoftCopy Librarian
- Included miscellaneous editorial updates

Changes made to the Fifteenth Edition

Updates made to the following areas:

- Hardware and software requirements
- Information about Library Server
- Updates to how PDF files are handled
- Updates to "Maintaining Your Repositories"

Changes made to the Fourteenth Edition

Updates made to the following areas:

- Hardware and software requirements
- Internet connection
- Migration from previous versions of SoftCopy Librarian

Changes made to the Thirteenth Edition

Removed support for Windows NT 4.0, and replaced the URL for the IBMLink Web site. editions of the *SoftCopy Librarian: User's Guide*.

Changes made to the Twelfth Edition

Made terminology changes regarding the new "Extended Shelf" architecture.

Changes Made in the Eleventh Edition

- Updates to Appendixes A through D. Clarifications were made to the procedures relating to working with repositories, such as:
 - More than one person maintaining your repository
 - Changing the definition of your repository
 - Deleting a repository
 - Managing changes to your repository

Changes Made in the Tenth Edition

- SoftCopy Librarian can handle shelves and associated publications created by OEM companies that use one of the IBM BookManager Build products.
- Updated IBM Web and e-Mail addresses for support and free downloads.
- Corrected directory path statement syntax in several examples
- Elimination of "EBRMGMT" as the default HLQ for the Shelf List (BKLSHELF) and establishing this field as a required entry.

Changes Made in the Ninth Edition

- Miscellaneous editorial updates.

Changes Made in the Eight Edition

- The SoftCopy Librarian has been rewritten in Java.
- A new user interface lets you display multiple source windows and multiple repository windows simultaneously. Refer to Chapter 14.
- You can transfer files directly between source and repository windows and between repository windows. Refer to Chapter 14.

Changes Made in the Seventh Edition

New Information

- The code for the current version of the SoftCopy Librarian is now located in the \SCL directory on the CDs in the IBM Online Library. Refer to Chapter 4.
- In the OS/390 Collection the SoftCopy Librarian is now located on the "Tools" disc. Refer to Chapter 4.
- Buttons for selecting the source have been added to the Transferring softcopy to the repository choice in the main menu of the SoftCopy Librarian window.

Changes Made in the Sixth Edition

New Information

- Information on maintaining your repositories from IBM's and other Web sites have been added. Refer to Chapter 1.
- Procedures for defining the IBM PUBLIB and other Web sites as the source to transfer have been added. Refer to Chapter 13.
- Procedures for transferring files from the IBM PUBLIB and other Web sites to your repositories have been added.

Changes Made in the Fifth Edition

New Information

- Procedures for installing and starting the OS/2 version of the SoftCopy Librarian have been included. Refer to Chapter 4 and Chapter 5 for more information.
- Minor changes for using the OS/2 SoftCopy Librarian have been made throughout.
- A method for automatically checking if a later version of the SoftCopy Librarian is available from the IBM Web site has been added to the Windows version of the SoftCopy Librarian. Refer to Chapter 4 for more information.

Changes Made in the Fourth Edition

New Information

- A check box that permits you to ignore a descriptor file that contains errors on a CD has been added to the SCL Setup - Location of Files to Install window. Refer to Chapter 13 for more information.
- Two new choices that control whether the **Ctrl** key is required to make additional selections have been added to the Options in SCRT - Shelves View and SCRT - Files View windows. The Extended Selection choice requires the use of the **Ctrl** key and the Multiple Selection choice does not require the use of the **Ctrl** key.

Changes Made in the Third Edition

New Information

- Information describing how to use the “cache erase” function when you make manual changes to the contents of your repository. Refer to Chapter 12 for more information.
- Information has been added on the automatic creation of a descriptor file for non-IBM CDs.
- Information describing how to exclude “missing” files from the shelves in your repository has been added. Refer to Chapter 14 for more information.
- A new section has been added describing how to create an exception file. Refer to “Creating an Exception File” on page 63 for more information.
- A new appendix has been added describing how to change to your repository definition and how to permit more than one user to maintain your repository through the use of shared work files. Refer to Appendix B for more information.
- A new appendix has been added describing how to remove a repository. Refer to Appendix C for more information.
- A new appendix has been added for independent software vendors (ISVs) who want to package and distribute product documentation enabled for the SoftCopy Librarian.

Changed Information

- The method for defining host repositories using OS/390 sequential data sets has been significantly revised. Refer to Chapter 8 for more information.
- The chapter on defining host repositories has been split into two chapters, one for repositories using OS/390 sequential data sets and one for repositories using the hierarchical file system of OS/390 UNIX System Services. Refer to Chapter 8 and Chapter 9 for more information.
- The chapter on creating exceptions files has been combined with the chapter on creating and managing your own shelves and associated publications. Chapter 15 for more information.
- Because the SoftCopy Librarian now has the ability to automatically create descriptor files, the chapter on creating descriptor files has been deleted from this edition.
- The chapter on distributing on media your product bookshelves and books to your customers has been expanded and made into an appendix.
- Minor editorial changes have been made throughout this manual.

Changes Made in the Second Edition

New Information

- Hardware requirements for a repository on a LAN server or PC workstation has been added. Refer to Chapter 2 for more information.
- A new chapter has been added describing how to set up repositories on LAN servers and PC workstations. Refer to Chapter 11 for more information.
- Information on editing names from the repository maintenance facility has been added. Refer to Chapter 14 for more information.

Changed Information

- New Web site for downloading the SoftCopy Librarian code. Refer to Chapter 1 for more information.
- The information on defining an OS/390 host repository has been reorganized. Refer to Chapter 8 for more information.
- The section describing how to install the SoftCopy Librarian has been revised. Refer to Chapter 4 for more information.
- The information describing how to start the SoftCopy Librarian has been reorganized. Refer to Chapter 4 for more information.
- The information on using tapes has been moved into an appendix. Refer to Appendix D for more information.

Technical changes or additions to the text and illustrations in this edition are indicated by a vertical line (|) to the left of the change.

Index

C

catalog
 creating for host repository 47

D

description of SoftCopy Librarian 1

F

functions of the SoftCopy Librarian 4

H

host repository
 creating catalog for 47
 requirements 5

I

installing
 SoftCopy Librarian 11
Internet connection
 setting up 25
introducing the SoftCopy Librarian 1

M

maintaining host repository 53
managing your own shelves and books 61
migrating
 from previous versions 27

O

overview of SoftCopy Librarian 4

P

planning for repositories 7

R

repositories
 planning for 7
requirements
 host repository 5

S

S/390 Service Update Facility
 system requirements 5

SCRT

 workstation requirements 5
setting up a host HFS repository
 for SoftCopy Librarian 36
setting up host repository
 for SoftCopy Librarian 30
setting up PC/LAN repository
 for SoftCopy Librarian 43
setting up Unix server repository
 for SoftCopy Librarian 39
SoftCopy Librarian
 books on tape 73
 creating catalog for host repository 47
 functions of 4
 general description of 1
 host repository requirements 5
 installation 11
 introducing 1
 maintaining host repository 53
 managing your own shelves and books 61
 migrating from previous versions 27
 OS/390 host repository setup
 in an HFS 35
 in sequential data sets 29
 OS/390 setup
 in sequential data sets 69
 overview 4
 PC/LAN setup 43
 planning for repositories 7
 setting up a host HFS repository 36
 setting up a proxy 25
 setting up host repository 30
 setting up Internet connection 25
 setting up PC/LAN repository 43
 setting up Unix server repository 39
 starting 15
 Unix-like setup 39
 uploading to host repository 51
 workstation requirements 5
 z/OS host repository setup
 in an HFS 35
 in sequential data sets 29
starting
 the SoftCopy Librarian 15

U

uploading
 to the host repository 51

W

workstation requirements

for SCRT 5

SoftCopy Librarian 5

Do You Have Questions, Problems, or Comments?

The IBM SoftCopy Librarian is a free tool, supported through e-Mails as time permits. For support, send a note explaining your question, problem, or comment to: bookmgr@us.ibm.com

The IBM SoftCopy Librarian software can be downloaded without charge from the IBM Bookmanager Web Site <http://www-3.ibm.com/software/office/bkmgr/>.

IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.



Program Number: 5648-032

Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

GC23-3414-15

