

Interactive System Productivity Facility (ISPF)



Reference Summary

z/OS Version 1 Release 2.0

Interactive System Productivity Facility (ISPF)



Reference Summary

z/OS Version 1 Release 2.0

Note

Before using this document, read the general information under "Notices" on page 177.

Second Edition (October 2001)

This edition applies to ISPF for Version 1 Release 2 of the licensed program z/OS (program number 5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications by phone or fax. IBM Software Manufacturing Solutions takes publication orders between 8:30 a.m. and 7:00 p.m. eastern standard time (EST). The phone number is (800) 879-2755. The fax number is (800) 284-4721.

You can also order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

A form for comments appears at the back of this publication. If the form has been removed, and you have ISPF-specific comments, address your comments to:

International Business Machines Corporation
Software Reengineering
Department G7IA / Building 503
Research Triangle Park, NC 27709-9990

FAX (United States & Canada): 1+800+227-5088
IBMLink (United States customers only): CIBMORCF@RALVM17
IBM Mail Exchange: USIB2HPD@VNET.IBM.COM
Internet: USIB2HPD@VNET.IBM.COM

If you would like a reply, be sure to include your name, address, telephone number, or FAX number.

Make sure to include the following in your comment or note:

Title and order number of this book
Page number or topic related to your comment

The ISPF development team maintains a site on the World-Wide Web. The URL for the site is:
<http://www.software.ibm.com/ad/ispf>

© Copyright International Business Machines Corporation 1989, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Preface	xi	Return Codes	24
Who Should Use This Book	xi	EDIF - Edit Interface	24
Chapter 1. ISPF General Information	1	Command Invocation Format	24
Invoking an ISPF Application	1	Call Invocation Format	25
Invoking the ISPF Conversion Utility	1	Return Codes	25
ISPF System Information	2	EDIREC - Initialize Edit Recovery	25
Dialog Test Commands	5	Command Invocation Format	25
Message Definitions	5	Call Invocation Format	26
Skeleton Control Statements	5	Return Codes	26
Panel Definitions	6	EDIT - Edit a Data Set	26
PDF Browse Primary Commands	9	Command Invocation Format	26
PDF Member List Commands	10	Call Invocation Format	27
Primary Commands	10	Return Codes	27
Line Commands	10	EDREC - Specify Edit Recovery Handling	27
PDF Data Set List Commands	11	Command Invocation Format	27
Primary Commands	11	Call Invocation Format	27
Line Commands	12	Return Codes	27
PDF Edit and View Commands	12	FILESTAT - Statistics for a file	28
Primary Commands	12	Command Invocation Format	28
Line Commands	16	Call Invocation Format	28
Search Strings	17	Return Codes	28
Chapter 2. ISPF Service Syntax with		FILEXFER - Upload or download file	28
Return Codes	19	Command Invocation Format	28
Syntax Notation	19	Call Invocation Format	28
ISPEXEC Command Invocation	19	Return Codes	28
ISPEXEC Parameter Conventions	19	FTCLOSE - End File Tailoring	29
The ISPLINK Interface	19	Command Invocation Format	29
CALL ISPLINK Parameters	20	Call Invocation Format	29
The ISPEXEC Interface	20	Return Codes	29
CALL ISPEXEC Parameters	20	FTERASE - Erase File Tailoring Output	29
ADDPOP - Start Pop-Up Window Mode	20	Command Invocation Format	29
Command Invocation Format	20	Call Invocation Format	30
Call Invocation Format	21	Return Codes	30
Return Codes	21	FTINCL - Include a Skeleton	30
BRIF - Browse Interface	21	Command Invocation Format	30
Command Invocation Format	21	Call Invocation Format	30
Call Invocation Format	21	Return Codes	30
Return Codes	21	FTOPEN - Begin File Tailoring	30
BROWSE - Browse a Data Set	22	Command Invocation Format	30
Command Invocation Format	22	Call Invocation Format	30
Call Invocation Format	22	Return Codes	30
Return Codes	22	GETMSG - Get a Message	31
CONTROL - Set Processing Modes	22	Command Invocation Format	31
Command Invocation Format	22	Call Invocation Format	31
Call Invocation Format	23	Return Codes	31
Return Codes	23	GRERROR - Graphics Error Block Service	31
DISPLAY - Display Panels and Messages	23	Command Invocation Format	31
Command Invocation Format	23	Call Invocation Format	31
Call Invocation Format	24	Return Codes	31
Return Codes	24	GRINIT - Graphics Initialization	32
DSINFO - Data Set Information Dialog	24	Command Invocation Format	32
Command Invocation Format	24	Call Invocation Format	32
Call Invocation Format	24	Return Codes	32
		GRTERM - Graphics Termination Service	32
		Command Invocation Format	32
		Call Invocation Format	32

Return Codes.	32	Call Invocation Format	41
LIBDEF - Allocate Application Libraries	32	Return Codes.	41
Command Invocation Format	32	LMMDEL - Delete a Member from a Data Set	41
Call Invocation Format	33	Command Invocation Format	41
Return Codes.	33	Call Invocation Format	41
LIST - Write Lines to the List Data Set	33	Return Codes.	41
Command Invocation Format	33	LMMDISP - Member List Service	42
Call Invocation Format	33	Display Option	42
Return Codes.	33	GET Option	43
LMCLOSE - Close a Data Set	34	PUT Option	43
Command Invocation Format	34	ADD Option	44
Call Invocation Format	34	DELETE Option	44
Return Codes.	34	FREE Option	45
LMCOMP - Compresses a Partitioned Data Set	34	LMMFIND - Find a Library Member	46
Command Invocation Format	34	Command Invocation Format	46
Call Invocation Format	34	Call Invocation Format	46
Return Codes.	34	Return Codes.	46
LMCOPY - Copy Members of a Data Set	34	LMMLIST - List a Library's Members.	46
Command Invocation Format	34	Command Invocation Format	46
Call Invocation Format	35	Call Invocation Format	47
Return Codes.	35	Return Codes.	47
LMDDISP - Data Set Display Service	35	LMMOVE - Move Members of a Data Set	47
Command Invocation Format	35	Command Invocation Format	47
Call Invocation Format	35	Call Invocation Format	47
Return Codes.	36	Return Codes.	48
LMDENQ - Return ENQs	36	LMMREN - Rename a Data Set Member.	48
Command Invocation Format	36	Command Invocation Format	48
Call Invocation Format	36	Call Invocation Format	48
Variables Returned in Each Row of the Table	36	Return Codes.	48
Return Codes.	37	LMMREP - Replace a Member of a Data Set	49
LMDFREE - Free a Data Set List	37	Command Invocation Format	49
Command Invocation Format	37	Call Invocation Format	49
Call Invocation Format	37	Return Codes.	49
Return Codes.	37	LMMSTATS - Set and Store ISPF Statistics	49
LMDINIT - Initialize a Data Set List	37	Command Invocation Format	49
Command Invocation Format	37	Call Invocation Format	49
Call Invocation Format	37	Return Codes.	50
Return Codes.	37	LMOPEN - Open a Data Set.	50
LMDLIST - List a Data Set	38	Command Invocation Format	50
Command Invocation Format	38	Call Invocation Format	50
Call Invocation Format	38	Return Codes.	50
Return Codes.	38	LMPRINT - Print a Partitioned or Sequential Data Set	51
LMERASE - Erase a Data Set	38	Command Invocation Format	51
Command Invocation Format	38	Call Invocation Format	51
Call Invocation Format	38	Return Codes.	51
Return Codes.	39	LMPUT - Write a Logical Record to a Data Set	51
LMFREE - Free Data Set from its Association with Data ID.	39	Command Invocation Format	51
Command Invocation Format	39	Call Invocation Format	51
Call Invocation Format	39	Return Codes.	52
Return Codes.	39	LMQUERY - Give a Dialog Information about a Data Set	52
LMGET - Read a Logical Record from a Data Set.	39	Command Invocation Format	52
Command Invocation Format	39	Call Invocation Format	52
Call Invocation Format	40	Return Codes.	52
Return Codes.	40	LMRENAME - Rename an ISPF Library.	53
LMINIT - Generate a Data ID for a Data Set	40	Command Invocation Format	53
Command Invocation Format	40	Call Invocation Format	53
Call Invocation Format	40	Return Codes.	53
Return Codes.	40	LOG - Write a Message to the Log Data Set	53
LMMADD - Add a Member to a Data Set	41	Command Invocation Format	53
Command Invocation Format	41		

Call Invocation Format	53	Return Codes.	63
MEMLIST - Member List Dialog	54	TBEXIST - Determine Whether a Row Exists in a Table	63
Command Invocation Format	54	Command Invocation Format	63
Call Invocation Format	54	Call Invocation Format	63
Return Codes.	54	Return Codes.	63
PQUERY - Obtain Panel Information	54	TBGET - Retrieve a Row from a Table	63
Command Invocation Format	54	Command Invocation Format	63
Call Invocation Format	54	Call Invocation Format	64
Return Codes.	55	Return Codes.	64
QBASELIB - Query Base Library Information	55	TBMOD - Modify a Row in a Table	64
Command Invocation Format	55	Command Invocation Format	64
Call Invocation Format	55	Call Invocation Format	64
Return Codes.	55	Return Codes.	64
QLIBDEF - Query LIBDEF Definition Information	55	TBOPEN - Open a Table	65
Command Invocation Format	55	Command Invocation Format	65
Call Invocation Format	55	Call Invocation Format	65
Return Codes.	55	Return Codes.	65
REMPop - Remove a Pop-Up Window	56	TBPUT - Update a Row in a Table.	65
Command Invocation Format	56	Command Invocation Format	65
Call Invocation Format	56	Call Invocation Format	65
Return codes	56	Return Codes.	65
SELECT - Select a Panel or Function	56	TBQUERY - Obtain Table Information	66
Command Invocation Format	56	Command Invocation Format	66
Call Invocation Format	56	Call Invocation Format	66
Return Codes.	57	Return Codes.	66
SETMSG - Set Next Message	57	TBSARG - Define a Search Argument.	66
Command Invocation Format	57	Command Invocation Format	66
Call Invocation Format	58	Call Invocation Format	66
Return Codes.	58	Return Codes.	66
TBADD - Add a Row to a Table	58	TBSAVE - Save a Table	67
Command Invocation Format	58	Command Invocation Format	67
Call Invocation Format	58	Call Invocation Format	67
Return Codes.	58	Return Codes.	67
TBBOTTOM - Set the Row Pointer to Bottom	59	TBSCAN - Search a Table.	67
Command Invocation Format	59	Command Invocation Format	67
Call Invocation Format	59	Call Invocation Format	67
Return Codes.	59	Return Codes.	67
TBCLOSE - Close and Save a Table	59	TBSKIP - Move the Row Pointer	68
Command Invocation Format	59	Command Invocation Format	68
Call Invocation Format	59	Call Invocation Format	68
Return Codes.	59	Return Codes.	68
TBCREATE - Create a New Table	60	TBSORT - Sort a Table.	68
Command Invocation Format	60	Command Invocation Format	68
Call Invocation Format	60	Call Invocation Format	68
Return Codes.	60	Return Codes.	68
TBDELETE - Delete a Row from a Table.	60	TBSTATS - Retrieve Table Statistics	69
Command Invocation Format	60	Command Invocation Format	69
Call Invocation Format	60	Call Invocation Format	69
Return Codes.	60	Return Codes.	69
TBDISPL - Display Table Information.	61	TBTOP - Set the Row Pointer to the Top.	69
Command Invocation Format	61	Command Invocation Format	69
Call Invocation Format	61	Call Invocation Format	70
Return Codes.	61	Return Codes.	70
TBEND - Close a Table without Saving	62	TBVCLEAR - Clear Table Variables	70
Command Invocation Format	62	Command Invocation Format	70
Call Invocation Format	62	Call Invocation Format	70
Return Codes.	62	Return Codes.	70
TBERASE - Erase a Table	63	TRANS - Translate Data from One Coded Character Set Identifier (CCSID) to Another	70
Command Invocation Format	63	Command Invocation Format	70
Call Invocation Format	63	Call Invocation Format	70

Return Codes.	71	Assignment Statement Syntax	79
VCOPY - Create a Copy of a Variable	71	Return Codes.	79
Command Invocation Format	71	AUTONUM - Set or Query Autonum Mode	79
Call Invocation Format	71	Macro Command Syntax	79
Return Codes.	71	Assignment Statement Syntax	79
VDEFINE - Define Function Variables	71	Return Codes.	79
Command Invocation Format	71	AUTOSAVE - Set or Query Autosave Mode	79
Call Invocation Format	71	Macro Command Syntax	79
Return Codes.	71	Assignment Statement Syntax	79
VDELETE - Remove a Definition of Function		Return Codes.	80
Variables	72	BLKSIZE - Query the Block Size	80
Command Invocation Format	72	Assignment Statement Syntax	80
Call Invocation Format	72	Return Codes.	80
Return Codes.	72	BOUNDS - Set or Query the Edit Boundaries	80
VERASE - Remove Variables from Shared and/or		Macro Command Syntax	80
Profile Pool	72	Assignment Statement Syntax	80
Command Invocation Format	72	Return Codes.	80
Call Invocation Format	72	BROWSE - Browse from within an Edit Session	80
Return Codes.	72	Macro Command Syntax	80
VGET - Retrieve Variables from a Pool or Profile	72	Return Codes.	80
Command Invocation Format	72	BUILTIN - Process a Built-In Command	80
Call Invocation Format	72	Macro Command Syntax	80
Return Codes.	73	Return Codes.	81
VIEW - View a Data Set	73	CANCEL - Cancel Edit Changes	81
Command Invocation Format	73	Macro Command Syntax	81
Call Invocation Format	73	Return Codes.	81
Return Codes.	74	CAPS - Set or Query Caps Mode	81
VIIF - View Interface	74	Macro Command Syntax	81
Command Invocation Format	74	Assignment Statement Syntax	81
Call Invocation Format	74	Return Codes.	81
Return Codes.	74	CHANGE - Change a Search String	81
VMASK - Associate an Edit Mask with a Dialog		Macro Command Syntax	81
Variable	75	Return Codes.	81
Command Invocation Format	75	CHANGE_COUNTS - Query Change Counts	82
Call Invocation Format	75	Assignment Statement Syntax	82
Return Codes.	75	Return Codes.	82
VPUT - Update Variables in the Shared or Profile		COMPARE - Compare Data Set.	82
Pool	75	Macro Command Syntax	82
Command Invocation Format	75	Return Codes.	82
Call Invocation Format	75	COPY - Copy Data	82
Return Codes.	75	Macro Command Syntax	82
VREPLACE - Replace a Variable	76	Return Codes.	82
Command Invocation Format	76	CREATE - Create a Data Set Member.	82
Call Invocation Format	76	Macro Command Syntax	82
Return Codes.	76	Return Codes.	82
VRESET - Reset Function Variables	76	CTL_LIBRARY - Query Controlled Library Status	83
Command Invocation Format	76	Assignment Statement Syntax	83
Call Invocation Format	76	Return Codes.	83
Return Codes.	76	CURSOR - Set or Query the Cursor Position	83
WSCON — Connect to a Workstation	76	Assignment Statement Syntax	83
Command Invocation Format	76	Return Codes.	83
Call Invocation Format	77	CUT — Cut and Save Lines	83
Return Codes.	77	Assignment Statement Syntax	83
WSDISCON — Connect to a Workstation	77	Return Codes.	83
Command Invocation Format	77	DATA_CHANGED - Query the Data Changed	
Call Invocation Format	77	Status	83
Return Codes.	77	Assignment Statement Syntax	83
		Return Codes.	83
Chapter 3. Edit Macro Commands	79	DATA_WIDTH - Query Data Width	84
AUTOLIST - Set or Query Autolist Mode	79	Assignment Statement Syntax	84
Macro Command Syntax	79	Return Codes.	84

DATAID - Query Data ID	84	Return Codes.	89
Assignment Statement Syntax	84	LEFT - Scroll Left	90
Return Codes.	84	Macro Command Syntax	90
DATASET - Query the Current Data Set Name	84	Return Codes.	90
Assignment Statement Syntax	84	LEVEL - Set or Query the Mod Level Number.	90
Return Codes.	84	Macro Command Syntax	90
DEFINE - Define a Name.	84	Assignment Statement Syntax	90
Macro Command Syntax	84	Return Codes.	90
Return Codes.	84	LINE - Set or Query a Line from the Data Set	90
DELETE - Delete Lines	85	Assignment Statement Syntax	90
Macro Command Syntax	85	Return Codes.	90
Return Codes.	85	LINE_AFTER - Add a Line to the Current Data Set	91
DISPLAY_COLS - Query Display Columns	85	Assignment Statement Syntax	91
Assignment Statement Syntax	85	Return Codes.	91
Return Codes.	85	LINE_BEFORE - Add a Line to the Current Data Set	91
DISPLAY_LINES - Query Display Lines	85	Assignment Statement Syntax	91
Assignment Statement Syntax	85	Return Codes.	91
Return Codes.	85	LINE_STATUS - Query Source and Change Information for a Line in a Data Set	91
DOWN - Scroll Down	85	Assignment Statement Syntax	91
Macro Command Syntax	85	Return Codes.	91
Return Codes.	85	LINENUM - Query the Line Number of a Labeled Line	91
EDIT - Edit from Within an Edit Session.	86	Assignment Statement Syntax	91
Macro Command Syntax	86	Return Codes.	91
Return Codes.	86	LOCATE - Locate a Line	92
END - End the Edit Session	86	Specific Locate Syntax	92
Macro Command Syntax	86	Generic Locate Syntax	92
Return Codes.	86	Return Codes.	92
EXCLUDE - Exclude Lines from the Panel	86	LRECL - Query the Logical Record Length	92
Macro Command Syntax	86	Assignment Statement Syntax	92
Return Codes.	86	Return Codes.	92
EXCLUDE_COUNTS - Query Exclude Counts	87	MACRO - Identify an Edit Macro	92
Assignment Statement Syntax	87	Macro Command Syntax	92
Return Codes.	87	Return Codes.	92
FIND - Find a Search String	87	MACRO_LEVEL - Query the Macro Nesting Level	93
Macro Command Syntax	87	Assignment Statement Syntax	93
Return Codes.	87	Return Codes.	93
FIND_COUNTS - Query Find Counts	87	MASKLINE - Set or Query the Mask Line	93
Assignment Statement Syntax	87	Assignment Statement Syntax	93
Return Codes.	87	Return Codes.	93
FLIP - Reverse Excluded Status of Lines	87	MEMBER - Query the Current Member Name.	93
Macro Command Syntax	87	Assignment Statement Syntax	93
Return Codes.	87	Return Codes.	93
FLOW_COUNTS - Query Flow Counts	88	MEND - End a Macro in the Batch Environment	93
Assignment Statement Syntax	88	Macro Command Syntax	93
Return Codes.	88	Return Codes.	93
HEX - Set or Query Hexadecimal Mode	88	MODEL - Copy a Model into the Current Data Set	94
Macro Command Syntax	88	Macro Command Model Name Syntax	94
Assignment Statement Syntax	88	Macro Command Class Name Syntax.	94
Return Codes.	88	Return Codes.	94
HILITE - Enhanced Edit Coloring	88	MOVE - Move a Data Set Member	94
Macro Command Syntax	88	Macro Command Syntax	94
Return Codes.	88	Return Codes.	94
IMACRO - Set or Query an Initial Macro	89	NONUMBER - Turn Off Number Mode	94
Macro Command Syntax	89	Syntax	94
Assignment Statement Syntax	89	Return Codes.	94
Return Codes.	89	NOTES - Set or Query Note Mode.	94
INSERT - Prepare Display for Data Insertion	89	Macro Command Syntax	94
Macro Command Syntax	89	Assignment Statement Syntax	95
Return Codes.	89	Return Codes.	95
LABEL - Set or Query a Line Label	89		
Assignment Statement Syntax	89		

NULLS - Set or Query Nulls Mode	95	SAVE - Save the Current Data	100
Macro Command Syntax	95	Macro Command Syntax	100
Assignment Statement Syntax	95	Return Codes	100
Return Codes.	95	SAVE_LENGTH - Set or Query Length for Variable	
NUMBER - Set or Query Number Mode.	95	Length Data.	100
Macro Command Syntax	95	Macro Command Syntax	100
Assignment Statement Syntax	95	Return Codes	100
Return Codes.	95	SCAN - Set Command Scan Mode	100
PACK - Set or Query Pack Mode	96	Macro Command Syntax	100
Macro Command Syntax	96	Assignment Statement Syntax	101
Assignment Statement Syntax	96	Return Codes	101
Return Codes.	96	SEEK - Seek a Data String, Positioning the Cursor	101
PASTE — Move or Copy Lines from Clipboard	96	Macro Command Syntax	101
Macro Command Syntax	96	Return Codes	101
Return Codes.	96	SEEK_COUNTS - Query Seek Counts	101
PRESERVE - Enable Saving of Trailing Blanks	96	Assignment Statement Syntax	101
Macro Command Syntax	96	Return Codes	101
Assignment Statement Syntax	96	SESSION — Identify Type of Session	101
Return Codes.	96	Assignment Statement Syntax	101
PROCESS - Process the Panel	96	Return Codes	101
Macro Command Syntax	96	SETUNDO - Set UNDO Mode.	102
Return Codes.	97	Macro Command Syntax	102
PROFILE - Set or Query the Current Profile	97	Assignment Statement Syntax	102
Macro Command Profile Control Syntax.	97	Return Codes	102
Macro Command Profile Lock Syntax	97	SHIFT (- Shift Columns Left	102
Macro Command Profile Reset Syntax	97	Macro Command Syntax	102
Assignment Statement Syntax	97	Return Codes	102
Return Codes.	97	SHIFT) - Shift Columns Right.	102
RANGE_CMD - Query a Command That You		Macro Command Syntax	102
Entered.	97	Return Codes	102
Assignment Statement Syntax	97	SHIFT < - Shift Data Left	102
Return Codes.	97	Macro Command Syntax	102
RCHANGE - Repeat a Change	97	Return Codes	103
Macro Command Syntax	97	SHIFT > - Shift Data Right	103
Return Codes.	98	Macro Command Syntax	103
RECFM - Query the Record Format	98	Return Codes	103
Assignment Statement Syntax	98	SORT - Sort Data	103
Return Codes.	98	Macro Command Syntax	103
RECOVERY - Set or Query Recovery Mode.	98	Return Codes	103
Macro Command Syntax	98	STATS - Set or Query Stats Mode.	103
Assignment Statement Syntax	98	Macro Command Syntax	103
Return Codes.	98	Assignment Statement Syntax	103
RENUM - Renumber Data Set Lines	98	Return Codes	103
Macro Command Syntax	98	SUBMIT - Submit Data for Batch Processing	103
Return Codes.	98	Macro Command Syntax	103
REPLACE - Replace a Data Set or Data Set Member	99	Return Codes	104
Macro Command Syntax	99	TABS - Set or Query Tabs Mode	104
Return Codes.	99	Macro Command Syntax	104
RESET - Reset the Data Display	99	Assignment Statement Syntax	104
Macro Command Syntax	99	Return Codes	104
Return Codes.	99	TABSLINE - Set or Query Tabs Line	104
RFIND - Repeat Find	99	Assignment Statement Syntax	104
Macro Command Syntax	99	Return Codes	104
Return Codes.	99	TENTER - Set Up Panel for Text Entry	104
RIGHT - Scroll Right	99	Macro Command Syntax	104
Macro Command Syntax	99	Return Codes	104
Return Codes.	99	TFLOW - Text Flow a Paragraph	105
RMACRO - Set or Query the Recovery Macro	100	Macro Command Syntax	105
Macro Command Syntax	100	Return Codes	105
Assignment Statement Syntax	100	TSPLIT - Text Split a Line	105
Return Codes	100	Macro Command Syntax	105

Return Codes	105
UNNUMBER - Remove Sequence Numbers	105
Macro Command Syntax	105
Return Codes	105
UP - Scroll Up	105
Macro Command Syntax	105
Return Codes	105
USER_STATE - Save or Restore User State	106
Assignment Statement Syntax	106
Return Codes	106
VERSION - Set or Query Version Number	106
Macro Command Syntax	106
Assignment Statement Syntax	106
Return Codes	106
VIEW - View from within an Edit Session	106
Macro Command Syntax	106
Return Codes	106
VOLUME — Query Volume Information	106
Assignment Statement Syntax	106
Return Codes	106
XSTATUS - Set or Query Exclude Status of a Line	107
Assignment Statement Syntax	107
Return Codes	107

Chapter 4. SCLM Services and Macros 109

SCLM Services	109
ACCTINFO - Retrieve Accounting Information	109
AUTHCODE - Set or Retrieve an AUTHCODE	110
BUILD - Build a Member	111
DBACCT - Retrieve Accounting Records for a Member	112
DBUTIL - Generate a Tailored Data Set and Report	112
DELETE - Delete Database Components	113
DELGROUP - Delete Group Database Components	113
DSALLOC—Allocate Data Sets for Group/Type	114
EDIT— Edit a Member of a Controlled Library	115
END - End an SCLM Services Session	117
EXPORT - Extract SCLM Accounting Information for a Group	117
FREE - Free Database from its Association with SCLM ID	118
IMPORT - Import SCLM Accounting Information to Current Project	118
INIT - Generate an SCLM ID for a Database	119
LOCK - Lock a Member or Assign an Access Key	119
MIGRATE - Create Accounting Information for Selected Members	120
NEXTGRP - Find the Next Group in a Hierarchy	121
PARSE - Parse a Member for Statistical and Dependency Information	121
PROMOTE - Promote a Member from One Library to Another	122
RPTARCH - Generate an SCLM Architecture Report	123
SAVE - Lock, Parse, and Store a Member	123
START - Generate an Application ID for a Service Session	124

STORE - Store Member Information in an Accounting Record	124
UNLOCK - Unlock a Member in a Development Library	125
VERDEL—Delete Version Information	126
VERINFO - Retrieve Version Information	126
VERRECOV - Recover A Version	127
SCLM Macros	128
FLMABEG - Define the Project Name of the Project Definition	128
FLMAEND - Last Macro in the Project Definition	128
FLMAGRP - Define a Group of Authorization Codes	128
FLMALLOC - Define Each DDname in the DDname Substitution List for a Translator	128
FLMALTC - Specify Alternate Control Information	129
FLMATVER - Enable the Audit and Version Utility	129
FLMCMPLB - Define a Set of Data Sets for a Language Containing Project Compool Dependencies	129
FLMCNTRL - Specify Project-Specific Control Options	129
FLMCPYLB - Identify Additional Data Sets to Be Concatenated to a DDname	131
FLMGROUP - Define One Group in the Project Definition	132
FLMINCLS - Associate Include-Sets with Types in the Project Hierarchy	132
FLMLANGL - Define a Language to SCLM	132
FLMSYSLB - Define a Set of Data Sets for a Language Containing Project Macros or Included Members	132
FLMTCOND - Select Build Translators Based on Group and Return Codes	132
FLMTOPTS - Select the Options Based on Group	132
FLMTRNSL - Define Once for Each Translator to Be Invoked for a Language	133
FLMTYPE - Define One FLMTYPE in the Project Definition	133

Chapter 5. System Variables 135

Time and Date	135
General	136
Terminal and Function Keys	139
Scrolling	141
PRINTG Command	141
Table Display Service	142
LIST Service	142
LOG and LIST Data Sets	142
Dialog Error	142
Tutorial Panels	143
Selection Panels	143
DTL Panels or Panels Containing a)PANEL Section	143

Chapter 6. Dialog Variables 145

PDF Non-Modifiable Variables	150
--	-----

Chapter 7. Dialog Tag Language (DTL)
Tags 151
Tag Summary 151

Notices 177
Programming Interface Information 178
Trademarks 178

Preface

This book is intended to serve as a quick reference for application developers and library administrators who use various components of the ISPF product.

Chapter 1 contains general information about ISPF.

Chapters 2 through 4 contain the syntax and return codes for the following:

- ISPF services
- Edit macro commands
- SCLM services and macros.

This book also contains ISPF variables (Chapter 5) and a summary of the Dialog Tag Language (DTL) tags for ISPF (Chapter 6).

Information in this book was extracted from the following prerequisite books:

- *ISPF Dialog Developer's Guide and Reference*
- *ISPF User's Guide*
- *ISPF Services Guide*
- *ISPF Edit and Edit Macros*
- *ISPF Software Configuration and Library Manager (SCLM) Reference*
- *ISPF Dialog Tag Language Guide and Reference*

This book replaces the ISPF and ISPF/PDF reference cards that were used in previous releases of ISPF and ISPF/PDF.

Who Should Use This Book

This book is for:

- Application programmers who write programs and/or command procedures that invoke ISPF services.
- Application programmers who use the ISPF editor and edit macros.
- Library administrators who use library management facilities.

Chapter 1. ISPF General Information

Invoking an ISPF Application

```
ISPSTART
{PANEL(panel-name) [OPT(option)][ADDDPOP]}
{CMD(command parm1 parm2) [LANG(APL|CREX)]}
{PGM(program-name) [PARM(parameters)]}
{WSCMD(workstation-command)
    [MODAL|MODELESS]
    [WSDIR(dir)]
    [MAX|MIN]
    [VIS|INVIS]}
{WSCMDV(var_name)
    [MODAL|MODELESS]
    [WSDIR(dir)]
    [MAX|MIN]
    [VIS|INVIS]}
[GUI(LU:address:tpname | IP:address:port |,FI:) |,NOGUIDSP) [TITLE(title)]
[GUISCRW(screen-width)]
[GUISCRD(screen-depth)]
[FRAME(STD|FIX|DLG)]
[CODEPAGE(codepage)] [CHARSET(character_set)]
[BKGRND(STD|DLG)]
[NEWAPPL[(application-id)]]
[SCRNAME(screen-name)]
[TEST|TESTX|TRACE|TRACEX]
[NOLOGO|LOGO(logo-panel-name)]
[BATSCRW(screen-width)]
[BATSCRD(screen-depth)]
[BDISPMAX(max-number-of-displays)]
[BREDIMAX(max-number-of-redisplays)]
[BDBCS]
[DANISH|ENGLISH|GERMAN|JAPANESE|
PORTUGUE|SPANISH|KOREAN|FRENCH|ITALIAN|CHINESE|
CHINESES|SGERMAN|UPPERENG]
```

Figure 1. ISPSTART Command

Invoking the ISPF Conversion Utility

ISPDTLC (for interactive interface)

OR


ISPDTLC ? (for help information)

OR

(command syntax)



ISPF General Information



ISPF System Information

Files Used by ISPF

Files used by a given invocation of ISPF must be allocated before that invocation.

DDNAME(lib-type)	Description
ISPFIL	File tailoring output
ISPILIB	Image library
ISPMLIB	Message
ISPPLIB	Panel
ISPPROF	User profile
ISPSLIB	Skeleton
ISPTABLE	Table output
ISPTLIB	Table input
SYSPROC	REXX/CLIST library
SYSEXEC	REXX library.

ACTIONS
 BACKWARD
 BOTTOM
 CANCEL
 CMDE
 COLOR
 CRETRIEV
 CUAATTR
 CURSOR
 DOWN
 DDLIST
 DSLIST [list name | DSname level]
 DTEST [parameter number]
 END
 ENVIRON [ENBLDUMP [ON | OFF]] [TERMTRAC [ON | ERROR | DUMP | OFF]]
 [TERMSTAT [QUERY]]
 EPDF datasetname [Browse] [View [Macro macroname] [Profile
 profilename] [Panel panelname][Recover] [Format formatname]
 [Mixed YES|NO]
 EXHELP
 EXIT
 FKA [ON | SHORT | OFF | PREFIX | NOPREFIX]
 FORWARD
 HELP
 INT
 ISPD TLC
 ISPFVAR [LMSG (ON|OFF) | JUMP(ON|OFF) | ABTAB(ON|OFF) | PSTAB(ON|OFF) |
 SESM(ON|OFF) | EDPRT(ON|OFF) | EURO (ON|OFF) | SPLTLINE (ON|OFF)]
 ISPFWORK
 ISPLIBD [libtype]
 ISPPREP
 ISRRLIST
 ISRRROUTE
 KEYLIST [PRIVATE | SHARED | ON | OFF]
 KEYS
 KEYSHELP
 LEFT
 LIST [PRINT | DELETE | KEEP]
 LOG [PRINT | DELETE | KEEP]
 MSGID [ON | OFF]
 NOP
 NRETRIEV
 PANELID [ON | OFF]
 PFSHOW [ON | OFF | TAILOR]
 PRINT
 PRINTG
 PRINT-HI
 PRINTL
 PRINTLHI
 PSCOLOR
 RCHANGE
 REFACTD [nnnnnnnn xx]
 REFACTL [nnnnnnnn xx]
 REFADDD [nnnnnnnn xx]

REFADDL [nnnnnnnn xx]
 REFLISTD [xx]
 REFLISTL [xx]
 REFOPEN
 REFOPENL
 RESIZE
 RETF
 RETP
 RETRIEVE
 RETURN
 RFIND
 RIGHT
 SAREA
 SCRNAME [screen name | PERM | ON | OFF]
 SETTINGS
 SPLIT [NEW]
 SPLITV
 START
 SWAP [LIST | PREV | NEXT | *screen name* | *n*]
 SWITCH [3270 | GUI]
 TOP
 TSO
 TSOCMD
 TSOGUI [ON | OFF]
 TUTOR [panelid]
 UP
 WINDOW
 WS
 WSCON
 WSDISCON
 ZKEYS

Command Table Actions

- ALIAS** When followed by the name of another command and optional parameters, allows specification of command aliases.
- NOP** Causes the command to be functionless. System displays an “inactive command” message in this case.
- PASSTHRU**
Causes the command to be passed to the dialog, as though it had not been found in the table.
- SELECT** When followed by selection keywords, causes the selected dialog command, program or selection panel to be given control immediately.
- SETVERB**
Causes the command to be passed to the dialog with the command verb stored separately from the parameters.
- Blank (no action)*
Causes the table entry to be ignored, and scanning to continue (to search for additional entries having the same verb).
- A variable name*
Begins with an ampersand. Its content may be one of the above actions. Allows dynamic specification of a command action.

Dialog Test Commands

Primary Commands

You can enter the following commands on the Command line while using Dialog Test (option 7).

CANCEL

END

LOCATE string

LOC

L

QUAL

RESUME

RES

Line Commands

The following line commands have special meaning during testing operations.

D[n] Delete one or *n* lines starting with this line.

I[n] Insert one or *n* lines directly after this line, with underscores and quotes in the appropriate fields.

R[n] Repeat this line once or *n* times.

Message Definitions

Line 1:

```
msgid ['short message'] [.HELP=panel-name| [NOKANA|KANA]
[.WINDOW=RESP|NORESP|LRESP|LNORESP] [.TYPE=NOTIFY|WARNING|ACTION|CRITICAL]
```

Line 2:

```
'long message' [+]
```

Line 3:

```
['long message' [+ ]
```

Line 4:

```
['long message' [+ ]
```

Line n:

```
['long message' ]
```

Skeleton Control Statements

```
)BLANK [number]
)CM comment
)DEFAULT abcdefg
)DOT table-name
)ENDSEL
)ENDDOT
)IM skel-name [NT] [OPT]
)SEL relational-expression
)SET variable = expression
)TB value1 ... value16
```

ISPF General Information

```
)TB value1[A] ... value16[A]
)TBA value1 ... value16
```

Panel Definitions

All parameters on header statements are optional. When preparing a panel header statement, use only one line. **Coded Character Set Identifier Section**

```
)CCSID NUMBER(xxxxx)
```

Panel Section

```
)PANEL [KEYLIST (keylist-name[,keylist-applid,SHARED])]
        [IMAGE (image-name, row, col)]
```

Attribute Section:

```
)ATTR [DEFAULT (def1def2def3)]
        [FORMAT(EBCDIC|DBCS|MIX)]
        [OUTLINE([L] [R] [O] [U] |BOX|NONE)]
```

Action Bar Choice Section:

```
)ABC DESC(choice-description-text) MNEM(number)
      PDC DESC(choice-description-text) UNAVAIL(variable) MNEM(number)
      ACC(key1[+key2][+key3])
      PDSEP(OFF|ON)
      ACTION RUN(command-name) PARM(command-parms)
```

Note: The MNEM keyword is only valid when running in GUI mode.

Action Bar Choice Initialization Section:

```
)ABCINIT
```

Note: Only valid when the Action Bar Choice section is specified.

Action Bar Choice Processing Section:

```
)ABCPROC
```

Note: Only valid when the Action Bar Choice section is specified.

Body Section:

```
)BODY [CMD(field-name)] [DEFAULT(def1def2def3)]
      [MSG(field-name)] [KANJI]
      [LMSG(field-name)] [WIDTH(width)]
      [ASIS] [EXPAND(xy)]
      [WINDOW(width,depth)] [FORMAT(EBCDIC|DBCS|MIX)]
      [OUTLINE([L] [R] [O] [U] |BOX|NONE)]
```

Note: All keywords must be specified on the same panel line.

Model Section:

```
)MODEL [CLEAR(var-name,var-name...)]
        [ROWS(ALL | SCAN)]
```

Area Section:

```
)AREA name [DEPTH(depth)]
```

Initialization Section:

```
)INIT
```

Reinitialization Section:

```
)REINIT
```

Processing Section:

```
)PROC
```

Help Section:

```
)HELP FIELD(field-name) PANEL(help-panel-name) | MSG(msg_name) | PASSTHRU
```

Specifying point and shoot fields:

```
)PNTS FIELD(field-name)|ZPSxyyy) VAR(variable) VALUE(value)
      [DEPTH (depth)] [IMAGE(image-name)] [IMAGEP(image-name)]
      [TEXT('text')] [PLACE(a, b, l, r)]
```

List Section

```
)LIST (list-name)
VAL(value) CHOICE(value)
```

Specifying the End of a Panel Definition:

```
)END
```

Panel Statements and Built-in Functions

Attribute Section:

```
AREA(DYNAMIC|GRAPHIC|SCRL)
ATTN(ON|OFF)
CAPS(ON|OFF|IN|OUT)
CKBOX(ON|OFF)
COLOR(WHITE|RED|BLUE|GREEN|PINK|YELLOW|TURQ)
COMBO(ON|OFF|name)
CSGRP(x)
CUADYN(value)
DATAMOD(datamod-code)
DDLST(ON|OFF|name)
DEPTH(d)
EXTEND(ON|OFF)
FORMAT(EBCDIC|DBCS|MIX)
GE(ON|OFF) 1
HILITE(USCORE|BLINK|REVERSE)
INTENS(HIGH|LOW|NON)
JUST(LEFT|RIGHT|ASIS)
LISTBOX(ON|OFF|name)
NOJUMP(ON|OFF)
NUMERIC(ON|OFF)
OUTLINE([L][R][O][U] |BOX|NONE)
PAD(NULLS|USER|char)
PADC(NULLS|USER|char)
PAS(ON|OFF)
RADIO(ON|OFF)
REP(character)
SCROLL(ON|OFF)
SKIP(ON|OFF)
TYPE(TEXT|INPUT|OUTPUT|DATAIN|DATAOUT)
UNAVAIL(ON|OFF)
USERMOD(usermod-code)
WIDTH(w)
```

Note: The Common User Access* (CUA*) attribute TYPE values listed below are identified in the section that follows.

```
TYPE(AB|ABSL|CEF|CH|CHAR|CT|DATAIN|DATAOUT|DT|EE|
      ET|FP|LEF|LI|LID|NEF|NT|PIN|
      PS|PT|RP|SAC|SI|SUC|VOI|WASL|WT)
TYPE(GRPBOX|SC)
USERMOD(usermod-code)
```

1. For use with TYPE(CHAR) only.

CUA Attribute TYPE Values:

TYPE Value	Description
AB	Action Bar Unselected Choices
ABSL	Action Bar Separator Line
CEF	Choice Entry Field
CH	Column Heading
CHAR	Character attributes in a dynamic area
CT	Caution Text
DATAIN	Input (unprotected) field in a dynamic area
DATAOUT	Output (protected) field in a dynamic area
DT	Descriptive Text
EE	Error Emphasis
ET	Emphasized Text
FP	Field Prompt
GRPBOX	Group Box
INPUT	Input (unprotected) field
LEF	List Entry Field
LI	List Items
LID	List Item Description
NEF	Normal Entry Field
NT	Normal Text
OUTPUT	Output (protected) field
PIN	Panel Instruction
PS	Point-and-Shoot
PT	Panel Title
RP	Reference Phrase
SAC	Select Available Choices
SC	Selected choice
SI	Scroll Information
SUC	Select Unavailable Choices
TEXT	Text (protected) field
VOI	Variable Output Information
WASL	Work Area Separator Line
WT	Warning Text

Initialization, Reinitialization, and Processing Sections:

```

variable = value
variable = LVLIN(areaname)
variable = PFK(value)
variable = TRANS (variable value,value...[MSG=message-id])
variable = TRUNC (variable,value)
variable = ADDSOSI(variable)
variable = DELSOSI(variable)
variable = ONEBYTE(variable)
variable = TWOBYTE(variable)
GOTO label
IF (variable operator value[,value...])
ELSE
EXIT
PANEXIT((value,value,...),
        {PGM, exit_add [,exit-data] [,MSG=value]
        LOAD, exit-mod[,exit-data] [,MSG=msgid]})
REFRESH(field1, field2, ...)
TOG (mode,fld,&variable [,value1,value2])
VEDIT (variable[,MSG=value])
VGET name-list [ ASIS | SHARED | PROFILE ]
VPUT name-list [ ASIS | SHARED | PROFILE ]

```

VER (variable[,NONBLANK],keyword[,value...]) [,MSG=message-id])

VER Keywords:

ALPHA	ALPHAB	BIT	DBCS	DSNAME	DSNAMEF	DSNAMEFM
DSNAMEPQ	DSNAMEQ	EBCDIC	ENUM	FILEID	HEX	IDATE
INCLUDE	ITIME	JDATE	JSTD	LEN	LIST	LISTV
LISTVX	LISTX	MIX	NAME	NAMEF	NUM	PICT
PICTCN	RANGE	STDDATE	STDTIME			

Panel Control Variables

.ALARM = YES|NO|blank|null|variable
 .ATTR(field) = 'keyword(value), keyword(value) ...'
 .ATTRCHAR(char) = 'keyword(value), keyword(value) ...'
 .AUTOSEL = YES|NO
 .CSRPOS = cursor-position
 .CSRROW = table-row-number
 .CURSOR = field-name
 .HELP = panel-name
 .MSG = message-id
 .PFKEY = contains function key pressed by user (PF01,PF02, ...,PF24)
 .RESP = ENTER|END
 .TRAIL = contains remainder from TRUNC operation
 .ZVARS = '(name-list)'

PDF Browse Primary Commands

You can enter the following commands on the command line while using the Browse function.

BROWSE [member]
 BRO

COLUMNS
 COLS
 COL

DISPLAY [char]
 DISPL [NOCC | CC]
 DISP
 DIS

EDIT [member]

FIND string [NEXT] [CHARS] [col-1 [col-2]]
 F [ALL] [PREFIX]
 [FIRST] [SUFFIX]
 [LAST] [WORD]
 [PREV]

HEX [ON | OFF]
 [VERT | DATA]

LOCATE {line-number | label}
 LOC
 L

RESET

PDF Component General Information

SUBMIT

VIEW [member]

You can use the following format to enter label definitions on the command line:

.cccc Defines a label (PDF component internal symbol), which is equated to the top line on the screen. Can be used with LOCATE to scroll directly to that line.

PDF Member List Commands

Primary Commands

You can enter the following commands on the command line on member list displays.

CONFIRM

LOCATE string

LOC

L

MLC

MLS

REFRESH

RESET

SAVE [list-id]

SELECT {pattern | * } [lcmd]

SEL

S

SORT [field1[field2]]

Line Commands

On all member list displays except those for option 3.1 and 3.4, you can enter the following one-character command at the beginning of a line.

S Selects the member.

On option 3.1 and 3.4 member list displays, you can enter the following one-character commands at the beginning of a line.

B Browses the member.

C Copies the member.

D Deletes the member.

E Edits the member.

G Resets the member.

J Submits the member.

M Moves the member.

P Prints the member.

- R** Renames the member. When using this command, you must also enter the new name to the right of the member name.
- T** TSO command.
- V** Views the member.
- W** WS command.

TSO commands, CLISTs, and REXX EXECs can be entered in member lists that have an expanded line command field. These are member lists displayed by using option M of the Data Set List utility. Here, any command other than B, D, E, P, R, or V is considered to be a TSO command, CLIST, or REXX EXEC.

PDF Data Set List Commands

Primary Commands

You can enter the following commands on the command line on option 3.4 data set list displays.

APPEND

CONFIRM [ON | OFF]

CON

C

DSLIST

EXCLUDE

FIND string [NEXT] [CHARS]

F [ALL] [PREFIX]

[FIRST] [SUFFIX]

[LAST] [WORD]

[PREV]

LC

LOCATE lparm

LOC

L

REFRESH

RESET

RFIND

SAVE [list-id]

SHOWCMD [ON | OFF]

SHOW

SORT [field1[field2]]

VA

VS

VT

VW

PDF Component General Information

Line Commands

On option 3.4 data set list displays, you can enter the following one-character commands at the beginning of a line. Any other command entered at the beginning of a line is considered to be a TSO command, CLIST, or REXX EXEC.

- B** For a library or partitioned data set, displays a member list. You can then use the S command to select a member to browse. For a sequential data set, displays the data set in browse mode.
- C** Catalogs the data set.
- CO** Copies a data set.
- D** Deletes an entire data set. Displays a Confirm Delete panel if you request confirmation.
- E** For a library or partitioned data set, displays a member list. You can then use the S command to select a member to edit. For a sequential data set, displays the data set in edit mode.
- F** Frees unused space in a data set.
- I** Displays library or data set information.
- M** For a library or partitioned data set, displays a member list.
- MO** Moves a data set.
- NX** Unexclude a line from display.
- NXF** Unexclude the first of a set of excluded data sets.
- NXL** Unexclude the last of a set of excluded data sets.
- P** Prints the library or data set.
- PX** Prints an index listing.
- R** Displays a panel, on which you can rename the library or data set.
- RA** Adds a data set to a reference list.
- RS** Resets statistical data.
- S** Displays library or data set information in short format.
- U** Uncatalogs the data set.
- V** For a library or partitioned data set, displays a member list. You can then use the S command to select a member to view. For a sequential data set, displays the data set in view mode.
- X** Excludes a data set from the list.
- Z** Compresses a library or data set.
- =** Repeats the last line command entered.

PDF Edit and View Commands

Primary Commands

While you are using the PDF editor to edit or view data, the following commands can be entered on the command line.

```
AUTOLIST [ON ]  
          [OFF]
```

```

AUTONUM [ON ]
        [OFF]

AUTOSAVE [ON          ]
         [OFF PROMPT ]
         [OFF NOPROMPT]

BOUNDS [left-col right-col]
BOUND
BNDS
BND

BROWSE [member]

BUILTIN cmdname

CANCEL
CAN

CAPS [ON ]
     [OFF]

CHANGE str-1 str-2 [range] [NEXT ] [CHARS ] [X ] [col-1 [col-2]]
CHG          [ALL ] [PREFIX] [NX]
CHA          [FIRST] [SUFFIX]
C           [LAST ] [WORD ]
           [PREV ]

COMPARE          [DSNAME ] [EXCLUDE ] [SAVE ] [SYSIN] [NEXT]

COPY [member] [AFTER label ]
      [BEFORE label]

CREATE [member] [range]
CRE

CUT [lptr-range ] [DEFAULT | clipboardname ] [REPLACE ] [DISPLAY ]

DEFINE name {MACRO CMD  }
DEF        {MACRO PGM  }
          {ALIAS name-2}
          {NOP        }
          {RESET      }
          {DISABLED   }

DELETE {ALL X|NX }
DEL    {range X|NX }
      {ALL range}

EDIT [member]

END

EXCLUDE str [range] [NEXT ] [CHARS ] [col-1 [col-2]]
EXC          [ALL ] [PREFIX]
EX           [FIRST] [SUFFIX]
X           [LAST ] [WORD ]
           [PREV ]

FIND str [range] [NEXT ] [CHARS ] [X ] [col-1 [col-2]]
F          [ALL ] [PREFIX] [NX]
          [FIRST] [SUFFIX]
          [LAST ] [WORD ]
          [PREV ]

FLIP [label1] [label2]

```

PDF Component General Information

HEX [ON DATA]
[ON VERT]
[OFF]

HILITE [ON] [AUTO] [RESET] [PAREN] [FIND] [CURSOR] [SEARCH] [DISABLED]
HI [OFF] [DEFAULT]
[LOGIC] [OTHER]
[IFLOGIC] [ASM]
[DOLOGIC] [BOOK]
[NOLOGIC] [C]
[COBOL]
[DTL]
[JCL]
[PANEL]
[PASCAL]
[PLI]
[REXX]
[SKEL]
[IDL]

IMACRO [name|NONE]

LEVEL num
LEV

LOCATE {label }
LOC {line-number}
L

LOCATE [FIRST] {CHANGE } [range]
LOC [LAST] {COMMAND }
L [NEXT] {ERROR }
[PREV] {EXCLUDED}
{LABEL }
{SPECIAL }

MODEL [CLASS [class-name]]
MOD

MODEL [model-name [qualifier...]] {AFTER label } [NOTE]
MOD {BEFORE label} [NONOTE]

MOVE [member] [AFTER label]
[BEFORE label]

NONUMBER

NOTES [ON]
NOTE [OFF]

NULLS [ON STD]
NULL [ON ALL]
NUL [OFF]

NUMBER [ON] [STD] [DISPLAY]
NUMB [OFF] [COBOL]
NUM [STD COBOL]
[STD COBOL]
[NOSTD]
[NOCOBOL]
[NOSTD NOCOBOL]

PACK [ON]
[OFF]

PASTE [clipboardname] [AFTER label][BEFORE label] [KEEP]

PRESERVE
 PROFILE [name] [number]
 PROF
 PRO
 PR

 PROFILE RESET
 PROF
 PRO
 PR
 PROFILE [LOCK | UNLOCK]
 PROF
 PRO
 PR

 RCHANGE

 RECOVERY [ON | OFF]
 RECOVER [WARN | NOWARN | SUSP]
 RECOV
 REC

 RENUM [ON] [STD] [DISPLAY]
 [COBOL]
 [STD COBOL]

 REN

 REPLACE [member] [range]
 REPL
 REP

 RESET [CHANGE] [range]
 RES [COMMAND]
 [ERROR]
 [EXCLUDED]
 [FIND]
 [LABEL]
 [SPECIAL]

 RFIND

 RMACRO [name|NONE]

 SAVE

 SETUNDO [STORAGE | RECOVER | OFF]
 SETU

 SORT [range] [X] [sort-field1...sort-field5]
 [NX]

 STATS [mode]

 SUBMIT [range]
 SUB

 TABS [ON] [STD]
 TAB [OFF] [ALL]
 [tab-character]

 UNDO

 UNNUMBER
 UNNUM
 UNN

PDF Component General Information

VERSION num
VERS
VER

VIEW [member]

Line Commands

Under Edit or View, you can enter the following line commands at the beginning of a line by typing over the line number. If you do not enter a number for the value of n, the default is 1 except for:

- The shift commands, which default to 2 column positions
- The TE command, which defaults to the number of lines remaining on the screen
- The TF command, which defaults to the current right boundary.

<[n 2]	Shifts data left two positions or the specified number of positions.
<<[n 2]	
>[n 2]	Shifts data right two positions or the specified number of positions.
>>[n 2]	
([n 2]	Shifts columns left two positions or the specified number of positions.
(([n 2]	
) [n 2]	Shifts columns right two positions or the specified number of positions.
))[n 2]	
A[n]	Identifies the line after which copied, moved, or model lines are to be inserted.
B[n]	Identifies the line before which copied, moved, or model lines are to be inserted.
BOUNDS	Displays the column boundary definition line.
BOUND	
BNDS	
BND	
C[n]	Copies one or more lines from one location to another.
CC	
COLS	Displays a position identification line.
COL	
D[n]	Deletes one or more lines.
DD	
F[n]	Redisplays one or more lines at the beginning of a block of excluded lines.
I[n]	Inserts a blank data entry line.
L[n]	Redisplays one or more lines at the end of a block of excluded lines.
LC[n]	Converts all uppercase alphabetic characters in one or more lines to lowercase.
LCC	
LCLC	
M[n]	Moves one or more lines from one location to another.
MM	
MASK	Displays the contents of the mask when used with the I (insert), TE (text entry), and TS (text split) line commands.
MD	Makes NOTE, MSG, INFO, and COLS lines into data lines.
MDD	
MDMD	
O[n]	Rearranges a single column list of items into multiple column, or tabular, format.
OO	
R[n]	Repeats one or more lines.
RR[n]	

S[n]	Redisplay one or more lines with the leftmost indentation in a block of excluded lines.
TABS TAB	Displays the tab definition line.
TE[n]	Inserts blank lines to allow power typing for text entry.
TF[n]	Restructures paragraphs following deletions, insertions, splitting, and so forth.
TS[n]	Divides a line so that data can be added.
UC[n] UCC UCUC	Converts all lowercase alphabetic characters in one or more lines to uppercase.
X[n] XX	Excludes one or more lines from a panel.

Search Strings

Picture Strings – Special Characters for String-1:

P'='	Any character
P'~'	Any character that is not a blank
P'.'	Any character that cannot be displayed
P'##'	Any numeric character, 0-9
P'-'	Any non-numeric character
P'@'	Any alphabetic character, uppercase or lowercase
P'<'	Any lowercase alphabetic character
P'>'	Any uppercase alphabetic character
P'\$'	Any special character, neither alphabetic nor numeric.

If you are using an APL or TEXT keyboard, you can use the following additional characters in a picture string:

P'⊠'	Any APL-specific or TEXT-specific character
P'_'	Any underscored non-blank character.

Picture Strings – Special Characters for String-2

P'='	Equal to the corresponding character in string-1
P'>'	Converts the corresponding character in string-1 to uppercase
P'<'	Converts corresponding character in string-1 to lowercase.

Character String Format

Simple string:

cccccc (no embedded blanks or commas)

Delimited string:

'cccc' or "cccc"

Hex string:

X'hhhh' or 'hhhh'X

PDF Component General Information

Text string:

T'cccc' or 'cccc'T

Picture string:

P'ssss' or 'ssss'P

Character string:

C'cccc' or 'cccc'C

Previous string:

* (single asterisk)

Chapter 2. ISPF Service Syntax with Return Codes

This chapter contains the ISPF services. The services are presented in alphabetic order. For each service, the command procedure format is shown, followed by the PL/I call formats. For more complete information, see the **ISPF Services Guide**.

Each service description consists of the following information:

Format

The syntax used to code the service, showing both command invocation and call invocation.

Return Codes

A description of the codes returned by the service. For all services, a return code of 12 or higher implies a severe error. This error is usually a syntax error, but can be any severe error detected when using the services.

Syntax Notation

In this manual, the following syntax notation conventions are used:

- Uppercase commands and their operands should be spelled as shown, but need not be entered in uppercase. Operands shown in lowercase are variables; a value should be substituted for them.
- Operands shown in brackets [] are optional, with a choice indicated by vertical bars |. One or none can be chosen; the defaults are underscored.
- Operands shown in braces { } are alternatives; one must be chosen.
- An ellipsis (...) indicates that the parameter shown can be repeated to specify additional items of the same category.

ISPEXEC Command Invocation

The general format for a command invocation is:

```
ISPEXEC service-name parameter1 parameter2 parameter3 ...
```

ISPEXEC Parameter Conventions

service-name

Alphabetic; up to 8 characters long.

parameter1

Positional parameter; required for some services.

parameter2 parameter3 ...

Keyword parameters. They can take either of two forms:

keyword

or

keyword(value)

The ISPLINK Interface

For calls in PL/I or COBOL, the general call format for invoking ISPF services from functions by using ISPLINK is:

```
CALL ISPLINK (service-name, parameter1, parameter2, ...);
```

ISPF Service Syntax

CALL ISPLINK Parameters

These parameters are positional. They must appear in the order described for each service.

Parameters shown inside brackets ([]) are optional, but ISPF assumes default values for those parameters you do not choose.

If you want to omit a parameter, you must still account for it by inserting a blank enclosed in single quotes (' ') in its place. This is how you would omit **parm2** from this sample call:

```
CALL ISPLINK (service-name, parm1, ' ', parm3);
```

If you need only the first few of a list of parameters, you must omit all other parameters to the right of the last parameter you need. For example, if you are using a service that has five parameters, but you need to use only the first three, code it like this:

```
CALL ISPLINK (service-name, parm1, parm2, parm3);
```

You must show the last parameter in the calling sequence with a '1' as the high order bit in the last entry of the address list. PL/I, COBOL, Pascal, and FORTRAN call statements automatically generate this high-order bit. However, you must use the VL keyword in assembler call statements.

The ISPEXEC Interface

You can use the command function form for service requests in a program function by using the call format of ISPEXEC. Excluding calls in FORTRAN, Pascal, and APL2*, the general call format for invoking ISPF services from program functions by using ISPEXEC is:

```
CALL ISPEXEC (buf-len, buffer);
```

CALL ISPEXEC Parameters

buf-len

Specifies a fullword fixed binary integer containing the length of the buffer.

buffer

Specifies a buffer containing the name of the service and its parameters just as they would appear in an ISPEXEC invocation for a command invocation written in CLIST.

The maximum buffer size is 32767 bytes.

All services that are valid through ISPEXEC command invocation statements are valid through the CALL ISPEXEC interface.

ADDDPOP - Start Pop-Up Window Mode

Command Invocation Format

```
ISPEXEC ADDPOP [POPLOC(field-name)] [ROW(row)]  
[COLUMN(column)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('ADDPOP ' [,field-name] [,row]
              [,column ] );
```

Return Codes

- 0 Normal completion.
- 12 An ADDPOP service call was issued before the panel was displayed or another ADDPOP service call was issued before a panel was displayed for the previous ADDPOP call.
- 20 Severe error.

BRIF - Browse Interface

Command Invocation Format

Command procedures cannot be used to invoke this service.

Call Invocation Format

```
CALL ISPLINK ('BRIF ' ,[data-name] ,rec-format
                  ,rec-len ,read-routine
                  ,[cmd-routine] ,[dialog-data]
                  ,[panel-name] ,[format-name]
                  ,['YES ' |'NO ']);
```

Return Codes

Read Routine

- 0 Normal completion.
- 4 Temporary end of file.
- 8 Record requested beyond end of data. The relative record number of the last data record and a pointer to the last data record are returned.
- 16 Read error. Browse data obtained up to the read error is formatted and displayed with an indication that a read error was encountered.
- 20 Severe error. (The BRIF service terminates immediately with a return code of 20.)

Command Routine

- 0 Normal completion.
- 4 The PDF component should process the requested function.
- 12 Command deferred; retain the command on the Command line. Browse data is redisplayed.
- 20 Severe error. (The BRIF service terminates immediately with a return code of 20.)

BRIF service

- 0 Normal completion.
- 12 No data to browse.
- 16 Unexpected return code received from a dialog-supplied routine; unable to continue. When an unexpected return code is received, the BRIF service terminates immediately with a return code of 16.

BROWSE - Browse a Data Set

Command Invocation Format

```
ISPEXEC BROWSE DATASET(dsname) [VOLUME(serial)]
                                [PASSWORD(pswd-value)]
                                [PANEL(panel-name)]
                                [FORMAT(format-name)]
                                [MIXED(YES|NO)]
```

OR

```
ISPEXEC BROWSE DATAID(data-id) [MEMBER(member-name)]
                                 [PANEL(panel-name)]
                                 [FORMAT(format-name)]
                                 [MIXED(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK ('BROWSE ',{dsname},{serial}
              ,{pswd-value}
              ,{panel-name}
              ,{data-id}
              ,{member-name}
              ,{format-name}
              ,['YES'|'NO'|'']);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|--|
| 0 | Normal completion. |
| 12 | Zero-length data; empty sequential data set or zero-length member of a partitioned data set. |
| 14 | Specified member not found. |
| 16 | One of the following: <ul style="list-style-type: none"> • No members matched the specified pattern. • No members in the partitioned data set. |
| 18 | A VSAM data set was specified but the ISPF Configuration Table does not allow VSAM processing. |
| 20 | Severe error; unable to continue. |

CONTROL - Set Processing Modes

Command Invocation Format

```
ISPEXEC CONTROL { DISPLAY { LOCK } }
                 { { LINE [START(line-number)] } }
                 { { SM [START(line-number)] } }
                 { { REFRESH } }
                 { { SAVE|RESTORE } }
                 { { ALLVALID } }
                 { NONDISPL [ENTER|END] [NOSETMSG] }
                 { ERRORS [CANCEL|RETURN] }
                 { SPLIT { ENABLE } }
```

```

{           { DISABLE }           }
{           }                     }
{ NOCMD    }                     }
{           }                     }
{ SUBTASK  { PROTECT }           }
{           { CLEAR  }           }
{           }                     }
{ TSOGUI   [QUERY|OFF|ON]       }
{ REFLIST  [UPDATE|NOUPDATE]    }

```

Call Invocation Format

CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('CONTROL ', operand);

Note: parameters that can appear in "operand" are:

```

{ 'DISPLAY' { , 'LOCK      ' } }
{           { , 'LINE     ' [,line-number] } }
{           { , 'SM       ' [,line-number] } }
{           { , 'REFRESH ' } }
{           { , 'SAVE     ' | 'RESTORE ' } }
{           { , 'ALLVALID' } }
{           } }
{ 'NONDISPL' [, 'ENTER ' | 'END ' ] }
{           } }
{ 'ERRORS '  [, 'CANCEL ' | 'RETURN ' ] [NOSETMSG] }
{           } }
{ 'SPLIT '   { , 'ENABLE ' } }
{           { , 'DISABLE ' } }
{           } }
{ 'NOCMD '   } }
{           } }
{ 'SUBTASK ' { , 'PROTECT ' } }
{           { , 'CLEAR ' } }
{           } }
{ 'TSOGUI '  [, 'QUERY' | 'OFF ' | 'ON ' ] }
{ 'REFLIST ' [, 'UPDATE' | 'NOUPDATE' ] }

```

Return Codes

- 0 Normal completion.
- 8 Split-screen mode already in effect. Applies only to a SPLIT DISABLE request. Split-screen mode remains enabled.
- 20 Severe error.

DISPLAY - Display Panels and Messages

Command Invocation Format

```

ISPEXEC DISPLAY [PANEL(panel-name)]
                [MSG(message-id)]
                [CURSOR(cursor-field-name)]
                [CSRPOS(cursor-position)]
                [COMMAND(stack-buffer-name)]
                [RETBUFFR(ret-buffer-name)]
                [RETLGTH(ret-length-name)]
                [MSGLOC(message-field-name)]

```

DISPLAY

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('DISPLAY ' [,panel-name]  
                [,message-id]  
                [,cursor-field-name]  
                [,cursor-position]  
                [,stack-buffer-name]  
                [,ret-buffer-name]  
                [,ret-length-name]  
                [,message-field-name]]);
```

Return Codes

- | | |
|----|--|
| 0 | Normal completion. For the COMMAND option, the ret-buffer-name is set to blanks and the ret-length-name is set to zero. Passing an empty command chain buffer also results in a normal completion. |
| 4 | One or more commands in the stack could not be found in the active set of command tables. |
| 8 | User requested termination via the END or RETURN command. For panels generated with the tag conversion utility, CANCEL and EXIT commands also give a return code of 8. |
| 12 | The specified panel, message, cursor field, or message location field could not be found. |
| 16 | Truncation or translation error in storing defined variables. |
| 20 | Severe error. |

DSINFO - Data Set Information Dialog

Command Invocation Format

```
ISPEXEC DSINFO DATASET(dsname) [VOLUME(serial)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('DSINFO ' [,dsname]  
                [,serial])
```

Return Codes

- | | |
|----|--|
| 0 | Normal completion. |
| 8 | User requested data set was not found. |
| 12 | One of the following: <ul style="list-style-type: none">• FAMS error.• Obtain error.• Error obtaining directory information. |
| 20 | Severe error; unable to continue. |

EDIF - Edit Interface

Command Invocation Format

Command procedures cannot be used to invoke this service.

Call Invocation Format

```
CALL ISPLINK ('EDIF      ',[data-name] ,profile-name
                    ,rec-format ,rec-len
                    ,read-routine, write-routine
                    ,[cmd-routine] ,[dialog-data]
                    ,[edit-len] ,[panel-name]
                    ,[macro-name] ,[format-name]
                    ,['YES      ' | 'NO      ' ]
                    ,['YES      ' | 'NO      ' ]
                    ,[parm-var]);
```

OR

```
CALL ISPLINK ('EDIF      ',[data-name] ,' '
                    ,[rec-format] ,[rec-len]
                    ,read-routine ,write-routine
                    ,[cmd-routine] ,[dialog-data]
                    ,' ' , ' ' , ' ' , ' '
                    , 'YES      ');
```

Return Codes

Read Routine

- 0 Normal completion.
- 8 End of data records (no data record returned).
- 16 Read error. If a read error is encountered when building the initial edit display, the EDIF service terminates with a return code of 20. Otherwise, the edit data is redisplayed.
- 20 Severe error. (EDIF service terminates immediately with a return code of 20.)

Write Routine Return Codes

- 0 Normal completion.
- 16 Output error, return to Edit mode.
- 20 Severe error. (EDIF service terminates immediately with a return code of 20).

Command Routine Return Codes

- 0 Normal completion.
- 4 The PDF component should process the requested function.
- 12 Command deferred; retain the command on the Command line. Edit data is redisplayed.
- 20 Severe error. (EDIF service terminates immediately with a return code of 20.)

EDIF Return Codes

- 0 Normal completion, data saved.
- 4 Normal completion, data not saved.
- 16 Unexpected return code received from a dialog-supplied routine. When an unexpected return code is received, the EDIF service terminates immediately with a return code of 16.
- 20 Severe error; unable to continue.

EDIREC - Initialize Edit Recovery

Command Invocation Format

Command procedures cannot be used to invoke this service.

EDIREC

Call Invocation Format

```
CALL ISPLINK ('EDIREC ', {'INIT      '[,command-name]}
                        {'QUERY    '}
                        {'CANCEL   '}
                        {'DEFER    '});
```

Return Codes

- 0 Normal completion.
 - INIT - EDIF recovery table was successfully created.
 - QUERY - Recovery is not pending.
- 4 Normal completion.
 - INIT - EDIF recovery table already exists for current application
 - QUERY - Entry found in EDIF recovery table (recovery is pending).
- 20 Severe error; unable to continue.

EDIT - Edit a Data Set

Command Invocation Format

```
ISPEXEC EDIT DATASET(dsname) [VOLUME(serial)]
                               [PASSWORD(pswd-value)]
                               [PANEL(panel-name)]
                               [MACRO(macro-name)]
                               [PROFILE(profile-name)]
                               [FORMAT(format-name)]
                               [MIXED(YES|NO)]
                               [LOCK(YES|NO)]
                               [CONFIRM(YES|NO)]
                               [WS(YES|NO)]
                               [PRESERVE]
                               [PARM(parm-var)]
OR
ISPEXEC EDIT DATAID(data-id) [MEMBER(member-name)]
                               [PANEL(panel-name)]
                               [MACRO(macro-name)]
                               [PROFILE(profile-name)]
                               [FORMAT(format-name)]
                               [MIXED(YES|NO)]
                               [LOCK(YES|NO)]
                               [CONFIRM(YES|NO)]
                               [WS(YES|NO)]
                               [PRESERVE]
                               [PARM(parm-var)]
OR
ISPEXEC EDIT WSFN(ws-filename) [PANEL(panel-name)]
                                [MACRO(macro-name)]
                                [PROFILE(profile-name)]
                                [FORMAT(format-name)]
                                [MIXED(YES|NO)]
                                [LOCK(YES|NO)]
                                [CONFIRM(YES|NO)]
                                [WS(YES|NO)]
                                [PRESERVE]
                                [PARM(parm-var)]
```


Call Invocation Format

```
CALL ISPLINK ('EDIT ' , {dsname} ,[serial]
                , [pswd-value]
                , [panel-name]
                , [macro-name]
                , [profile-name]
                , {data-id}
                , [member-name]
                , [format-name]
                , ['YES ' | 'NO ' ]
                , ['YES ' | 'NO ' ]
                , ['YES ' | 'NO ' ]
                , {ws-filename-buffer-name}
                , ['YES' | 'NO']
                , ['PRESERVE']
                , ' '
                , [parm-var]);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|--|
| 0 | Normal completion; data was saved. |
| 4 | Normal completion; data was <i>not</i> saved. |
| 12 | YES was specified for the LOCK parameter. |
| 14 | Member or sequential data set in use. |
| 16 | One of the following: <ul style="list-style-type: none"> • No members matched the specified pattern. • No members in the partitioned data set. |
| 18 | A VSAM data set was specified but the ISPF Configuration Table does not allow VSAM processing. |
| 20 | Severe error; unable to continue. |

EDREC - Specify Edit Recovery Handling

Command Invocation Format

```
ISPEXEC EDREC {INIT [CMD(command-name)]}
               {QUERY }
               {PROCESS [PASSWORD(pswd-value)]
               [DATAID(data-id)]}
               {CANCEL }
               {DEFER }
```

Call Invocation Format

```
CALL ISPLINK ('EDREC ' {,'INIT ' [,command-name]}
                {,'QUERY ' }
                {,'PROCESS ' [,pswd-value] [,data-id]}
                {,'CANCEL ' }
                {,'DEFER ' });
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|---|----------------|
| 0 | Normal return. |
|---|----------------|

EDREC

- INIT - Edit recovery table was successfully created.
 - QUERY - Recovery is not pending.
 - PROCESS - Recovery was completed and the data was saved.
- 4 Normal return.
- INIT - Edit recovery table already exists for current application.
 - QUERY - Entry found in edit recovery table; recovery is pending.
 - PROCESS - Recovery was completed, but user did not save data.
- 20 Severe error; unable to continue.

FILESTAT - Statistics for a file

Command Invocation Format

```
ISPEXEC FILESTAT FILE(var-name)
                        [LRECL(var-name),DATE(var-name)]
```

Call Invocation Format

```
CALL ISPLINK ('FILESTAT',var-name
              ,[var-name,var-name])
```

Return Codes

- 0 Workstation file exists.
- 4 Workstation file does not exist.
- 8 Error in variable specification.
- 10 No workstation connection exists.
- 12 Workstation device is not ready.
- 20 Severe error in FILESTAT service.

FILEXFER - Upload or download file

Command Invocation Format

```
ISPEXEC FILEXFER HOST(var-name) WS(var-name) TO(HOST|WS)
                [VOLUME(volume)]
                [BINARY|TEXT]
                [STATS|NOSTATS]
                [CHKDATE (YES|NO)]
                [SETDATE (YES|SCLM|NO)]
                [MAKEPATH (YES|NO)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('FILEXFER',host_var,ws_var,'HOST'|'WS',
              [volume,'BINARY'|'TEXT',
               'STATS'|'NOSTATS',
               'YES'|'NO',
               'YES'|'SCLM'|'NO',
               'YES'|'NO',])
```

Return Codes

- 2 Source file and target file have the same date and time.
- 4 LMSTAT failed.

6	Data set not cataloged.
7	Error in variable specification.
8	"TO" direction not valid.
9	Host name is too long.
10	No workstation connection exists.
11	Return code 1 from DTTRANSFER. Host data set had null object handle.
12	Return code 2 from DTTRANSFER. Workstation file had null object handle.
13	Return code 3 from DTTRANSFER. Host data set could not be opened.
14	Return code 4 from DTTRANSFER. Workstation file could not be opened.
15	Return code 5 from DTTRANSFER. Error reading host data set.
16	Return code 6 from DTTRANSFER. Error reading workstation file.
17	Return code 7 from DTTRANSFER. Error writing host data set.
18	Return code 8 from DTTRANSFER. Error writing workstation file.
19	Return code 9 from DTTRANSFER. Error closing host data set.
20	Severe error in transfer service.
21	Return code 10 from DTTRANSFER. Error closing workstation file.
22	Return code 11 from DTTRANSFER. User refused file access.
23	Data set or member in use.

FTCLOSE - End File Tailoring

Command Invocation Format

```
ISPEXEC  FTCLOSE  [NAME(member-name)]
                [LIBRARY(library)]
                [NOREPL]
```

Call Invocation Format

```
CALL  ISPEXEC (buf-len, buffer);

OR

CALL  ISPLINK ('FTCLOSE ' [,member-name]
                [,library]
                [, 'NOREPL ']);
```

Return Codes

0	Normal completion.
4	Member already exists in the output library and NOREPL was specified. The original member is unchanged.
8	File not open. FOPEN was not used prior to FTCLOSE.
12	Output file in use. ENQ failed.
16	Skeleton library or output file not allocated.
20	Severe error.

FTERASE - Erase File Tailoring Output

Command Invocation Format

```
ISPEXEC  FTERASE  member-name [LIBRARY(library)]
```

FTERASE

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('FTERASE ', member-name [,library]);
```

Return Codes

0	Normal completion.
8	File does not exist.
12	Output file in use; ENQ failed.
16	Alternate output library not allocated.
20	Severe error.

FTINCL - Include a Skeleton

Command Invocation Format

```
ISPEXEC FTINCL skel-name [NOFT]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('FTINCL ', skel-name [, 'NOFT ' ] );
```

Return Codes

0	Normal completion.
8	Skeleton does not exist.
12	Skeleton in use; ENQ failed.
16	Data truncation occurred or skeleton library or output file not allocated.
20	Severe error.

FTOPEN - Begin File Tailoring

Command Invocation Format

```
ISPEXEC FTOOPEN [TEMP]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('FTOPEN ' [, 'TEMP ' ] );
```

Return Codes

0	Normal completion.
---	--------------------

8	File tailoring already in progress.
12	Output file in use; ENQ failed.
16	Skeleton library or output file not allocated.
20	Severe error.

GETMSG - Get a Message

Command Invocation Format

```
ISPEXEC GETMSG MSG(message-id) [SHORTMSG(short-message-name)]
                                [LONGMSG(long-message-name)]
                                [ALARM(alarm-name)]
                                [HELP(help-name)]
                                [TYPE(type-name)]
                                [WINDOW(window-name)]
                                [CCSID(ccsid-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('GETMSG ' ,message-id [,short-message-name]
                                [,long-message-name]
                                [,alarm-name]
                                [,help-name]
                                [,type-name]
                                [,window-name]
                                [,ccsid-name]);
```

Return Codes

0	Normal completion.
12	The specified message could not be found.
20	Severe error.

GRERROR - Graphics Error Block Service

Command Invocation Format

```
ISPEXEC *This service does not apply to
        command or APL2 procedures*
```

Call Invocation Format

```
CALL ISPEXEC *This service cannot be used
              with this interface*
```

OR

```
CALL ISPLINK ('GRERROR ' , error-record-pointer,
              call-format-descriptor-module-pointer);
```

Return Codes

0	Normal completion.
---	--------------------

GRERROR

8 ISPF/GDDM* interface is not established.
20 Severe error.

GRINIT - Graphics Initialization

Command Invocation Format

ISPEXEC *This service does not apply to
command or APL2 procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used
with this interface*

OR

CALL ISPLINK ('GRINIT ' ,application-anchor-block
[,panel-name]);

Return Codes

0 Normal completion.
8 The specified panel does not contain a GRAPHIC area.
12 The specified panel could not be found.
20 Severe error.

GRTERM - Graphics Termination Service

Command Invocation Format

ISPEXEC *This service does not apply to
command or APL2 procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used
with this interface*

OR

CALL ISPLINK ('GRTERM ');

Return Codes

0 Normal completion.
20 Severe error.

LIBDEF - Allocate Application Libraries

Command Invocation Format

ISPEXEC LIBDEF lib-type [DATASET|EXCLDATA|LIBRARY|EXCLLIBR]
[ID(dataset-list)|ID(libname)]
[COND|UNCOND|STACK|STKADD]

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('LIBDEF ', lib-type
              [, 'DATASET ' | 'EXCLDATA' | 'LIBRARY ' | 'EXCLLIBR']
              [, dataset-list | libname]
              [, 'COND ' | 'UNCOND ' ] | 'STACK ' | 'STKADD ');
```

Return Codes

0	Normal completion.
4	Application library does not exist for this type (when removing the application library).
8	Application library already exists for this type (when COND is used).
12	ISPPROF was specified as the lib-type; invalid lib-type specified with EXCLDATA or EXCLLIBR.
16	A libname was not allocated, or the dataset-list contains an invalid MVS dsname.
20	Severe error.

LIST - Write Lines to the List Data Set

Command Invocation Format

```
ISPEXEC LIST BUFNAME(dialog-variable-name)
             LINELEN(line-length)
             [PAGE]
             [SINGLE|DOUBLE|TRIPLE]
             [OVERSTRK]
             [CC]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('LIST ', dialog-variable-name, line-length
              [, 'PAGE ' ]
              [, 'SINGLE ' | 'DOUBLE ' | 'TRIPLE ' ]
              [, 'OVERSTRK' ]
              [, 'CC ' ]);
```

Return Codes

0	Normal completion.
8	Maximum line length or data set LRECL exceeded; data has been truncated.
12	Specified dialog variable not found.
20	Severe error.

LMCLOSE - Close a Data Set

Command Invocation Format

```
ISPEXEC LMCLOSE DATAID(data-id)
```

Call Invocation Format

```
CALL ISPLINK ('LMCLOSE ',data-id);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 8 | Data set is not open. |
| 10 | No ISPF library or data set is associated with the given data ID; that is, LMINIT has not been completed. |
| 20 | Severe error; unable to continue. |

LMCOMP - Compresses a Partitioned Data Set

Command Invocation Format

```
ISPEXEC LMCOMP DATAID(data-id)
```

Call Invocation Format

```
CALL ISPLINK ('LMCOMP ',data-id);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Successful completion. |
| 10 | No data set is associated with the given data ID. |
| 12 | One of the following: <ul style="list-style-type: none">• Data set not partitioned.• Data set specified not allocated.• Data set is open.• Data set is not movable.• Data set must be allocated exclusively. Use ENQ(EXCLU) in LMINIT service• Concatenated libraries are not allowed for LMCOMP |
| 20 | Severe error; unable to continue. |

LMCOPY - Copy Members of a Data Set

Command Invocation Format

```
ISPEXEC LMCOPY FROMID(from-data-id)
           [FROMMEM(from-member-name)]
           TODATAID(to-data-id)
           [TOMEM(to-member-name)]
```



```
[REPLACE]
[PACK]
[TRUNC]
[LOCK]
[SCLMSET(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK ('LMCOPY ', from-data-id
              , [from-member-name]
              , to-data-id
              , [to-member-name]
              , ['REPLACE ']
              , ['PACK   ']
              , ['TRUNC  ']
              , ['LOCK   ']);
              , ['YES|NO  ']
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Normal completion.
- 4 Member not available:
 - The member is in a controlled ISPF library and is currently owned by another user.
 - The member is in a controlled ISPF library and the user is not a valid user as specified by member access ID.
 - Lock was requested but the project is SCLM-controlled.
 - "From" library not LMF-controlled.
 - "From" data set is empty.
 - No members matched the specified pattern in the "from" data set.
- 8 "From" member not found.
- 10 No data set is associated with the given data ID.
- 12 One of the following:
 - Invalid data set organization.
 - Data set attribute invalid for copying or copying packed data.
 - Open error.
 - A like named member already exists in the 'TO' data set, and the Replace option was not specified.
 - One or more members of the 'TO' data set are "in use" by you or another user and could not be copied.
- 16 Truncation error.
- 20 Severe error; unable to continue.

LMDDISP - Data Set Display Service

Command Invocation Format

```
ISPEXEC LMDDISP LISTID(dslist-id)
              [VIEW(VOLUME|SPACE|ATTRIB|TOTAL)]
              [CONFIRM(YES|NO)]
              [PANEL(panel-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len,buffer);
```

OR

LMDDISP

```
CALL ISPLINK('LMDDISP ', dslist-id
            , ['VOLUME ' | 'SPACE ' | 'ATTRIB ' | 'TOTAL ']
            , ['YES ' | 'NO ']
            , [panel-name]);
```

Return Codes

0 Normal completion.
10 A data set list does not exist for the list-id specified via keyword LISTID.
12 Invalid parameter value.
20 A severe error occurred while processing the data set list.

LMDENQ – Return ENQs

Command Invocation Format

```
QUERYENQ TABLE(table-name)
        QNAME(qname)
        RNAME(rname)
        REQ(pattern)
        WAIT
        LIMIT(limit)
        SAVE(list-id)
        XSYS
```

Call Invocation Format

```
CALL ISPLINK ('QUERYENQ' ,table-name
            ,qname
            ,rname
            ,pattern
            ,['WAIT ']
            ,limit
            ,list-id
            ,['XSYS ']);

OR
CALL ISPEXEC (buf-len, buffer);
```

Variables Returned in Each Row of the Table

Table 1.

NAME	SIZE	DESCRIPTION
ZENJOB	8	Job or address space name holding or requesting the ENQ
ZENQNAME	8	Qname portion of the ENQ
ZENRNAME	255	Rname portion of the ENQ
ZENDISP	5	SHARE or EXCLU
ZENHOLD	4	OWN or WAIT
ZENSCOPE	7	SYSTEM or SYSTEMS
ZENSTEP	7	STEP or blank
ZENGLOBAL	6	GLOBAL or blank
ZENSYST	8	System name

Return Codes

0	Table returned
4	Table returned but truncated due to limit
8	No ENQs satisfy request
12	Table creation error. See message for more details.
20	Severe error, most likely a TBADD failure.

LMDFREE - Free a Data Set List

Command Invocation Format

```
ISPEXEC LMDFREE LISTID(list-id-var)
```

Call Invocation Format

```
CALL ISPLINK ('LMDFREE ',list-id);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

0	Normal completion.
8	Free dslid-id failed. The error condition is described in "Dialog Error" on page 142.
10	No data set level or volume is associated with the given dslid-id. LMDINIT has not been completed.
20	Severe error; unable to continue.

LMDINIT - Initialize a Data Set List

Command Invocation Format

```
ISPEXEC LMDINIT LISTID(dslid-id-var)
                {LEVEL(dsname-level)}
                {VOLUME(volume-serial)}
```

Call Invocation Format

```
CALL ISPLINK ('LMDINIT ',dslid-id-var
                ,{dsname-level}
                ,{volume-serial} );
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

0	Normal completion. The unique dslid-id is returned in the variable specified in keyword LISTID.
8	Dslid-id not created; the error condition is described "Dialog Error" on page 142.
12	A keyword value is incorrect.

LMDINIT

- 16 Truncation or translation error in accessing dialog variables.
20 Severe error; unable to continue.
-

LMDLIST - List a Data Set

Command Invocation Format

```
ISPEXEC LMDLIST LISTID(dslist-id)
              OPTION(LIST|FREE|SAVE)
              DATASET(dataset-var)
              [STATS(Yes|NO)]
              [GROUP(group)]
```

Call Invocation Format

```
CALL ISPLINK ('LMDLIST ' ,dslist-id
              , 'LIST ' | 'FREE ' | 'SAVE '
              , dataset-var
              , ['YES ' | 'NO ' ]
              , [group]
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 One of the following:
- LIST option - Normal completion. The name of the next data set in the list is returned in the variable specified in keyword DATASET. Data set statistics are returned, if requested.
 - FREE option - Normal completion. The internal storage associated with the the data set is freed.
 - SAVE option - Normal completion. The data set list has been successfully written to a data set.
- 4 No data sets matched specified search criteria (the values for keywords LEVEL and VOLUME on the LMDINIT service).
- 8 End of data set list.
- 10 Data set list does not exist for list-id.
- 12 A keyword value is incorrect.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.
-

LMERASE - Erase a Data Set

Command Invocation Format

```
ISPEXEC LMERASE {PROJECT(project)
                GROUP(group)
                TYPE(type)      }
                {DATASET(dataset)}
                [PURGE(YES|NO)]
                [VOLUME(volume)]
                [PASSWORD(password)]
```

Call Invocation Format

```
CALL ISPLINK('LMERASE ' ,{project
                        ,group
                        ,type  }
```

```
, {dataset}
, ['YES ' | 'NO '];
, [volume]
, [password];
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|--|
| 0 | Normal completion. |
| 8 | One of the following: <ul style="list-style-type: none"> • Specified data set is not cataloged. • Erase data set failed. • Data set has not expired yet. • Data set name is an alias. • No data set specified as input • PROJECT specified, but GROUP or TYPE not specified. |
| 12 | Expiration data not expired and PURGE (NO) specified. |
| 20 | Severe error; unable to continue. |

LMFREE - Free Data Set from its Association with Data ID

Command Invocation Format

```
ISPEXEC LMFREE DATAID(data-id)
```

Call Invocation Format

```
CALL ISPLINK ('LMFREE ', data-id);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 8 | Free data ID failed; the error condition is described “Dialog Error” on page 142. |
| 10 | No ISPF library or data set is associated with the given data ID; that is, LMINIT has not been completed. |
| 20 | Severe error; unable to continue. |

LMGET - Read a Logical Record from a Data Set

Command Invocation Format

```
ISPEXEC LMGET DATAID(data-id)
MODE(MOVE|LOCATE|INVAR)
DATALOC(data-loc-var)
DATALEN(data-len-var)
MAXLEN(max-length)
```

LMGET

Call Invocation Format

```
CALL ISPLINK ('LMGET ',data-id
              , 'MOVE ' | 'LOCATE ' | 'INVAR '
              ,data loc-var
              ,data len-var
              ,max-length);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion.
- 8 End-of-data set condition; no message formatted.
- 10 No ISPF library or data set associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:
 - The data set is not open or is not open for input.
 - An LMMFIND was not done for a partitioned data set.
 - The parameter value is invalid.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMINIT - Generate a Data ID for a Data Set

Command Invocation Format

```
ISPEXEC LMINIT DATAID(data-id-var)

      {PROJECT(project) GROUP1(group1) TYPE(type)
      [GROUP2(group2)] [GROUP3(group3)] [GROUP4(group4)]}
      {DATASET(dsname)
      {DDNAME(ddname)
      [VOLUME(serial)] [PASSWORD(password)]
      [ENQ(SHR|EXCLU|SHRW|MOD)] [ORG(org-var)]
```

Call Invocation Format

```
CALL ISPLINK ('LMINIT ', data-id-var
              ,{project,group1 [,group2]
              [,group3] [,group4] ,type}
              ,{dsname
              {ddname
              ,[serial] ,[password]
              ,['SHR ' | 'EXCLU ' | 'SHRW ' | 'MOD ' ] ,[org-var]);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Normal completion.
- 8 Data ID not created.
- 12 The parameter value is invalid.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMMADD - Add a Member to a Data Set

Command Invocation Format

```
ISPEXEC LMMADD DATAID(data-id)
          MEMBER(member-name)
          [STATS(YES|NO)]
          [NOENQ]
```

Call Invocation Format

```
CALL ISPLINK ('LMMADD ',data-id
              ,member-name
              ,['YES ' | 'NO'])
              ,['NOENQ'];
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 4 | Directory already contains the specified name. |
| 10 | No ISPF library or MVS data set is associated with the given data ID; that is, LMINIT has not been completed. |
| 12 | One of the following: <ul style="list-style-type: none"> • The data set is not open or is not open for output. • The parameter value is invalid. • The data set organization is invalid. • The values for some member statistics are invalid. |
| 14 | No record has been written for the member to be added. |
| 16 | Truncation or translation error in accessing dialog variables. |
| 20 | Severe error; unable to continue. |

LMMDEL - Delete a Member from a Data Set

Command Invocation Format

```
ISPEXEC LMMDEL DATAID(data-id)
          MEMBER(member-name)
          [NOENQ]
```

Call Invocation Format

```
CALL ISPLINK('LMMDEL ',data-id
              ,member-name)
              ,['NOENQ'];
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 8 | Member not found. |
| 10 | No data set is associated with the given data ID; that is, LMINIT has not been completed. |

LMMDEL

- 12 One of the following:
- The data set is not open or is not open for output.
 - The parameter value is invalid.
 - The data set organization is invalid.
- 20 Severe error; unable to continue.

LMMDISP - Member List Service

Display Option

Command Invocation Format

```
ISPEXEC LMMDISP DATAID(data-id)
        [OPTION(DISPLAY)]
        [MEMBER(pattern)]
        [STATS(YES|NO)]
        [PANEL(panel-name)]
        [CURSOR(ZCMD|ZLLCMD|ZLUDATA)]
        [TOP(top-row)]
        [COMMANDS(S|ANY)]
        [FIELD(I|9)]
        [ALLOWNEW]
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
            ,['DISPLAY ' ]
            ,[pattern]
            ,['YES ' | 'NO ' ]
            ,[panel-name]
            ,['ZCMD ' | 'ZLLCMD ' | 'ZLUDATA ' ]
            ,[top-row]
            ,' '
            ,' '
            ,['S ' | 'ANY ' ]
            ,[I|9]
            ,['ALLOWNEW'];
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 One or more members were selected and/or a primary command not recognized by LMMDISP was entered.
- 4 The requested data sets were empty, or no members matched the specified pattern.
- 8 END or RETURN was entered.
- 10 No data set is associated with the given data ID; LMUNIT has not been completed.
- 12 Indicates one of the following conditions:
- Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

GET Option

Command Invocation Format

```
ISPEXEC LMMDISP DATAID(data-id)
        OPTION(GET)
        [STATS(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
             , 'GET
             '
             , ['YES ' | 'NO ']);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Successful completion.
- 8 No more selected members.
- 10 No data set is associated with the given data ID; LMINIT has not been completed.
- 12 Indicates one of the following conditions:
 - Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

PUT Option

Command Invocation Format

```
ISPEXEC LMMDISP DATAID(data-id)
        OPTION(PUT)
        MEMBER(member-name)
        [ZLLCMD(lcmd-value)]
        [ZLUDATA(udata-value)]
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
             , 'PUT
             '
             , member-name
             '
             '
             '
             '
             '
             '
             , [lcmd-value]
             , [udata-value]);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Successful completion.
- 8 Specified member does not exist.

LMMDISP

- 10 No data set is associated with the given data ID; LMINIT has not been completed.
- 12 Indicates one of the following conditions:
 - Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

ADD Option

Command Invocation Format

```
ISPEXEC LMMDISP DATAID(data-id)
        OPTION(ADD)
        MEMBER(member-name)
        [ZLLCMD(lcmd-value)]
        [ZLUDDATA(udata-value)]
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
            , 'ADD '
            , member-name
            , ' '
            , ' '
            , ' '
            , ' '
            , ' '
            , ' '
            , [lcmd-value]
            , [udata-value]);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Successful completion.
- 8 Member already exists in member list.
- 10 No data set is associated with the given data ID; LMINIT has not been completed.
- 12 Indicates one of the following conditions:
 - Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

DELETE Option

Command Invocation Format

```
ISPEXEC LMMDISP DATAID(data-id)
        OPTION(DELETE)
        MEMBER(member-name)
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
             , 'DELETE '
             , member-name);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Successful completion.
- 8 A specified member does not exist in the member list.
- 10 No data set is associated with the given data ID; LMINIT has not been completed.
- 12 Indicates one of the following conditions:
 - Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

FREE Option**Command Invocation Format**

```
ISPEXEC LMMDISP DATAID(data-id)
        OPTION(FREE)
```

Call Invocation Format

```
CALL ISPLINK('LMMDISP ', data-id
             , 'FREE ');
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Successful completion.
- 8 No member list is associated with the given data ID.
- 10 No data set is associated with the given data ID; LMINIT has not been completed.
- 12 Indicates one of the following conditions:
 - Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMMFIND - Find a Library Member

Command Invocation Format

```
ISPEXEC LMMFIND DATAID(data-id)
          MEMBER(member-name)
          [LOCK]
          [LRECL(lrecl-var)]
          [RECFM(recfm-var)]
          [GROUP(group-var)]
          [STATS(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK ('LMMFIND ',data-id
              ,member-name
              ,['LOCK  ']
              ,[lrecl-var]
              ,[recfm-var]
              ,[group-var]
              ,['YES   '| 'NO   ']);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion. If you specify LOCK and the member is in a controlled ISPF library, a return code of zero shows that the user is a valid user as specified by the member access ID. The member is available and is now currently owned by the user. The member is not available for updating by any other user. For more information about the member access ID, see *ISPF Library Management Facility*
- 4 One of the following:
 - Member not available; the member resides in a controlled ISPF library and is currently owned by another user.
 - Member not available; the member resides in a controlled ISPF library, and the user is not a valid user as specified by the member access ID.
 - Lock was requested but the project is SCLM-controlled.
- 8 Member not found.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:
 - Data set is not open or is not open for input.
 - The parameter value is invalid.
 - Data set is not partitioned.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMMLIST - List a Library's Members

Command Invocation Format

```
ISPEXEC LMMLIST DATAID(data-id)
          [OPTION(LIST|FREE|SAVE)]
          [MEMBER(member-var)]
          [STATS(YES|NO)]
          [GROUP(group)]
          [PATTERN(member-pattern)]
```

Call Invocation Format

```
CALL ISPLINK ('LMMLIST ',data-id
             ,['LIST ' | 'FREE ' | 'SAVE ' ]
             ,[member-var]
             ,['YES ' | 'NO ' ]
             ,[group])
             ,[member-pattern]);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0** One of the following:
- LIST option - Normal completion. The member list is available and the next member in the list is returned in the member-var parameter.
 - FREE option - Normal completion. The member list is freed successfully.
 - SAVE option - Normal completion. The member list is successfully written to the data set.
- 4** Empty member list.
- 8** One of the following:
- LIST option - End of member list.
 - FREE option - Member list does not exist.
 - SAVE option - For a data ID, the LMMLIST service was invoked with the SAVE option after being invoked with the LIST option, but before being invoked with the FREE option.
- 10** No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12** One of the following:
- The data set is not open or is not partitioned.
 - The parameter value is invalid.
 - Member list was created using LMMDISP.
- 16** Truncation or translation error in accessing dialog variables.
- 20** Severe error; unable to continue.

LMMOVE - Move Members of a Data Set

Command Invocation Format

```
ISPEXEC LMMOVE FROMID(from-data-id)
              [FROMMEM(from-member-name)]
              TODATAID(to-data-id)
              [TOMEM(to-member-name)]
              [REPLACE]
              [PACK]
              [TRUNC]
              [SCLMSET(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK ('LMMOVE ' ,from-data-id
             ,[from-member-name]
             ,to-data-id
             ,[to-member-name]
             ,['REPLACE ' ]
             ,['PACK ' ]
             ,['TRUNC ' ]);
             ,['YES|NO ' ]
```

LMMOVE

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Successful completion. |
| 4 | One of the following: <ul style="list-style-type: none">• "From" data set is empty.• No member matched the pattern in the "from" data set. |
| 8 | "From" member not found. |
| 10 | No data set is associated with given data ID. |
| 12 | One of the following: <ul style="list-style-type: none">• Invalid data set organization.• Data set attribute invalid for packed data.• Open error.• A like named member already exists in the 'TO' data set, and the Replace option was not specified.• One or more members of the 'TO' data set are "in use" by you or another user and could not be copied. |
| 16 | Truncation error. |
| 20 | Severe error; unable to continue. |

LMMREN - Rename a Data Set Member

Command Invocation Format

```
ISPEXEC LMMREN DATAID(data-id)
          MEMBER(old-member-name)
          NEWNAME(new-member-name)
          [NOENQ]
```

Call Invocation Format

```
CALL ISPLINK('LMMREN ',data-id
             ,old-member-name
             ,new-member-name)
            ,['NOENQ'];
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 4 | Directory already contains the specified new name. |
| 8 | Member not found. |
| 10 | No data set is associated with the given data ID; that is, LMINIT has not been completed. |
| 12 | One of the following: <ul style="list-style-type: none">• The data set is not open or is not open for output.• The parameter value is invalid.• The data set organization is invalid. |
| 20 | Severe error; unable to continue. |

LMMREP - Replace a Member of a Data Set

Command Invocation Format

```
ISPEXEC LMMREP DATAID(data-id)
          MEMBER(member-name)
          [STATS(YES|NO)]
          [NOENQ]
```

Call Invocation Format

```
CALL ISPLINK('LMMREP ',data-id
             ,member-name
             ,['YES ' | 'NO '])
             ,['NOENQ'];
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion.
- 8 Member is added; it did not previously exist.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:
 - The data set is not open or is not open for output.
 - The parameter value is invalid.
 - The data set organization is invalid.
 - Some member statistics have invalid values.
- 14 No record has been written for the member to be replaced.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMMSTATS - Set and Store ISPF Statistics

Command Invocation Format

```
ISPEXEC LMMSTATS DATAID(data-id) MEMBER(member-name)
          [VERSION(version-number)]
          [MODLEVEL(mod-level)]
          [CREATED(create-date)]
          [MODDATE(last-modified-date)]
          [MODTIME(last-modified-time)]
          [CURSIZE(current-size)]
          [INITSIZE(initial-size)]
          [MODRECS(records-modified)]
          [USER(user-id)]
          [DELETE]
          [CREATED4(4-char-year-create-date)]
          [MODDATE4(4-char-year-last-modified-date)]
          [SCLM(ON|OFF|ASIS)]
```

Call Invocation Format

```
CALL ISPLINK ('LMMSTATS',data-id
             ,member-name
             ,[version-number]
             ,[mod-level]
             ,[create-date]
```

LMMSTATS

```
,[last-modified-date]  
,[last-modified-time]  
,[current-size]  
,[initial-size]  
,[records-modified]  
,[user-id]  
,['DELETE ']  
,[4-char-year-create-date]  
,[4-char-year-last-modified-date]  
,[ON|OFF|ASIS]);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Normal completion.
- 4 One of the following:
 - Data set is empty.
 - No members matched the pattern.
- 8 Member not found.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:
 - Invalid parameter value.
 - Data set is not partitioned.
 - Data ID represents a concatenation of data sets.
 - Data set is open for output.
- 20 Severe error; unable to continue.

LMOOPEN - Open a Data Set

Command Invocation Format

```
ISPEXEC LMOOPEN DATAID(data-id)  
                [OPTION(INPUT|OUTPUT)]  
                [LRECL(lrecl-var)]  
                [RECFM(recfm-var)]  
                [ORG(org-var)]
```

Call Invocation Format

```
CALL ISPLINK ('LMOOPEN ',data-id  
             ,['INPUT ' | 'OUTPUT ']  
             ,[lrecl-var]  
             ,[recfm-var]  
             ,[org-var]);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion.
- 8 Data set could not be opened.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:

- The parameter value is invalid.
 - Data set is already open.
 - Cannot open concatenated data sets for output.
 - Cannot open a data set allocated SHR for output.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMPRINT - Print a Partitioned or Sequential Data Set

Command Invocation Format

```
ISPEXEC LMPRINT DATAID(data-id)
                [MEMBER(member-name)]
                [INDEX]
                [FORMAT(YES|NO)]
```

Call Invocation Format

```
CALL ISPLINK ('LMPRINT ',data-id
              ,[member-name]
              ,['INDEX '])
              ,['YES ' | 'NO ']);
```

OR

```
CALL ISPEXEC (buf-len,buffer);
```

Return Codes

- 0 Normal completion.
- 4 One of the following:
- Data set is empty.
 - No members matched the pattern.
- 8 Member not found.
- 10 No data set associated with given data ID.
- 12 One of the following:
- Invalid data set organization; must be partitioned or sequential.
 - Invalid parameter.
- 20 Severe error; unable to continue.

LMPUT - Write a Logical Record to a Data Set

Command Invocation Format

```
ISPEXEC LMPUT DATAID(data-id)
            MODE(INVAR|MOVE)
            DATALOC(data-loc-var)
            DATALEN(data-length)
            [NOBSCAN]
```

Call Invocation Format

```
CALL ISPLINK ('LMPUT ',data-id
              ,['INVAR ' | 'MOVE '])
              ,data-loc-var
              ,data-length
              ,['NOBSCAN ']);
```

LMPUT

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12 One of the following:
 - The data set is not open or is not open for output.
 - The parameter value is invalid.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMQUERY - Give a Dialog Information about a Data Set

Command Invocation Format

```
ISPEXEC LMQUERY DATAID(data-id)
      [PROJECT(proj-var)] [GROUP1(group1-var)]
      [GROUP2(group2-var)] [GROUP3(group3-var)]
      [GROUP4(group4-var)] [TYPE(type-var)]
      [DATASET(dsn-var)] [DDNAME(ddn-var)]
      [VOLUME(serial-var)] [ENQ(enq-var)]
      [OPEN(open-var)] [LRECL(lrecl-var)]
      [RECFM(recfm-var)] [DSORG(dsorg-var)]
      [ALIAS(alias-var)] [PASSWORD(password-var)]
```

Call Invocation Format

```
CALL ISPLINK ('LMQUERY ',data-id
             ,[proj-var] ,[group1-var]
             ,[group2-var] ,[group3-var]
             ,[group4-var] ,[type-var]
             ,[dsn-var] ,[ddn-var]
             ,[serial-var]
             ,[enq-var]
             ,[open-var] ,[lrecl-var]
             ,[recfm-var] ,[dsorg-var]
             ,[alias-var] ,[password-var]);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion.
- 4 No applicable information available for a specified keyword; blanks are returned.
- 10 No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 16 Truncation or translation error in accessing dialog variables.
- 20 Severe error; unable to continue.

LMRENAME - Rename an ISPF Library

Command Invocation Format

```
ISPEXEC LMRENAME PROJECT(project)
                    GROUP(group)
                    TYPE(type)
                    { [NEWPROJ(new-project)]
                      [NEWGROUP(new-group)]
                      [NEWTYPED(new-type)] }
```

Call Invocation Format

```
CALL ISPLINK('LMRENAME',project
             ,group
             ,type
             ,{[new-project]
              ,[new-group]
              ,[new-type] });
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

0	Normal completion.
4	New name already exists.
8	One of the following: <ul style="list-style-type: none"> • Specified data set does not exist. • Rename or catalog failed. • Data set name is an alias.
12	The parameter value is invalid.
20	Severe error; unable to continue.

LOG - Write a Message to the Log Data Set

Command Invocation Format

```
ISPEXEC LOG MSG(message-id)
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('LOG      ', message-id);
```

Return Codes

0	Normal completion.
12	The message ID contains invalid syntax or was not found.
20	Severe error.

MEMLIST - Member List Dialog

Command Invocation Format

```
ISPEXEC MEMLIST DATAID(data-id)
      [MEMBER(pattern)]
      [CONFIRM(YES|NO)]
      [PANEL(panel-name)]
      [FIELD(1|9)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('MEMLIST ', data-id,
             [,pattern]
             [,YES|NO]
             [,panel-name]
             [,1|9]);
```

Return Codes

- | | |
|----|---|
| 0 | Normal completion. |
| 8 | The requested data set was empty or no members matched the specified pattern. |
| 10 | No data set is associated with the given data ID. LMINIT has not been completed. |
| 12 | One of the following: <ul style="list-style-type: none"> • Data set not partitioned. • Parameter value not valid. • Invocation syntax not valid. |
| 16 | A truncation or translation error occurred in accessing dialog variables. |
| 20 | Severe error. |

PQUERY - Obtain Panel Information

Command Invocation Format

```
ISPEXEC PQUERY PANEL(panel-name) AREANAME(area-name)
      [AREATYPE(area-type-name)]
      [WIDTH(area-width-name)]
      [DEPTH(area-depth-name)]
      [ROW(row-number-name)]
      [COLUMN(column-number-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('PQUERY ', panel-name, area-name
             [,area-type-name])
```

```
[,area-width-name]
[,area-depth-name]
[,row-number-name]
[,column-number-name]);
```

Return Codes

- 0 Normal completion.
- 8 The panel does not contain the specified area.
- 12 The specified panel cannot be found.
- 16 Not all values are returned because insufficient space was provided.
- 20 Severe error.

QBASELIB - Query Base Library Information

Command Invocation Format

```
ISPEXEC QBASELIB dd-name [ID(id-var)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('QBASELIB',dd-name,[,id-var]);
```

Return Codes

- 0 A DDNAME for the specified dd-name exists and the requested information, if any, has been successfully returned.
- 4 The specified dd-name is not valid.
- 16 A dialog variable translation or truncation error has occurred.
- 20 A severe error has occurred.

QLIBDEF - Query LIBDEF Definition Information

Command Invocation Format

```
ISPEXEC QLIBDEF lib-type [TYPE(type-var)] [ID(id-var)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('QLIBDEF ',lib-type,[,type-var][,id-var]);
```

Return Codes

- 0 A LIBDEF definition for the specified lib-type exists and the requested information, if any, has been successfully returned.
- 4 The specified lib-type does not have an active LIBDEF definition.

QLIBDEF

- 12 An invalid lib-type value of ISPPROF has been specified.
- 16 A dialog variable translation or truncation error has occurred.
- 20 A severe error has occurred.

REMPop - Remove a Pop-Up Window

Command Invocation Format

```
ISPEXEC REMPOP [ ALL ]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('REMPop ' [, 'ALL ']);
```

Return codes

- 0 Normal completion.
- 16 A pop-up window does not exist at this select level.
- 20 Severe error.

SELECT - Select a Panel or Function

Command Invocation Format

```
ISPEXEC SELECT { PANEL(panel-name) [OPT(option)] [ADDPop] }  
                { CMD(command) [LANG(APL|CREX)] }  
                { [MODE(LINE|FSCR)] }  
                { [BARRIER] }  
                { [NEST] }  
                { PGM(program-name) [PARM(parameters)] }  
                { [MODE(LINE|FSCR)] }  
                { WSCMD(workstation-command) }  
                { [MODAL|MODELESS] }  
                { [WSDIR(DIR)] }  
                { [MAX|MIN] }  
                { [VIS|INVIS] }  
                { WSCMDV(var_name) }  
                { [MODAL|MODELESS] }  
                { [WSDIR(DIR)] }  
                { [MAX|MIN] }  
                { [VIS|INVIS] }  
  
                [NEWAPPL [(application-id)] [PASSLIB]] | [NEWPOOL] [SUSPEND]  
                [SCRNAME(screen-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('SELECT ', length, keywords);
```

Note: parameters that can appear in *keywords* are:

```

{ PANEL(panel-name) [OPT(option)] [ADDDPOP] }
{
{ CMD(command) [LANG(APL|CREX)] }
{ [MODE(LINE|FSCR)] }
{ [BARRIER] }
{ [NEST] }
{
{ PGM(program-name) [PARM(parameters)] }
{ [MODE(LINE|FSCR)] }
{ WSCMD(workstation-command) }
{ [MODAL|MODELESS] }
{ [WSDIR(DIR)] }
{ [MAX|MIN] }
{ [VIS|INVIS] }
{ WSCMDV(var_name) }
{ [MODAL|MODELESS] }
{ [WSDIR(DIR)] }
{ [MAX|MIN] }
{ [VIS|INVIS] }
{
[NEWAPPL [(application-id)][PASSLIB]]|[NEWPOOL] [SUSPEND]
[SCRNAME(screen-name)]

```

Return Codes

The following return codes are possible if a panel is specified:

- 0 Normal completion. The END command was entered from the selected menu.
- 4 Normal completion. The RETURN command was entered or the EXIT option was specified from the selected menu or from some lower-level menu.
- 12 The specified panel could not be found.
- 16 Truncation error in storing the ZCMD or ZSEL variable.
- 20 Severe error.

Notes:

1. A return code of 0 is returned when the SELECT service has been coded with no other parameters.
2. If a command or program is invoked by using SELECT, the return code from the command or program is passed to the function that invoked SELECT.

The following return codes are possible from a MODAL workstation command:

- 20 Parameter or syntax on SELECT service (all SELECTs) is not valid.
- 41 A null command was passed to the workstation.
- 42 ISPF was not able to start the command at the workstation.
- 43 Remote execution of commands was not allowed by the user.

OTHER

The return code from the workstation command + 100 if the return code from the workstation command was > 0.

SETMSG - Set Next Message

Command Invocation Format

```

ISPEXEC SETMSG MSG(message-id)
           [COND]
           [MSGLOC(message-field-name)]

```

SETMSG

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('SETMSG ', message-id [, 'COND ']  
                                     [,message-field-name]);
```

Return Codes

0	Normal completion.
4	SETMSG with COND parameter issued and a SETMSG request was pending.
12	The specified message field name or message could not be found.
20	Severe error.

TBADD - Add a Row to a Table

Command Invocation Format

```
ISPEXEC TBADD table-name  
              [SAVE(name-list)]  
              [ORDER]  
              [MULT(number-of-rows)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('TBADD ', table-name  
              [,name-list]  
              [, 'ORDER ']  
              [,number-of-rows]);
```

Return Codes

0	Normal completion.
4	The number-of-rows parameter was specified but storage was obtained for only a single row.
8	A row with the same key already exists; CRP set to TOP (zero). Returned only for tables with keys.
12	Table is not open.
16	Numeric convert error; see numeric restrictions for TBSORT. Returned only for sorted tables.
20	Severe error.

TBBOTTOM - Set the Row Pointer to Bottom

Command Invocation Format

```
ISPEXEC TBBOTTOM table-name [SAVENAME(var-name)]
                               [ROWID(rowid-name)]
                               [NOREAD]
                               [POSITION(crp-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBBOTTOM', table-name [,var-name]
                                                    [,rowid-name]
                                                    [, 'NOREAD ' ]
                                                    [,crp-name]);
```

Return Codes

0	Normal completion.
8	Table is empty; CRP set to TOP (zero).
12	Table is not open.
16	Variable value has been truncated, or insufficient space was provided to return all extension variable names.
20	Severe error.

TBCLOSE - Close and Save a Table

Command Invocation Format

```
ISPEXEC TBCLOSE table-name [NEWCOPY|REPLCOPY]
                               [NAME(alt-name)]
                               [PAD(percentage)]
                               [LIBRARY(library)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBCLOSE ', table-name [, 'NEWCOPY ' | 'REPLCOPY' ]
                                                    [, alt-name]
                                                    [, percentage]
                                                    [, library]);
```

Return Codes

0	Normal completion.
12	Table is not open.
16	Alternate table output library was not allocated.
20	Severe error.

TBCREATE

TBCREATE - Create a New Table

Command Invocation Format

```
ISPEXEC TBCREATE table-name [KEYS(key-name-list)]
                               [NAMES(name-list)]
                               [WRITE|NOWRITE]
                               [REPLACE]
                               [LIBRARY(library)]
                               [SHARE]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBCREATE', table-name [,key-name-list]
            [,name-list]
            [,'WRITE ']'|'NOWRITE '])
            [,'REPLACE '])
            [,library]
            [,'SHARE ']);
```

Return Codes

0	Normal completion.
4	Normal completion—a duplicate table exists but REPLACE was specified.
8	Either the table already exists and REPLACE was not specified, or REPLACE was specified and the table is in SHARE mode.
12	Table in use; ENQ failed.
16	WRITE mode specified and alternate table input library not allocated. TBCREATE checks the input library to determine if a duplicate table exists. See return code 8.
20	Severe error.

TBDELETE - Delete a Row from a Table

Command Invocation Format

```
ISPEXEC TBDELETE table-name
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBDELETE', table-name);
```

Return Codes

0	Normal completion.
---	--------------------

- 8 Keyed tables: the row specified by the value in key variables does not exist; CRP set to TOP (zero). Non-keyed tables: CRP was at TOP (zero) and remains at TOP.
- 12 Table is not open.
- 20 Severe error.

TBDISPL - Display Table Information

Command Invocation Format

```
ISPEXEC TBDISPL table-name [PANEL(panel-name)]
                             [MSG(message-id)]
                             [CURSOR(field-name)]
                             [CSRROW(table-row-number)]
                             [CSRPOS(cursor-position)]
                             [AUTOSEL(YES|NO)]
                             [POSITION(crp-name)]
                             [ROWID(rowid-name)]
                             [MSGLOC(message-field-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
CALL ISPLINK ('TBDISPL ', table-name [,panel-name]
                                           [,message-id]
                                           [,field-name]
                                           [,table-row-number]
                                           [,cursor-position]
                                           [,'YES ' | 'NO ' ]
                                           [,crp-name]
                                           [,rowid-name]
                                           [,message-field-name]);
```

Return Codes

- 0 If the panel definition contains neither a)REINIT nor a)PROC section, the Enter key was pressed, or a scroll command was entered. Any of the following occurred:
 - One row was selected in the scrollable part of the display. The CRP is set to point to that table row and the row is retrieved. The input fields from the selected model set on the display are then stored in the function pool.
 - The user entered information into the fixed portion of the display.
 - All of the following:
 - A scroll return to function has been specified (ZTDRET defined to UP, DOWN, or VERTICAL).
 - More rows are needed to fill a scroll request.
 - No selected rows remain to be processed.

If the panel definition contains a)REINIT or)PROC section, there is the additional possibility that the user entered no information and just pressed Enter.

- 4 The Enter key was pressed or a scroll command was entered. The first or both of the following occurred:
 - Two or more rows in the scrollable part of the display were selected. The CRP is set to the first selected row and the row is retrieved. The input fields from the selected model set on the display are then stored in the function pool.
 - The user entered information into the fixed portion of the display.

TBDISPL

- If scroll return to function has been specified, and two or more rows are selected for processing, TBDISPL returns a return code 4 until all selected rows are processed. You process the request for more rows to be added to the table only after all selected rows have been processed; that is, only when ZTDSELS has a value of 0.

For subsequent TBDISPL requests with no panel name and no message ID, return code 4 is issued for each request until one selected row remains to be accessed. For this last row, a return code of zero is issued by TBDISPL, still specified with no panel name and no message ID. The variable ZTDSELS will have a value of one.

- 8 The END or RETURN command was entered. For panels created by the tag conversion utility, CANCEL and EXIT commands also give a return code of 8. If CANCEL and EXIT are requested from a panel displayed using TBDISPL service calls and the panel was defined with dialog tag language (DTL), the dialog manager returns the command in ZVERB and sets a return code of 8 from the display screen. The CRP is set to the first of any selected rows in the scrollable part of the display. The input fields from the selected model set on the display are then stored in the function pool. If no rows were selected, the CRP is at the top (zero). To process all selected rows when END or RETURN was entered, continue to issue TBDISPL requests with no panel name or message ID specified until ZTDSELS is one.

If the user enters the END command on a table display panel, a subsequent redisplay will result in a return code of 8.

The user may have entered information into the fixed portion of the display.

- 12 The specified panel, message, cursor field, or message location field could not be found.
- 16 Truncation or translation error in storing defined variables.
- 20 Severe error.

TBEND - Close a Table without Saving

Command Invocation Format

```
ISPEXEC TBEND table-name
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBEND ', table-name);
```

Return Codes

- 0 Normal completion.
- 12 Table is not open.
- 20 Severe error.

TBERASE - Erase a Table

Command Invocation Format

```
ISPEXEC TBERASE table-name [LIBRARY(library)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBERASE ', table-name [,library]);
```

Return Codes

0	Normal completion.
8	Table does not exist in the output library.
12	Table in use; ENQ failed.
16	Table output library not allocated.
20	Severe error.

TBEXIST - Determine Whether a Row Exists in a Table

Command Invocation Format

```
ISPEXEC TBEXIST table-name
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBEXIST ', table-name);
```

Return Codes

0	Normal completion; the CRP is positioned to the specified row.
8	Keyed tables: the specified row does not exist; the CRP is set to TOP (zero). Non-keyed tables: service not possible; the CRP is set to TOP.
12	Table is not open.
20	Severe error.

TBGET - Retrieve a Row from a Table

Command Invocation Format

```
ISPEXEC TBGET table-name [SAVENAME(var-name)]
                        [ROWID(rowid-name)]
                        [NOREAD]
                        [POSITION(crp-name)]
```

TBGET

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('TBGET ', table-name [,var-name]  
                                     [,rowid-name]  
                                     [,'NOREAD '  
                                     [,crp-name]);
```

Return Codes

0	Normal completion.
8	Keyed tables: The row specified by the value in the key variables does not exist; the CRP is set to TOP (zero). Non-keyed tables: the CRP was at TOP and remains at TOP.
12	Table is not open.
16	Variable value has been truncated, or insufficient space was provided to return all extension variable names.
20	Severe error.

TBMOD - Modify a Row in a Table

Command Invocation Format

```
ISPEXEC TBMOD table-name [SAVE(name-list)]  
                          [ORDER]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('TBMOD ', table-name [,name-list]  
                                     ['ORDER ']);
```

Return Codes

0	Normal completion. Keyed tables: Existing row was updated. Non-keyed tables: New row was added to table.
8	Keys did not match; new row was added to the table. Returned only for tables with keys.
12	Table is not open.
16	Numeric conversion error; see numeric restrictions for TBSORT. Returned only for sorted tables.
20	Severe error.

TBOPEN - Open a Table

Command Invocation Format

```
ISPEXEC TBOPEN table-name [WRITE|NOWRITE]
                             [LIBRARY(library)]
                             [SHARE]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBOPEN ', table-name [, 'WRITE ' | 'NOWRITE ' ]
                                                    [, library]
                                                    [, 'SHARE ' ]);
```

Return Codes

0	Normal completion.
8	Table does not exist.
12	ENQ failed; table was in use by another user or the current user.
16	Table input library was not allocated.
20	Severe error.

TBPUT - Update a Row in a Table

Command Invocation Format

```
ISPEXEC TBPUT table-name [SAVE(name-list)]
                             [ORDER]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBPUT ', table-name [, name-list]
                                                    [, 'ORDER ' ]);
```

Return Codes

0	Normal completion.
8	Keyed tables: the key does not match that of the current row; CRP set to TOP (zero). Non-keyed tables: CRP was at TOP and remains at TOP.
12	Table is not open.
16	For sorted tables: numeric conversion error; see numeric restrictions for TBSORT.
20	Severe error.

TBQUERY - Obtain Table Information

Command Invocation Format

```
ISPEXEC TBQUERY table-name [KEYS(key-name)]
                             [NAMES(var-name)]
                             [ROWNUM(rownum-name)]
                             [KEYNUM(keynum-name)]
                             [NAMENUM(namenum-name)]
                             [POSITION(crp-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBQUERY ', table-name [,key-name]
                                                    [,var-name]
                                                    [,rownum-name]
                                                    [,keynum-name]
                                                    [,namenum-name]
                                                    [,crp-name] );
```

Return Codes

0	Normal completion.
12	Table is not open.
16	Not all keys or names were returned because insufficient space was provided.
20	Severe error.

TBSARG - Define a Search Argument

Command Invocation Format

```
ISPEXEC TBSARG table-name [ARGLIST(name-list)]
                             [NEXT|PREVIOUS]
                             [NAMECOND(name-cond-pairs)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBSARG ', table-name
                                                    [,name-list]
                                                    [,'NEXT'  '|' 'PREVIOUS']
                                                    [,name-cond-pairs]);
```

Return Codes

0	Normal completion.
8	All column variables are null and the name-list parameter was not specified; no argument is established.
12	Table is not open.
20	Severe error.

TBSAVE - Save a Table

Command Invocation Format

```
ISPEXEC TBSAVE table-name [NEWCOPY|REPLCOPY]
                             [NAME(alt-name)]
                             [PAD(percentage)]
                             [LIBRARY(library)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBSAVE ', table-name, [,'NEWCOPY '| 'REPLCOPY'
                                       [,alt-name]
                                       [,percentage]
                                       [,library]);
```

Return Codes

0	Normal completion.
12	Table is not open.
16	Alternate table output library was not allocated.
20	Severe error.

TBSCAN - Search a Table

Command Invocation Format

```
ISPEXEC TBSCAN table-name [ARGLIST(name-list)]
                             [SAVENAME(var-name)]
                             [ROWID(rowid-name)]
                             [NEXT|PREVIOUS]
                             [NOREAD]
                             [POSITION(crp-name)]
                             [CONDLIST(condition-value-list)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);

OR

CALL ISPLINK ('TBSCAN ', table-name [,name-list]
                                       [,var-name]
                                       [,rowid-name]
                                       [,'NEXT '| 'PREVIOUS']
                                       [,'NOREAD '|
                                       [,crp-name]
                                       [,condition-value-list]);
```

Return Codes

0	Normal completion.
8	Row does not exist, no match was found; CRP is set to TOP (zero). The row ID remains unchanged.

TBSCAN

- 12 Table is not open.
- 16 Variable value has been truncated, or insufficient space is provided to return all extension variable names.
- 20 Severe error.

TBSKIP - Move the Row Pointer

Command Invocation Format

```
ISPEXEC TBSKIP table-name [NUMBER(number)]
                             [SAVENAME(var-name)]
                             [ROWID(rowid-name)]
                             [ROW(rowid)]
                             [NOREAD]
                             [POSITION(crp-name)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBSKIP ', table-name [,number]
                                           [,var-name]
                                           [,rowid-name]
                                           [,rowid]
                                           [,'NOREAD ']
                                           [,crp-name]);
```

- 0 Normal completion.
- 8 CRP would have gone beyond the number of rows in the table. This includes a table empty condition, with CRP set to TOP (zero). The row ID remains unchanged.
- 12 Table is not open.
- 16 Variable value has been truncated, or insufficient space is provided to return all extension variable names.
- 20 Severe error.

TBSORT - Sort a Table

Command Invocation Format

```
ISPEXEC TBSORT table-name FIELDS(sort-list)
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBSORT ', table-name, sort-list);
```

Return Codes

- 0 Normal completion.
- 12 Table is not open.
- 16 Numeric convert error.
- 20 Severe error.

TBSTATS - Retrieve Table Statistics

Command Invocation Format

```
ISPEXEC TBSTATS table-name [CDATE(date-created-name)]
                             [CTIME(time-created-name)]
                             [UPDATE(date-updated-name)]
                             [UTIME(time-updated-name)]
                             [USER(user-name)]
                             [ROWCREAT(row-created-name)]
                             [ROWCURR(rownum-name)]
                             [ROWUPD(row-updated-name)]
                             [TABLEUPD(table-updated-name)]
                             [SERVICE(service-name)]
                             [RETCODE(return-code-name)]
                             [STATUS1(status1-name)]
                             [STATUS2(status2-name)]
                             [STATUS3(status3-name)]
                             [LIBRARY(library)]
                             [CDATE4D(date-created-name-4-digit)]
                             [UPDATE4D(date-updated-name-4-digit)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('TBSTATS ', table-name [,date-created-name]
                                       [,time-created-name]
                                       [,date-updated-name]
                                       [,time-updated-name]
                                       [,user-name]
                                       [,row-created-name]
                                       [,rownum-name]
                                       [,row-updated-name]
                                       [,table-updated-name]
                                       [,service-name]
                                       [,return-code-name]
                                       [,status1-name]
                                       [,status2-name]
                                       [,status3-name]
                                       [,library]
                                       [,date-created-name-4-digit]
                                       [,date-updated-name-4-digit]);
```

Return Codes

0	Normal completion (returned even if the table does not exist).
16	Variable value has been truncated.
20	Severe error.

TBTOP - Set the Row Pointer to the Top

Command Invocation Format

```
ISPEXEC TBTOP table-name
```

TBTOP

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('TBTOP ', table-name);
```

Return Codes

0	Normal completion.
12	Table is not open.
20	Severe error.

TBVCLEAR - Clear Table Variables

Command Invocation Format

```
ISPEXEC TBVCLEAR table-name
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);  
  
OR  
  
CALL ISPLINK ('TBVCLEAR', table-name);
```

Return Codes

0	Normal completion.
12	Table is not open.
20	Severe error.

TRANS - Translate Data from One Coded Character Set Identifier (CCSID) to Another

Command Invocation Format

```
ISPEXEC TRANS FRMCCSID(from-ccsid-number)  
              TOCCSID(to-ccsid-number)  
              FROMVAR(from-variable-name)  
              [TOVAR(to-variable-name)]  
              [LENGTH(data-length)]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer)  
  
OR  
  
CALL ISPLINK ('TRANS ', from-ccsid-number, to-ccsid-number,  
             from-variable-name  
             [, to-variable-name]  
             [, data-length]);
```

Return Codes

0	Normal completion.
4	Translation tables do not support the requested 'to/from' combination.
8	From variable not found.
16	Variable services indicated a translation error or truncation occurred storing the translated data.
20	Severe error.

VCOPY - Create a Copy of a Variable

Command Invocation Format

ISPEXEC *This service does not apply to APL2 or command procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used with this interface*

OR

```
CALL ISPLINK ('VCOPY ', name-list, length-array, value-array
              [, 'LOCATE ' | 'MOVE ' ] );
```

Return Codes

0	Normal completion.
8	One or more variables do not exist.
12	Validation failed.
16	Truncation has occurred during data movement (move mode only).
20	Severe error.

VDEFINE - Define Function Variables

Command Invocation Format

ISPEXEC *This service does not apply to APL2 or command procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used with this interface*

OR

```
CALL ISPLINK ('VDEFINE ', name-list, variable, format, length
              [,options-list]
              [,user-data]);
```

Return Codes

0	Normal completion.
8	Variable not found.
16	Data truncation occurred.
20	Severe error.

VDELETE

VDELETE - Remove a Definition of Function Variables

Command Invocation Format

```
ISPEXEC *This service does not apply to APL2 or
        command procedures*
```

Call Invocation Format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

```
CALL ISPLINK ('VDELETE ', name-list|'* ');
```

Return Codes

0	Normal completion.
8	At least one variable not found.
20	Severe error.

VERASE - Remove Variables from Shared and/or Profile Pool

Command Invocation Format

```
ISPEXEC VERASE name-list
            [ASIS|SHARED|PROFILE|BOTH]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('VERASE ', name-list
            [, 'ASIS ' | 'SHARED ' | 'PROFILE ' | 'BOTH ' ] );
```

Return Codes

0	Normal completion.
8	At least one variable not found.
20	Severe error.

VGET - Retrieve Variables from a Pool or Profile

Command Invocation Format

```
ISPEXEC VGET name-list [ASIS|SHARED|PROFILE]
```

Call Invocation Format

```
CALL ISPEXEC (buf-len, buffer);
```

OR

```
CALL ISPLINK ('VGET ', name-list
            [, 'ASIS ' | 'SHARED ' | 'PROFILE ' ] );
```

Return Codes

0	Normal completion.
8	Variable not found.
12	Validation failed.
16	Translation error or truncation occurred during data movement.
20	Severe error.

VIEW - View a Data Set

Command Invocation Format

```
ISPEXEC VIEW DATASET(dsname) [VOLUME(serial)]
                                [PASSWORD(pswd-value)]
                                [PANEL(panel-name)]
                                [MACRO(macro-name)]
                                [PROFILE(profile-name)]
                                [FORMAT(format-name)]
                                [MIXED(YES|NO)]
                                [CONFIRM(YES|NO)]
                                [WS(YES|NO)]
                                [CHGWARN(YES|NO)]
                                [PARAM(parm-var)]
```

OR

```
ISPEXEC VIEW DATAID(data-id) [MEMBER(member-name)]
                                [PANEL(panel-name)]
                                [MACRO(macro-name)]
                                [PROFILE(profile-name)]
                                [FORMAT(format-name)]
                                [MIXED(YES|NO)]
                                [CONFIRM(YES|NO)]
                                [WS(YES|NO)]
                                [CHGWARN(YES|NO)]
                                [PARAM(parm-var)]
```

OR

```
ISPEXEC VIEW WSFN(ws-filename) [PANEL(panel-name)]
                                [MACRO(macro-name)]
                                [PROFILE(profile-name)]
                                [FORMAT(format-name)]
                                [MIXED(YES|NO)]
                                [CONFIRM(YES|NO)]
                                [WS(YES|NO)]
                                [CHGWARN(YES|NO)]
                                [PARAM(parm-var)]
```

Call Invocation Format

```
CALL ISPLINK ('VIEW ', {dsname} , [serial]
              , [pswd-value]
              , [panel-name]
              , [macro-name]
              , [profile-name]
              , {data-id}
              , [member-name]
              , [format-name]
              , ['YES' | 'NO']
              , ['YES' | 'NO'])
              , {ws-filename-buffer-name}
              , ['YES' | 'NO']
              , ['YES' | 'NO']
              , [parm-var]);
```


- 4 The PDF component should process the requested function.
- 12 Command deferred; retain the command on the Command line. View data is redisplayed.
- 20 Severe error. (VIIF service terminates immediately with a return code of 20.)

VIIF Return Codes

- 0 Normal completion, data saved.
- 4 Normal completion, data not saved.
- 12 View has been disabled through the ISPF Configuration table.
- 16 Unexpected return code received from a dialog-supplied routine. When an unexpected return code is received, the EDIF service terminates immediately with a return code of 16.
- 20 Severe error; unable to continue.

VMASK - Associate an Edit Mask with a Dialog Variable

Command Invocation Format

ISPEXEC *This service does not apply to APL2 or command procedures*

Call Invocation Format

```
CALL ISPLINK ('VMASK ' ,name-list{,'FORMAT ' {' , 'IDATE ' ' } }
                                     { , 'STDDATE ' ' } }
                                     { , 'ITIME ' ' } }
                                     { , 'STDTIME ' ' } }
                                     { , 'JDATE ' ' } }
                                     { , 'JSTD ' ' } }
                                     { , 'USER ' ' , 'mask' , masklen) }
```

Return Codes

- 0 Normal completion.
- 8 Variable not found.
- 20 Severe error.

VPUT - Update Variables in the Shared or Profile Pool

Command Invocation Format

ISPEXEC VPUT name-list [ASIS|SHARED|PROFILE]

Call Invocation Format

CALL ISPEXEC (buf-len, buffer);

OR

```
CALL ISPLINK ('VPUT ' , name-list
               [, 'ASIS ' ' | 'SHARED ' ' | 'PROFILE ' ' ] );
```

Return Codes

- 0 Normal completion.
- 8 Variable not found.

VPUT

16 Truncation occurred while copying variables to the application profile pool.
20 Severe error.

VREPLACE - Replace a Variable

Command Invocation Format

ISPEXEC *This service does not apply to
APL2 or command procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used with this interface*

OR

CALL ISPLINK ('VREPLACE', name-list, lengths, values);

Return Codes

0 Normal completion.
16 Truncation has occurred during data movement.
20 Severe error.

VRESET - Reset Function Variables

Command Invocation Format

ISPEXEC *This service does not apply to
APL or command procedures*

Call Invocation Format

CALL ISPEXEC *This service cannot be used with this interface*

OR

CALL ISPLINK ('VRESET ');

Return Codes

0 Normal completion.
20 Severe error.

WSCON — Connect to a Workstation

Command Invocation Format

ISPEXEC WSCON [IP(ip_var_name)]
[LU(lu_var_name)]
[FI]
[TITLE(title_var_name)]
[FRAME(STD | FIX | DLG)]
[BKGRND(STD | DLG)]
[CODEPAGE(codepage)]

```
[CHARSET(character_set)]
[NOGUIDSP]
[PANEL(YES | NO | ONERROR)]
```

Call Invocation Format

```
CALL ISPLINK ('WSCON '
             ,[ip_var_name]
             ,[lu_var_name]
             ,[FI]
             ,[title_var_name]
             ,[STD | FIX | DLG]
             ,[STD | DLG]
             ,[codepage]
             ,[character_set]
             ,[NOGUIDSP]
             ,[YES | NO | ONERROR]);
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion. Connection established.
- 8 The user pressed End, Exit, or Cancel from the *Initiate Workstation Connection* panel without making a connection.
- 12 Already in GUI mode. Recursive error.
- 14 Connecting in GUI mode is not supported when in partition mode or split screen.
- 16 Cannot connect to workstation.
- 20 Parameters not valid or syntax conflict. For example, both IP and LU were specified.

WSDISCON — Connect to a Workstation

Command Invocation Format

```
ISPEXEC WSDISCON
```

Call Invocation Format

```
CALL ISPLINK ('WSDISCON');
```

OR

```
CALL ISPEXEC (buf-len, buffer);
```

Return Codes

- 0 Normal completion. User disconnected from workstation.
- 8 User trying to disconnect from workstation, but there is no current connection.
- 10 User trying to disconnect from GUI mode, but is connected with GUISCRD or GUISCRW values that are different than the host emulator session. User is not disconnected.
- 12 User trying to disconnect from a GUI display when running BATCH GUI mode. User is not disconnected.

WSDISCON

- 14 User trying to disconnect from workstation while running the Workstation Tool Integration Configuration program. User is not disconnected.

Chapter 3. Edit Macro Commands

This chapter contains the syntax and return codes for the ISPF Edit macros. For a complete description of the Edit macros see *ISPF Edit and Edit Macros*

AUTOLIST - Set or Query Autolist Mode

Macro Command Syntax

```
ISREDIT AUTOLIST [ON | OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = AUTOLIST
```

```
ISREDIT AUTOLIST = [ON | OFF]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

AUTONUM - Set or Query Autonum Mode

Macro Command Syntax

```
ISREDIT AUTONUM [ON | OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = AUTONUM
```

```
ISREDIT AUTONUM = [ON | OFF]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

AUTOSAVE - Set or Query Autosave Mode

Macro Command Syntax

```
ISREDIT AUTOSAVE [ON          ]
                  [OFF PROMPT  ]
                  [OFF NOPROMPT]
```

Assignment Statement Syntax

```
ISREDIT (var1,var2) = AUTOSAVE
```

```
ISREDIT AUTOSAVE = [ON          ]
                   [OFF PROMPT  ]
                   [OFF NOPROMPT]
```

AUTOSAVE - BLKSIZE

Return Codes

0	Normal completion.
4	OFF NOPROMPT specified.
20	Severe error.

BLKSIZE - Query the Block Size

Assignment Statement Syntax

ISREDIT (varname) = BLKSIZE

Return Codes

0	Normal completion.
12	Syntax error.
20	Severe error.

BOUNDS - Set or Query the Edit Boundaries

Macro Command Syntax

ISREDIT BOUNDS [left-col right-col]

Assignment Statement Syntax

ISREDIT (var1,var2) = BOUNDS

ISREDIT BOUNDS = [left-col right-col]

Return Codes

0	Normal completion.
4	Right boundary greater than default; default right boundary used.
12	Invalid boundaries specified.
20	Severe error.

BROWSE - Browse from within an Edit Session

Macro Command Syntax

ISREDIT BROWSE member

Return Codes

0	Normal completion
12	Your error (invalid member name, recovery pending)
20	Severe error.

BUILTIN - Process a Built-In Command

Macro Command Syntax

ISREDIT BUILTIN cmdname

Return Codes

n	Return code from the built-in command.
20	Severe error.

CANCEL - Cancel Edit Changes**Macro Command Syntax**

```
ISREDIT CANCEL
```

Return Codes

0	Normal completion.
20	Severe error.

CAPS - Set or Query Caps Mode**Macro Command Syntax**

```
ISREDIT CAPS [ON | OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = CAPS
```

```
ISREDIT CAPS = [ON | OFF]
```

Return Codes

0	Normal completion.
20	Severe error.

CHANGE - Change a Search String**Macro Command Syntax**

```
ISREDIT CHANGE string-1 string-2 [label-range] [NEXT ] [CHARS ] [X ] [col-1 [col-2]]
[ALL ] [PREFIX] [NX]
[FIRST] [SUFFIX]
[LAST ] [WORD ]
[PREV ]
```

Return Codes

0	Normal completion.
4	String not found.
8	Change error. String-2 is longer than string-1 and substitution was not performed on at least one change.
12	Inconsistent parameters. The string to be found will not fit between the specified columns.
20	Severe error.

CHANGE_COUNTS - Query Change Counts

Assignment Statement Syntax

```
ISREDIT (var1,var2) = CHANGE_COUNTS
```

Return Codes

0	Normal completion.
20	Severe error.

COMPARE - Compare Data Set

Macro Command Syntax

```
ISREDIT COMPARE dsname [NEXT ] [SAVE] [SYSIN] [EXCLUDE]
```

Return Codes

0	Normal completion
8	Member or data set not found, or an error opening the member or data set occurred.
12	No parameters specified, or another parameter error such as not valid NEXT or member specification.
20	Severe error. SuperC, allocation, or delta file error occurred.

COPY - Copy Data

Macro Command Syntax

```
ISREDIT COPY member {AFTER } lptr [linenum-range]
                    {BEFORE}
                    (member)
                    data set name
```

Return Codes

0	Normal completion.
8	End of data reached before last record read.
12	Invalid line pointer (lptr); member not found or BLDL error.
16	End of data reached before first record of specified range was reached.
20	Syntax error (invalid name, incomplete range,), or I/O error.

CREATE - Create a Data Set Member

Macro Command Syntax

```
ISREDIT CREATE member lptr-range
                    (member) {range}
                    dataset(member) {range}
```

Return Codes

0	Normal completion.
8	Member already exists, member not created.

- 12 Invalid line pointer (lptr). The referenced line does not exist in the file.
- 20 Syntax error (invalid name or incomplete lptr range), or I/O error.

CTL_LIBRARY - Query Controlled Library Status

Assignment Statement Syntax

```
ISREDIT (var1,var2) = CTL_LIBRARY
```

Return Codes

- 0 Normal completion.
- 20 Severe error.

CURSOR - Set or Query the Cursor Position

Assignment Statement Syntax

```
ISREDIT (var1,var2) = CURSOR
ISREDIT CURSOR = lptr [col]
```

Return Codes

- 0 Normal completion.
- 4 Column number beyond data, line number incremented.
- 12 Invalid line number.
- 20 Severe error.

Note: To set the cursor to the command line, exit your macro with a return code of 1.

CUT — Cut and Save Lines

Assignment Statement Syntax

```
ISREDIT CUT [lptr-range] [DEFAULT | clipboardname[
[REPLACE]
```

Return Codes

- 0 Normal completion.
- 12 Parameter error. Insufficient storage, or no more clipboards available.
- 20 Severe error.

DATA_CHANGED - Query the Data Changed Status

Assignment Statement Syntax

```
ISREDIT (varname) = DATA_CHANGED
```

Return Codes

- 0 Normal completion.
- 20 Severe error.

DATA_WIDTH - Query Data Width

Assignment Statement Syntax

ISREDIT (varname) = DATA_WIDTH

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

DATAID - Query Data ID

Assignment Statement Syntax

ISREDIT (varname) = DATAID

Return Codes

0	The data ID returned was passed to the editor.
4	Data ID was generated by and will be freed by the editor.
8	A previously generated data ID was returned.
20	Severe error.

DATASET - Query the Current Data Set Name

Assignment Statement Syntax

ISREDIT (varname) = DATASET

Return Codes

0	Normal completion.
20	Severe error.

DEFINE - Define a Name

Macro Command Syntax

```
ISREDIT DEFINE name {MACRO CMD }
                   {MACRO PGM  }
                   {ALIAS name-2}
                   {NOP        }
                   {RESET      }
                   {DISABLED   }
```

Return Codes

0	Normal completion.
8	RESET was attempted for a name not currently defined, or DEFINE name ALIAS name-2 requested and name-2 is a NOP.
12	DEFINE was attempted for a name not currently defined.
20	Severe error (unknown command).

DELETE - Delete Lines

Macro Command Syntax

```
ISREDIT DELETE { ALL X | NX [lptr-range] }  
               { [ALL] X | NX lptr-range }  
               { lptr  
               { lptr-range }
```

Return Codes

0	Normal (lines deleted successfully).
4	No lines deleted.
8	No standard records exist.
12	Invalid line number.
20	Severe error.

DISPLAY_COLS - Query Display Columns

Assignment Statement Syntax

```
ISREDIT (var1,var2) = DISPLAY_COLS
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

DISPLAY_LINES - Query Display Lines

Assignment Statement Syntax

```
ISREDIT (var1,var2) = DISPLAY_LINES
```

Return Codes

0	Normal completion.
4	No visible data lines.
8	No existing data lines.
12	Invalid command format.
20	Severe error.

DOWN - Scroll Down

Macro Command Syntax

```
ISREDIT DOWN amt
```

Return Codes

0	Normal completion.
2	No more data DOWN.
4	No visible lines.
8	No data to display.

DOWN - END

- 12 Amount not specified.
- 20 Severe error.

EDIT - Edit from Within an Edit Session

Macro Command Syntax

ISREDIT EDIT member

Return Codes

- 0 Normal completion. Data was saved.
- 4 Normal completion. Data was not saved.
- 12 Your error (invalid member name, recovery pending).
- 14 Member in use.
- 20 Severe error.
- 28 No ISREDIT MACRO statement preceded this call, or BROWSE was substituted because of the size of the member being edited.

END - End the Edit Session

Macro Command Syntax

ISREDIT END

Return Codes

- 0 Normal completion.
- 4 New member saved.
- 12 END not done, AUTOSAVE OFF PROMPT set, or Data not saved (insufficient space).
- 20 Severe error.

EXCLUDE - Exclude Lines from the Panel

Macro Command Syntax

ISREDIT EXCLUDE string [label-range] [NEXT] [CHARS] [col-1 [col-2]]
[ALL] [PREFIX]
[FIRST] [SUFFIX]
[LAST] [WORD]
[PREV]

Return Codes

- 0 Normal completion.
- 4 String not found.
- 8 Line(s) not excluded.
- 12 Inconsistent parameters
- 20 Severe error.

EXCLUDE_COUNTS - Query Exclude Counts

Assignment Statement Syntax

```
ISREDIT (var1,var2) = EXCLUDE_COUNTS
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

FIND - Find a Search String

Macro Command Syntax

```
ISREDIT FIND string [label-range] [NEXT ] [CHARS ] [X ] [col-1 [col-2]]
[ALL ] [PREFIX] [NX]
[FIRST] [SUFFIX]
[LAST ] [WORD ]
[PREV ]
```

Return Codes

0	Normal completion.
4	String not found.
12	Syntax error.
20	Severe error.

FIND_COUNTS - Query Find Counts

Assignment Statement Syntax

```
ISREDIT (var1,var2) = FIND_COUNTS
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

FLIP - Reverse Excluded Status of Lines

Macro Command Syntax

```
ISREDIT FLIP [label-range]
```

Return Codes

0	Successful completion. The excluded status of the requested lines was reversed.
20	Severe error.

FLOW_COUNTS - Query Flow Counts

Assignment Statement Syntax

ISREDIT (var1,var2) = FLOW_COUNTS

Return Codes

0 Normal completion.
20 Severe error.

HEX - Set or Query Hexadecimal Mode

Macro Command Syntax

ISREDIT HEX [ON DATA]
 [ON VERT]
 [OFF]

Assignment Statement Syntax

ISREDIT (var1,var2) = HEX

ISREDIT HEX = [ON DATA]
 [ON VERT]
 [OFF]

Return Codes

0 Normal completion.
20 Severe error.

HILITE - Enhanced Edit Coloring

Macro Command Syntax

ISREDIT HILITE [ON] [AUTO] [RESET] [PAREN] [FIND] [CURSOR] [SEARCH] [DISABLED]
 [OFF] [DEFAULT]
 [LOGIC] [OTHER]
 [IFLOGIC] [ASM]
 [DOLOGIC] [BOOK]
 [NOLOGIC] [C]
 [COBOL]
 [DTL]
 [JCL]
 [PANEL]
 [PASCAL]
 [PLI]
 [REXX]
 [SKEL]
 [IDL]

Return Codes

0 Normal completion.
8 One of the following conditions:
• LOGIC or SEARCH not supported in the current environment
• Invalid language
• HILITE unavailable.

- 12 One of the following conditions:
- HILITE dialog is invalid from an edit macro
 - HILITE not available because of the installation defaults
 - HILITE not available because the edit panel in use is not enabled for enhanced color
 - Other error encountered.
- 20 Severe error. Possibly extra parameters.

IMACRO - Set or Query an Initial Macro

Macro Command Syntax

```
ISREDIT IMACRO {name | NONE}
```

Assignment Statement Syntax

```
ISREDIT (varname) = IMACRO
```

```
ISREDIT IMACRO = name
```

Return Codes

- 0 Normal completion.
- 4 IMACRO set not accepted; profile is locked.
- 12 Invalid name specified.
- 20 Severe error.

INSERT - Prepare Display for Data Insertion

Macro Command Syntax

```
ISREDIT INSERT lptr [numlines]
```

Return Codes

- 0 Normal completion.
- 12 Invalid line number.
- 20 Severe error.

LABEL - Set or Query a Line Label

Assignment Statement Syntax

```
ISREDIT (var1,var2) = LABEL lptr
```

```
ISREDIT LABEL lptr = labelname [level]
```

Return Codes

- 0 Normal completion.
- 4 Label name not returned, specified line has no label.
- 8 Label set, but an existing label at the same level was deleted.
- 12 Line number specified is beyond the end of data.
- 20 Severe error.

LABEL - LEFT

LEFT - Scroll Left

Macro Command Syntax

ISREDIT LEFT amt

Return Codes

0	Normal completion.
4	No visible lines.
8	No data to display.
12	Amount not specified.
20	Severe error.

LEVEL - Set or Query the Mod Level Number

Macro Command Syntax

ISREDIT LEVEL num

Assignment Statement Syntax

ISREDIT (varname) = LEVEL

ISREDIT LEVEL = num

Return Codes

0	Normal completion.
4	Statistics mode is off; the command is ignored.
12	Invalid value specified.
20	Severe error.

LINE - Set or Query a Line from the Data Set

Assignment Statement Syntax

ISREDIT (varname) = LINE lptr

ISREDIT LINE lptr = data

Return Codes

0	Normal completion.
4	Data truncated (line shorter than data supplied).
8	Variable not found.
12	Invalid line number.
16	Variable data truncated.
20	Severe error.

LINE_AFTER - Add a Line to the Current Data Set**Assignment Statement Syntax**

```
ISREDIT LINE_AFTER lptr = [DATALINE] data
                          [INFOLINE]
                          [MSGLINE ]
                          [NOTELINE]
```

Return Codes

0	Normal completion.
4	Data truncated.
12	Invalid line number.
20	Severe error.

LINE_BEFORE - Add a Line to the Current Data Set**Assignment Statement Syntax**

```
ISREDIT LINE_BEFORE lptr = [DATALINE] data
                            [INFOLINE]
                            [MSGLINE ]
                            [NOTELINE]
```

Return Codes

0	Normal completion.
4	Data truncated.
12	Invalid line number.
20	Severe error.

LINE_STATUS - Query Source and Change Information for a Line in a Data Set**Assignment Statement Syntax**

```
ISREDIT (varname) = LINE_STATUS lptr
```

Return Codes

0	Normal completion.
12	Line number not valid.
20	Severe error.

LINENUM - Query the Line Number of a Labeled Line**Assignment Statement Syntax**

```
ISREDIT (varname) = LINENUM label
```

Return Codes

0	Normal completion.
4	Line 0 specified.

LINENUM - LOCATE

8	Label specified, but not found (variable set to 0).
12	Invalid line number.
20	Severe error.

LOCATE - Locate a Line

Specific Locate Syntax

```
ISREDIT LOCATE lptr
```

Generic Locate Syntax

```
ISREDIT LOCATE [FIRST] {CHANGE } [lptr-range]
                  [LAST ] {COMMAND }
                  [NEXT ] {ERROR   }
                  [PREV ] {EXCLUDED}
                        {LABEL   }
                        {SPECIAL }
                        {INFOLINE}
                        {MSGLINE}
                        {NOTELINE}
```

Return Codes

0	Normal completion.
4	Line not located.
8	Empty member or data set.
20	Severe error.

LRECL - Query the Logical Record Length

Assignment Statement Syntax

```
ISREDIT (varname) = LRECL
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

MACRO - Identify an Edit Macro

Macro Command Syntax

```
ISREDIT MACRO [(var1 [,var2,...])] [PROCESS ]
                                      [NOPROCESS]
```

Return Codes

0	Normal completion.
8	No parameters are permitted for this processing.
12	Syntax error.
20	Severe error.

MACRO_LEVEL - Query the Macro Nesting Level

Assignment Statement Syntax

```
ISREDIT (varname) = MACRO_LEVEL
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

MASKLINE - Set or Query the Mask Line

Assignment Statement Syntax

```
ISREDIT (varname) = MASKLINE
```

```
ISREDIT MASKLINE = data
```

Return Codes

0	Normal completion.
4	Data truncated.
16	Variable data truncated.
20	Severe error.

MEMBER - Query the Current Member Name

Assignment Statement Syntax

```
ISREDIT (varname) = MEMBER
```

Return Codes

0	Normal completion.
12	Invalid command format.
20	Severe error.

MEND - End a Macro in the Batch Environment

Macro Command Syntax

```
ISREDIT MEND
```

Return Codes

0	Normal completion.
20	Severe error.

Note: Only required in the MVS/370 environment.

MODEL - MOVE

MODEL - Copy a Model into the Current Data Set

Macro Command Model Name Syntax

```
ISREDIT MODEL model-name [qualifier] {AFTER } lptr [NOTES ]  
                               {BEFORE}           [NONOTES]
```

Macro Command Class Name Syntax

```
ISREDIT MODEL CLASS class-name
```

Return Codes

0	Normal completion.
12	Invalid line pointer.
20	Severe error.

MOVE - Move a Data Set Member

Macro Command Syntax

```
ISREDIT MOVE member {AFTER } lptr  
                    {BEFORE}  
                    (member)  
                    data set name  
                    data.set.name(member)
```

Return Codes

0	Normal completion.
8	End of data before last record read, or the specified dataset is in use.
12	Invalid line pointer (lptr); member not found or BLDL error.
16	End of data before first record read.
20	Syntax error (invalid name, incomplete range), or I/O error.

NONUMBER - Turn Off Number Mode

Syntax

```
ISREDIT NONUMBER
```

Return Codes

0	Normal completion.
20	Severe error.

NOTES - Set or Query Note Mode

Macro Command Syntax

```
ISREDIT NOTES [ON | OFF ]
```

Assignment Statement Syntax

```
ISREDIT (varname) = NOTES
```

```
ISREDIT NOTES = [ON | OFF]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

NULLS - Set or Query Nulls Mode

Macro Command Syntax

```
ISREDIT NULLS [ON STD]
               [ON ALL]
               [OFF  ]
```

Assignment Statement Syntax

```
ISREDIT (var1,var2) = NULLS
```

```
ISREDIT NULLS = [ON STD]
                 [ON ALL]
                 [OFF  ]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

NUMBER - Set or Query Number Mode

Macro Command Syntax

```
ISREDIT NUMBER [ON ] [STD   ] [DISPLAY]
                [OFF] [COBOL ]
                [STD COBOL]
                [NOSTD]
                [NOCOBOL]
                [NOSTD NOCOBOL]
```

Assignment Statement Syntax

```
ISREDIT (var1,var2) = NUMBER
```

```
ISREDIT NUMBER = [ON ] [STD   ] [DISPLAY]
                  [OFF] [COBOL ]
                  [STD COBOL]
                  [NOSTD]
                  [NOCOBOL]
                  [NOSTD NOCOBOL]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

PACK - PROCESS

PACK - Set or Query Pack Mode

Macro Command Syntax

ISREDIT PACK [ON | OFF]

Assignment Statement Syntax

ISREDIT (varname) = PACK

ISREDIT PACK = [ON | OFF]

Return Codes

0 Normal completion.
20 Severe error.

PASTE — Move or Copy Lines from Clipboard

Macro Command Syntax

ISREDIT PASTE [AFTER] lptr [clipboardname]
[BEFORE] [KEEP]

Return Codes

0 Normal completion.
12 Parameter error. Clipboard empty or does not exist.
20 Severe error.

PRESERVE - Enable Saving of Trailing Blanks

Macro Command Syntax

ISREDIT PRESERVE [ON | OFF]

Assignment Statement Syntax

ISREDIT (varname) = PRESERVE

ISREDIT PRESERVE = [ON | OFF]

Return Codes

0 Normal completion.
6 Record format is not variable.
16 Error setting variable.
20 Severe error.

PROCESS - Process the Panel

Macro Command Syntax

ISREDIT PROCESS [DEST] [RANGE cmd1 [cmd2]]

Return Codes

0	Normal completion.
4	Range expected by macro, but you did not specify it; defaults set.
8	Destination expected by macro, but you did not specify it; defaults set.
12	Both range and destination expected by macro, but you did not specify them; defaults set.
16	You entered incomplete or conflicting line commands.
20	Severe error.

Note: ISPF does not consider a return code of 12 from the PROCESS edit macro command an error and does not terminate a macro that receives a return code of 12 from the PROCESS edit macro.

PROFILE - Set or Query the Current Profile**Macro Command Profile Control Syntax**

```
ISREDIT PROFILE [name] [number]
```

Macro Command Profile Lock Syntax

```
ISREDIT PROFILE {LOCK | UNLOCK}
```

Macro Command Profile Reset Syntax

```
ISREDIT PROFILE RESET
```

Assignment Statement Syntax

```
ISREDIT (var1,var2) = PROFILE
```

Return Codes

0	Normal completion.
20	Severe error.

RANGE_CMD - Query a Command That You Entered**Assignment Statement Syntax**

```
ISREDIT (varname) = RANGE_CMD
```

Return Codes

0	Normal completion.
4	Line command not set.
8	Line command setting not acceptable.
20	Severe error.

RCHANGE - Repeat a Change**Macro Command Syntax**

```
ISREDIT RCHANGE
```

RCHANGE - RECFM

Return Codes

0	Normal completion.
4	String not found.
8	Change error (string-2 longer than string-1 and substitution was not performed on at least one change).
12	Syntax error.
20	Severe error.

RECFM - Query the Record Format

Assignment Statement Syntax

ISREDIT (varname) = RECFM

Return Codes

0	Normal completion.
20	Severe error.

RECOVERY - Set or Query Recovery Mode

Macro Command Syntax

ISREDIT RECOVERY [ON [SUSP]]
 [OFF [WARN]]
 [OFF NOWARN]

Assignment Statement Syntax

ISREDIT (var1, var2) = RECOVERY

ISREDIT RECOVERY = [ON [SUSP]]
 [OFF [WARN]]
 [OFF NOWARN]

Return Codes

0	Normal completion.
20	Severe error.

RENUM - Renumber Data Set Lines

Macro Command Syntax

ISREDIT RENUM [ON] [STD] [DISPLAY]
 [OFF] [COBOL]
 [STD COBOL]

Return Codes

0	Normal completion.
20	Severe error.

REPLACE - Replace a Data Set or Data Set Member

Macro Command Syntax

```
ISREDIT REPLACE member lptr-range
ISREDIT REPLACE (member) lptr-range
ISREDIT REPLACE dataset lptr-range
ISREDIT REPLACE dataset(member) lptr-range
```

Return Codes

```
0      Normal completion.
8      Member in use.
12     Invalid line pointer; member not found or BLDL error.
20     Syntax error (invalid name, incomplete line pointer value), or I/O error.
```

RESET - Reset the Data Display

Macro Command Syntax

```
ISREDIT RESET [CHANGE ] [lptr-range]
               [COMMAND ]
               [ERROR   ]
               [EXCLUDED]
               [LABEL   ]
               [SPECIAL ]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

RFIND - Repeat Find

Macro Command Syntax

```
ISREDIT RFIND
```

Return Codes

```
0      Normal completion.
4      String not found.
12     Syntax error.
20     Severe error (string not defined).
```

RIGHT - Scroll Right

Macro Command Syntax

```
ISREDIT RIGHT amt
```

Return Codes

```
0      Normal completion.
4      No visible lines.
8      No data to display.
```

RIGHT - RMACRO

12	Amount not specified.
20	Severe error.

RMACRO - Set or Query the Recovery Macro

Macro Command Syntax

```
ISREDIT RMACRO {name | NONE}
```

Assignment Statement Syntax

```
ISREDIT (varname) = RMACRO
```

```
ISREDIT RMACRO = {name | NONE}
```

Return Codes

0	Normal completion.
12	Invalid name specified.
20	Severe error.

SAVE - Save the Current Data

Macro Command Syntax

```
ISREDIT SAVE
```

Return Codes

0	Normal completion.
4	New member saved.
12	Data not saved; not enough PDS space or directory space.
20	Severe error.

SAVE_LENGTH - Set or Query Length for Variable Length Data

Macro Command Syntax

```
ISREDIT (variable) = SAVE_LENGTH .lptr  
ISREDIT SAVE_LENGTH .lptr = value
```

Return Codes

0	Normal completion.
4	Value supplied on set call was out of range. If the supplied length was too great, it is adjusted to equal the maximum record length. Otherwise, the length is adjusted to the length of the nonblank data portion of the record.
6	Record format is not variable. Any value of an assigned request is ignored.
16	Error setting variable.
20	Severe error.

SCAN - Set Command Scan Mode

Macro Command Syntax

```
ISREDIT SCAN [ON | OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = SCAN
ISREDIT SCAN = [ON | OFF]
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

SEEK - Seek a Data String, Positioning the Cursor

Macro Command Syntax

```
ISREDIT SEEK string [label-range] [NEXT ] [CHARS ] [X ] [col-1 [col-2]]
                                     [ALL ] [PREFIX] [NX]
                                     [FIRST] [SUFFIX]
                                     [LAST ] [WORD ]
                                     [PREV ]
```

Return Codes

```
0      Normal completion.
4      String not found.
12     Syntax error.
20     Severe error.
```

SEEK_COUNTS - Query Seek Counts

Assignment Statement Syntax

```
ISREDIT (var1,var2) = SEEK_COUNTS
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

SESSION — Identify Type of Session

Assignment Statement Syntax

```
ISREDIT (var1,var2) = SESSION
```

Return Codes

```
0      Normal completion.
20     Severe error.
```

SETUNDO - SHIFT (

SETUNDO - Set UNDO Mode

Macro Command Syntax

```
ISREDIT SETUNDO [STORAGE]
                  [RECOVER]
                  [ON]
                  [OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = SETUNDO

ISREDIT SETUNDO = [STORAGE]
                  [RECOVER]
                  [ON]
                  [OFF]
```

Return Codes

- 0 Successful completion. SETUNDO was turned on or off, or status remains unchanged because UNDO was already on or off.
- 20 Severe error. Probably a parameter error (something other than STG, REC, or OFF was specified).

SHIFT (- Shift Columns Left

Macro Command Syntax

```
ISREDIT SHIFT ( lptr [n | 2]
```

Return Codes

- 0 Normal completion.
- 12 Invalid line number.
- 20 Severe error.

SHIFT) - Shift Columns Right

Macro Command Syntax

```
ISREDIT SHIFT ) lptr [n | 2]
```

Return Codes

- 0 Normal completion.
- 12 Invalid line number.
- 20 Severe error.

SHIFT < - Shift Data Left

Macro Command Syntax

```
ISREDIT SHIFT < lptr [n | 2]
```

Return Codes

0	Normal completion.
12	Invalid line number.
20	Severe error.

SHIFT > - Shift Data Right**Macro Command Syntax**

```
ISREDIT SHIFT > lptr [n | 2]
```

Return Codes

0	Normal completion.
12	Invalid line number.
20	Severe error.

SORT - Sort Data**Macro Command Syntax**

```
ISREDIT SORT [label-range] [X ] [sort-field1 ... sort-field5]
[NX]
```

Return Codes

0	Normal completion.
4	Lines were already in sort order.
8	No records to sort.
16	Not enough storage to perform sort.
20	Severe error.

STATS - Set or Query Stats Mode**Macro Command Syntax**

```
ISREDIT STATS [ON | OFF]
```

Assignment Statement Syntax

```
ISREDIT (varname) = STATS
```

```
ISREDIT STATS = [ON | OFF]
```

Return Codes

0	Normal completion.
20	Severe error.

SUBMIT - Submit Data for Batch Processing**Macro Command Syntax**

```
ISREDIT SUBMIT [lptr-range]
```

STATS - SUBMIT

Return Codes

0	Normal completion.
20	Severe error (submit failed).

TABS - Set or Query Tabs Mode

Macro Command Syntax

```
ISREDIT TABS [ON] [STD]
              [ALL]
              [tab-character]
              [OFF]
```

Assignment Statement Syntax

```
ISREDIT (var1,var2) = TABS

ISREDIT TABS = [ON] [STD]
               [ALL]
               [tab-character]
               [OFF]
```

Return Codes

0	Normal completion.
20	Severe error.

TABSLINE - Set or Query Tabs Line

Assignment Statement Syntax

```
ISREDIT (varname) = TABSLINE

ISREDIT TABSLINE = data
```

Return Codes

0	Normal completion.
4	Data truncated.
8	Invalid data detected and ignored.
20	Severe error (invalid input).

TENTER - Set Up Panel for Text Entry

Macro Command Syntax

```
ISREDIT TENTER lptr [numlines]
```

Return Codes

0	Normal completion.
12	Invalid line number.
20	Severe error.

TFLOW - Text Flow a Paragraph

Macro Command Syntax

ISREDIT TFLOW lptr [col]

Return Codes

0	Normal completion.
12	Invalid line number.
20	Severe error.

TSPLIT - Text Split a Line

Macro Command Syntax

ISREDIT TSPLIT [lptr col]

Return Codes

0	Normal completion.
12	Invalid line number.
20	Severe error.

UNNUMBER - Remove Sequence Numbers

Macro Command Syntax

ISREDIT UNNUMBER

Return Codes

0	Normal completion.
12	Number mode not on.
20	Severe error.

UP - Scroll Up

Macro Command Syntax

ISREDIT UP amt

Return Codes

0	Normal completion.
2	No more data UP.
4	No visible lines.
8	No data to display.
12	Amount not specified.
20	Severe error.

USER_STATE - Save or Restore User State

Assignment Statement Syntax

ISREDIT (varname) = USER_STATE

ISREDIT USER_STATE = (varname)

Return Codes

0 Normal completion.
20 Severe error.

VERSION - Set or Query Version Number

Macro Command Syntax

ISREDIT VERSION num

Assignment Statement Syntax

ISREDIT (varname) = VERSION

ISREDIT VERSION = num

Return Codes

0 Normal completion.
4 Stats mode is off, the command is ignored.
12 Invalid value specified (the version must be 1 to 99).
20 Severe error.

VIEW - View from within an Edit Session

Macro Command Syntax

ISREDIT VIEW member

Return Codes

0 Normal completion
12 Your error (invalid member name, recovery pending)
20 Severe error.

VOLUME — Query Volume Information

Assignment Statement Syntax

ISREDIT (var1,var2) = VOLUME

Return Codes

0 Normal completion.
4 The data set is a multivolume data set and the shared pool variable ZEDMVOL is set to contain all the volume serial numbers of the data set. ZEDMVOL has the length of the number of volumes times six.

20 Severe error.

XSTATUS - Set or Query Exclude Status of a Line

Assignment Statement Syntax

```
ISREDIT (varname) = XSTATUS lptr
```

```
ISREDIT XSTATUS lptr = X | NX
```

Return Codes

- 0 Normal completion.
- 8 An attempt to set a line status to NX could not be performed. The line has a pending line command on it. For example, if an excluded line contains an M line command in the line command area, then the MOVE/COPY IS PENDING message is displayed and the lines cannot be shown. The reset command can be used to remove your line commands from the line command area.
- 12 Line number is not an existing line.
- 20 Severe error.

VERSION - XSTATUS

Chapter 4. SCLM Services and Macros

This chapter contains the syntax conventions and return codes for the SCLM services as well as the syntax conventions for the SCLM macros. For a complete description of the services and macros see the *ISPF Software Configuration and Library Manager (SCLM) Reference*

SCLM Services

ACCTINFO - Retrieve Accounting Information

Command Invocation Format

```
FLMCMO ACCTINFO,project
           ,[prj_def]
           ,group
           ,type
           ,member
           ,[user_info_table]
           ,[include_table]
           ,[change_code_table]
           ,[ada_cu_table]
           ,[SEARCH|FORWARD|MATCH]
           ,[dd_msgs]
```

Call Invocation Format

```
lastrc := FLMLNK('ACCTINFO ',sclm_id,
                ,group
                ,type
                ,member
                ,user_info_table
                ,include_table
                ,change_code_table
                ,ada_cu_table
                ,SEARCH|FORWARD|MATCH
                ,msg_array);
```

Return Codes

- 0 Normal completion. An account record exactly matching the specified criteria was found and the information was stored successfully.
- 8 Error completion. No account record was found for the specified member.
 - If FORWARD was specified then there are no accounting records for the group which match or follow the specified type and member name.
 - If MATCH was specified then there is not an account record with the specified group, type and member name.
 - If SEARCH was specified then there are no matching account records found when searching up the hierarchy starting from the specified group.
- 12 Error completion. Refer to the messages for more information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. An invalid parameter list was passed to the requested service.
- 34 Severe error condition. An invalid service was requested.

- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

AUTHCODE - Set or Retrieve an AUTHCODE

Command Invocation Format

```
FLMCMO AUTHCODE,project
                ,[prj_def]
                ,group
                ,type
                ,member
                ,[from_authcode]
                ,[to_authcode]
                ,[C|U]
                ,[dd_authmsgs]
                ,[dd_authrept]
```

Call Invocation Format

```
lastrc := FLMLNK('AUTHCODE',sclm_id,
                ,group
                ,type
                ,member
                ,from_authcode
                ,to_authcode
                ,C|U
                ,dd_authmsgs
                ,dd_authrept);
```

Return Codes

- 0 Normal completion. Authcode changed or reported successfully.
- 2 Normal completion. Authcode not changed. One of the following occurred:
- To_authcode = existing authcode (no change needed)
 - From_authcode requested does not equal existing authcode (no change wanted)
 - Member is not editable.
- 4 Warning condition. Segment exists at a lower level with an authcode not equal to the "to_authcode" which could overlay the current segment.
- 8 Error condition. Invalid type, member, or mode parameter. See the dd_authmsgs for details.
- 12 Severe error condition. Accounting record not found or severe error.
- 16 Severe error condition. One of the following occurred:
- Not authorized to update "to_authcode", access_key mismatch, or not authorized to update data set.
 - Verification failed.
 - Error updating accounting record.
 - Invalid group.
- SCLM might not produce messages because there was an error invoking the AUTHCODE module.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is not valid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
- You requested an invalid service.

- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

BUILD - Build a Member

Command Invocation Format

```
FLMCMD BUILD,project
           ,[prj_def]
           ,group
           ,type
           ,member
           ,[userid]
           ,[E|L|M|S]
           ,[C|F|R|U]
           ,[Y|N]
           ,[Y|N]
           ,[prefix_userid]
           ,[dd_bldmsgs]
           ,[dd_bldrept]
           ,[dd_bldlist]
           ,[dd_bldexit]
```

Call Invocation Format

```
lastrc := FLMLNK('BUILD ' ,sclm_id
                 ,group
                 ,type
                 ,member
                 ,{userid|' '}
                 ,{E|L|N|S}
                 ,{C|F|R|U}
                 ,{Y|N}
                 ,{Y|N}
                 ,{prefix_userid | ' '}
                 ,dd_bldmsgs
                 ,dd_bldrept
                 ,dd_bldlist
                 ,dd_bldexit);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 12 Severe error condition. Messages are not produced. Error invoking the Build module.
- 16 Severe error condition. Messages are not produced. Unable to retrieve SCLM ID information.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced for one of the following reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DBACCT - Retrieve Accounting Records for a Member

Command Invocation Format

You cannot use command procedures to call this service.

Call Invocation Format

```
lastrc := FLMLNK('DBACCT ',sclm_id
                ,group
                ,type
                ,member
                ,found_group
                ,$acct_info
                ,$list_info
                ,$msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. The accounting record could not be found.
- 8 Error condition. See the \$msg_array parameter above for more details.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced for one of the following reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DBUTIL - Generate a Tailored Data Set and Report

Command Invocation Format

```
FLMCMDBUTIL,project
    ,[prj_def]
    ,[acct_group1|*],[acct_group2]
    ,[acct_group3],[acct_group4]
    ,[acct_group5],[acct_group6]
    ,[acct_type|*],[acct_member|*]
    ,[authcode|*],[change_code|*]
    ,[change_group|*],[change_userid|*]
    ,[language|*],[YES|NO]
    ,[ACCT|BMAP|*]
    ,[IN|OUT|*]
    ,[arch_group],[arch_type],[arch_member]
    ,[EXTENDED|NORMAL|SUBUNIT]
    ,[YES|NO]
    ,[YES|NO]
    ,[report_name],[dd_msgs]
    ,[dd_rept],[dd_tailor]
    ,[report_line]
```

Call Invocation Format

You cannot use call procedures to start this service.

Return Codes

- 0 Normal completion.
- 4 Warning condition.

- 8 Error condition.
 >8 Severe error condition. Messages are not produced.

DELETE - Delete Database Components

Command Invocation Format

```
FLMCMD DELETE,project
           ,[prj_def]
           ,group
           ,type
           ,member
           ,access_key
           ,[ACCT|BMAP|TEXT]
```

Call Invocation Format

```
lastrc := FLMLNK('DELETE ' ,sclm_id
                ,group
                ,type
                ,member
                ,access_key
                ,{ACCT|BMAP|TEXT}
                , $msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. The member, accounting record, and/or build map were not found.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced for one of the following reasons:
- Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DELGROUP - Delete Group Database Components

Command Invocation Format

```
FLMCMD DELGROUP,project
           ,[prj_def]
           ,{group|*}
           ,{type|*}
           ,{member|*}
           ,{ACCT|BMAP|TEXT|OUTPUT}
           ,[EXECUTE|REPORT]
           ,[dd_list]
           ,[dd_msgs]
           ,[dd_rept]
           ,[dd_exit]
```

DELGROUP

Call Invocation Format

```
lastrc := FLMLNK('DELGROUP',sclm_id
                ,{group|*}
                ,{type|*}
                ,{member|*}
                ,{ACCT|BMAP|TEXT|OUTPUT}
                ,{EXECUTE|REPORT}
                ,dd_list
                ,dd_msgs
                ,dd_rept
                ,dd_exit);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 12 Severe error condition. SCLM does not produce messages because there was an error invoking the DELGROUP module.
- 16 Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module (for future use).
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DSALLOC—Allocate Data Sets for Group/Type

Command Invocation Format

```
FLMCMD DSALLOC,project
                ,[prj_def]
                ,first_group
                ,[A|P]
                ,total_groups
                ,type
                ,ddname
```

Call Invocation Format

```
lastrc := FLMLNK('DSALLOC ',sclm_id
                ,first_group
                ,{A|P}
                ,total_groups
                ,type
                ,ddname
                , $msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. The \$msg_array parameter contains the warning

message associated with this condition. A warning occurs if the number of data sets allocated to ddname is less than the number requested in the total_groups parameter.

- 8 Error condition. The \$msg_array parameter contains the error message associated with this condition.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID (sclm_id parameter) is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services were not initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

EDIT— Edit a Member of a Controlled Library

Command Invocation Format

```
FLMCMD EDIT,project
      ,(prj_def)
      ,group1
      ,(group2)
      ,(group3)
      ,(group4)
      ,type
      ,member
      ,(Y|N)
      ,(imac)
      (prof),
      ,(Y|N)
      ,(Y|N)
      ,(Y|N)
      ,(Y|N)
      ,(authcode)
      ,(chgcode)
      ,(volser)
      ,(dd_editmsgs)
```

Call Invocation Format

```

lastrc := FLMLNK('EDIT', sclm_id
                ,group1
                ,(group2)
                ,(group3)
                ,(group4)
                ,type
                ,member
                ,(Y|N)
                ,(imac)
                ,(prof)
                ,(Y|N)
                ,(Y|N)
                ,(Y|N)
                ,(Y|N)
                ,(authcode)
                ,(chgcode)
                ,(volser)
                ,(dd_editmsgs));

```

Return Codes

Possible return codes are:

- | | |
|-----------|---|
| 0 | Normal completion. |
| 8 | Error condition. See the dd_editmsgs for details. |
| 12 | Severe error condition. SCLM does not produce messages because there was an error invoking the edit module. |
| 20 | Severe error condition. SCLM does not produce messages because the SCLM ID is invalid. |
| 24 | Severe error condition. SCLM does not produce messages because SCLM services have not been initialized. See the <i>SCLM Reference</i> for information on initializing an SCLM services session. |
| 32 | Severe error condition. SCLM does not produce messages for one of the following reasons: <ul style="list-style-type: none"> • You requested an invalid service. • You supplied an invalid parameter list for the requested service. • The version of FLMLNK subroutine does not match the version of the SCLM services module. |

END - End an SCLM Services Session

Command Invocation Format

You cannot use command procedures to call this service.

Call Invocation Format

```
lastrc := FLMLNK('END      ',appl_id
                ,msg_line);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. Unable to free an SCLM ID associated with the application ID.
- 8 Error condition.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

EXPORT - Extract SCLM Accounting Information for a Group

Command Invocation Format

```
FLMCMDB EXPORT,project
           ,[prj_def]
           ,group
           ,[Y|N]
           ,[dd_msgs]
           ,[dd_rept]
```

Call Invocation Format

```
lastrc := FLMLNK('EXPORT ',sclm_id
                ,group
                ,{Y|N}
                ,dd_msgs
                ,dd_rept);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 12 Severe error condition. SCLM does not produce messages because there was an error invoking the IMPORT module.
- 16 Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.
- 20 Severe error condition. SCLM does not produced messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

EXPORT

- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module (for future use).
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

FREE - Free Database from its Association with SCLM ID

Command Invocation Format

You cannot use command procedures to call this service.

Call Invocation Format

```
lastrc := FLMLNK('FREE      ',sclm_id  
                ,msg_line);
```

Return Codes

- 0 Normal completion.
- 8 Error condition.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

IMPORT - Import SCLM Accounting Information to Current Project

Command Invocation Format

```
FLMCMD IMPORT,project  
        ,[prj_def]  
        ,group  
        ,[authcode|' '  
        ,[change_code|' '  
        ,[userid|' '  
        ,[C|U|R]  
        ,[dd_msgs]  
        ,[dd_rept]
```

Call Invocation Format

```
lastrc := FLMLNK('IMPORT  ',sclm_id  
                ,group  
                ,{authcode}  
                ,{change_code}  
                ,{userid}  
                ,{C|U|R}  
                ,dd_msgs  
                ,dd_rept);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 12 Severe error condition. SCLM does not produce messages because there was an error invoking the IMPORT module.
- 16 Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.
- 20 Severe error condition. SCLM does not produced messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module (for future use).
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

INIT - Generate an SCLM ID for a Database**Command Invocation Format**

You cannot use command procedures to call this service.

Call Invocation Format

```
l astrc := FLMLNK('INIT      ',appl_id
                  ,project
                  ,prj_def
                  ,sclm_id
                  ,msg_line);
```

Return Codes

- 0 Normal completion.
- 8 Error condition.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

LOCK - Lock a Member or Assign an Access Key**Command Invocation Format**

```
FLMCMD LOCK,project
          ,[prj_def]
          ,group
          ,type
```

LOCK

```
,member  
,[authcode]  
,[access_key]  
,[userid]
```

Call Invocation Format

```
lastrc := FLMLNK('LOCK ' ,sclm_id  
                ,group  
                ,type  
                ,member  
                ,{authcode|' '  
                ,{access_key|' '  
                ,{userid|' '  
                ,found_group  
                ,max_prom_group  
                , $acct_info  
                , $list_info  
                , $msg_array);
```

Return Codes

- 0 Normal completion.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

MIGRATE - Create Accounting Information for Selected Members

Command Invocation Format

```
FLMCMD MIGRATE,project  
                ,[prj_def]  
                ,group,type,member  
                ,[authcode]  
                ,[language]  
                ,[change_code]  
                ,[C|U|F]  
                ,[dd_migmsgs]  
                ,[dd_miglist]  
                ,[dd_migrept]  
                ,[date]  
                ,[time]
```

Call Invocation Format

```
lastrc:=FLMLNK('MIGRATE ' ,sclm_id  
                ,group  
                ,type  
                ,member  
                ,authcode  
                ,language  
                ,change_code
```

```
,C|U|F
,[dd_migmsgs]
,[dd_miglist]
,[dd_migrept]
,[date]
,[time]);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. See the SCLM messages for more information.
- 8 Error condition. See the SCLM messages for more information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. SCLM does not produce messages for one of the following reasons:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.

NEXTGRP - Find the Next Group in a Hierarchy

Command Invocation Format

```
FLMCMO NEXTGRP,project
                ,[prj_def]
                ,group
                ,[dd_msgs]
```

Call Invocation Format

```
lastrc := FLMLNK('NEXTGRP ',sclm_id
                ,group
                ,dd_msgs);
```

Return Codes

- 0 Normal completion. NEXTGRP completed successfully. Variables are set.
- 4 Warning condition. The group is already the top group. No variables are set.
- 8 Error condition. Invalid project, prj_def, or group name.
- 12 Severe error condition. SCLM might not produce messages because there was an error invoking the NEXTGRP module. For certain conditions messages are available.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.

PARSE - Parse a Member for Statistical and Dependency Information

Command Invocation Format

You cannot use command procedures to call this service.

PARSE

Call Invocation Format

```
lastrc := FLMLNK('PARSE ' ,sclm_id
                ,group
                ,type
                ,member
                ,language
                ,{Y|N}
                ,ddname
                , $stats_info
                , $list_info
                , $msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition. A parser error occurred.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

PROMOTE - Promote a Member from One Library to Another

Command Invocation Format

```
FLMCMDB PROMOTE,project
                ,[prj_def]
                ,group
                ,type
                ,member
                ,[userid]
                ,{E|M|S}
                ,{C|U|R}
                ,[dd_prommsgs]
                ,[dd_promrept]
                ,[dd_promexit]
                ,[dd_copyerr]
```

Call Invocation Format

```
lastrc := FLMLNK('PROMOTE ' ,sclm_id
                ,group,type,member
                ,{userid|' '})
                ,{E|N|S}
                ,{C|U|R}
                ,dd_prommsgs,dd_promrept
                ,dd_promexit,dd_copyerr);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.

- 12 Severe error condition. Messages are not produced. Error invoking the Promote module.
- 16 Severe error condition. Messages are not produced. Unable to retrieve SCLM ID information.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

RPTARCH - Generate an SCLM Architecture Report

Command Invocation Format

```
FLMCMD RPTARCH,project,[prj_def]
           ,group
           ,type
           ,member
           ,[HL|LEC|CC|GEN|TOP SOURCE|NONE]
           ,dd_rptmsgs
           ,dd_rptrept
```

Call Invocation Format

You cannot use call procedures to start this service.

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 16 Error condition. Unable to retrieve the SCLM table.

SAVE - Lock, Parse, and Store a Member

Command Invocation Format

```
FLMCMD SAVE,project,[prj_def]
           ,group,type,member
           ,[authcode],[access_key]
           ,[userid],[language]
           ,[Y|N]
           ,[ddname],[C|U]
           ,[C|U]
           ,[change_code]
```

Call Invocation Format

```
lastrc := FLMLNK('SAVE ' ,sclm_id
                ,group,type,member
                ,authcode,access_key
                ,{userid|' '},language
                ,{Y|N}
                ,ddname
                ,{C|U}
                ,{C|U}
                ,{Y|N}
```

SAVE

```
, $list_info  
, max_prom_group  
, $msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

START - Generate an Application ID for a Service Session

Command Invocation Format

You cannot use command procedures to call this service.

Call Invocation Format

```
lastrc := FLMLNK('START ' ,appl_id);
```

Return Codes

- 0 Normal completion.
- 12 Severe error condition. The maximum application ID limit was exceeded.
- 16 Severe error condition. An invalid version of the SCLM table was loaded.
- 20 Severe error condition. An invalid version of the NLS table was loaded.
- 24 Severe error condition. Unable to load the SCLM table.
- 28 Severe error condition. Unable to load the NLS table or the SCLM I/O load module.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

STORE - Store Member Information in an Accounting Record

Command Invocation Format

You cannot use command procedures to call this service.

Call Invocation Format

```
lastrc := FLMLNK('STORE ' ,sclm_id  
 ,group,type,member  
 ,access_key
```

```
,language
,{userid|' '}
,{C|U}
,{Y|N}
,$stats_info,$list_info
,$msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

UNLOCK - Unlock a Member in a Development Library

Command Invocation Format

```
FLMCMDB UNLOCK,project
      ,[prj_def]
      ,group
      ,type
      ,member
      ,[access_key]
```

Call Invocation Format

```
lastrc := FLMLNK('UNLOCK ',sclm_id
      ,group
      ,type
      ,member
      ,{access_key|' '}
      ,$msg_array);
```

Return Codes

- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.
- 20 Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24 Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32 Severe error condition. Messages are not produced. One of the following is true:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34 Severe error condition. An invalid service was requested.

- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

VERDEL—Delete Version Information

Command Invocation Format

```
FLMCMD VERDEL,project
           ,[prj_def]
           ,group
           ,type
           ,member
           ,date
           ,time
           ,[dd_msgs]
           ,[longdate]
```

Call Invocation Format

```
lastrc := FLMLNK('VERDEL ',sclm_id,
                 ,group
                 ,type
                 ,member
                 ,date
                 ,time
                 , $msg_array
                 ,[longdate]);
```

Return Codes

- 0 Normal completion. The audit and version information were deleted.
- 8 Error completion. No audit and version information was deleted. No audit record was found that matches the specified criteria.
- 12 Error completion. Refer to the messages for more information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. An invalid parameter list was passed to the requested service.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

VERINFO - Retrieve Version Information

Command Invocation Format

```
FLMCMD VERINFO,project
           ,[prj_def]
           ,group
           ,type
           ,member
           ,[date]
           ,[time]
           ,[user_info_table]
           ,[include_table]
           ,[change_code_table]
           ,[ada_cu_table]
           ,[FORWARD|BACKWARD|MATCH]
           ,[dd_msgs]
           ,[longdate]
```

Call Invocation Format

```
lastrc := FLMLNK('VERINFO ',sclm_id,
                ,group
                ,type
                ,member
                ,date
                ,time
                ,user_info_table
                ,include_table
                ,change_code_table
                ,ada_cu_table
                ,FORWARD|BACKWARD|MATCH
                ,$msg_array
                ,[longdate]);
```

Return Codes

- 0 Normal completion. An audit record exactly matching the specified criteria was found and the information was stored successfully.
- 8 Error completion. No audit record was found for the specified member.
- If FORWARD was specified then there are no audit records for the group which match or follow the specified type, member, date and time.
 - If BACKWARD was specified then there are no audit records for the group which match or precede the specified type, member, date and time.
 - If MATCH was specified then there is not an audit record with the specified group, type and member name.
- 12 Error completion. Refer to the messages for more information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. An invalid parameter list was passed to the requested service.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

VERRECOV - Recover A Version**Command Invocation Format**

```
FLMCMD VERRECOV,project
                ,[prj_def]
                ,group
                ,type
                ,member
                ,date
                ,time
                ,[to_dataset]
                ,[to_group]
                ,[to_type]
                ,[authcode]
                ,[dd_msgs]
                ,[longdate]
```

Call Invocation Format

```
lastrc := FLMLNK('VERRECOV',sclm_id,
                ,group
                ,type
                ,member
```

VERRECOV Service

```
,date  
,time  
,to_dataset  
,to_group  
,to_type  
,authcode  
,$msg_array  
,[longdate]);
```

Return Codes

- 0 Normal completion. The audit and version information were recovered.
- 8 Error completion. No audit and version information was recovered. No audit record was found that matches the specified criteria.
- 10 Error completion. No audit and version information was recovered. The member could not be locked with the specified authorization code.
- 12 Error completion. Refer to the messages for more information.
- 20 Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24 Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32 Severe error condition. An invalid parameter list was passed to the requested service.
- 34 Severe error condition. An invalid service was requested.
- 36 Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

SCLM Macros

FLMABEG - Define the Project Name of the Project Definition

Macro Format

```
name FLMABEG
```

FLMAEND - Last Macro in the Project Definition

Macro Format

```
FLMAEND
```

FLMAGRP - Define a Group of Authorization Codes

Macro Format

```
name FLMAGRP AC=(code1,code2,...)
```

FLMALLOC - Define Each DDname in the DDname Substitution List for a Translator

Macro Format

```
FLMALLOC IOTYPE={A|I|L|N|O|P|S|U|W}  
[,BLKSIZE=block_size]  
[,CATLG=N|Y]  
[,DDNAME=ddname]  
[,DINIT=N|Y]  
[,DIRBLKS=directory_blocks]  
[,DISP=OLD|SHR|MOD|NEW]  
[,DFLTMEM=default_member]  
[,DFLTYP=default_type]
```

```
[,KEYREF=keyword_reference]
[,LANG=language]
[,MALLOC=N|Y]
[,ALLCDEL=N|Y]
[,LRECL=record_length]
[,MEMBER=member_name]
[,NOSAVRC=no_save_rc]
[,PRINT=N|Y|I]
[,RECFM=record_format]
[,RECNM=number_of_records]
[,INCLS=include_set_name]
```

FLMALTC - Specify Alternate Control Information

Macro Format

```
name FLMALTC
  ACCT=primary_accounting_data_set
  [,ACCT2=secondary_accounting_data_set]
  [,DSNAME=dataset_name]
  [,EXPACCT=export_account_data_set]
  [,VERS=primary_audit_control_data_set]
  [,VERS2=secondary_audit_control_data_set]
  [,VERPDS=version_pds_name]
```

FLMATVER - Enable the Audit and Version Utility

Macro Format

```
FLMATVER
  GROUP=group|*
  ,TYPE=type|*
  ,SEQNUM=STANDARD|STD|COBOL|NONE
  [,VERSION=YES|NO]
  [,VERCOUNT=number_to_retain]
```

FLMCMLPB - Define a Set of Data Sets for a Language Containing Project Compool Dependencies

Macro Format

```
[language] FLMCMLPB dataset_name
```

FLMCNTRL - Specify Project-Specific Control Options

Macro Format

```
FLMCNTRL    [ACCT=primary_account_data_set|project.ACCOUNT.FILE]

  [,ACCT2=secondary_account_data_set]

  [,EXPACCT=export_account_data_set]

  [,VERS=primary_audit_control_data_set]

  [,VERS2=secondary_audit_control_data_set]

  [,VSAMRLS=NO|YES]

  [,VERPDS=version_pds_name]

  [,VERCOUNT=number_to_retain]

  [,DSNAME=dataset_name_pattern]
```

FLMCNTRL

[,DASDUNIT=DASD_unit_name|SYSALLDA]
[,VIOUNIT=VIO_unit_name|VIO]
[,MAXLINE=max_line_count|60]
[,MAXVIO=max_vio_count|5000]
[,OPTOVER=N|Y]
[,VERCC=change_code_routine]
[,VERCCDS=change_code_dataset]
[,VERCCCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,VERCCOP=change_code_options]
[,CCVFY=initial_change_code_exit_routine]
[,CCVFYDS=initial_change_code_exit_dataset]
[,CCVFYCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,CCVFYOP=initial_change_code_exit_options]
[,CCSAVE=save_change_code_exit_routine]
[,CCSAVDS=save_change_code_exit_dataset]
[,CCSAVCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,CCSAVOP=save_change_code_exit_options]
[,AVDVFY=verify_audit_version_delete_exit_routine]
[,AVDVFYDS=verify_audit_version_delete_exit_dataset]
[,AVDVFYCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,AVDVFYOP=verify_audit_version_delete_exit_options]
[,AVDNTF=notify_audit_version_delete_exit_routine]
[,AVDNTFDS=notify_audit_version_delete_exit_dataset]
[,AVDNTFCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,AVDNTFOP=notify_audit_version_delete_exit_options]
[,BLDINIT=build_initial_user_exit_routine]
[,BLDINIDS=build_initial_user_exit_dataset]
[,BLDINICM=LINK|ATTACH|TSOLNK|ISPLNK]
[,BLDINIOP=build_initial_user_exit_options]
[,BLDNTF=build_notify_user_exit_routine]
[,BLDNTFDS=build_notify_user_exit_dataset]
[,BLDNTFCM=LINK|ATTACH|TSOLNK|ISPLNK]
[,BLDNTFOP=build_notify_user_exit_options]


```
[,PRMINIT=promote_initial_user_exit_routine]
    [,PRMINIDS=promote_initial_user_exit_dataset]
    [,PRMINICM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,PRMINIOP=promote_initial_user_exit_options]
[,PRMVFY=promote_verify_user_exit_routine]
    [,PRMVFYDS=promote_verify_user_exit_dataset]
    [,PRMVFYCM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,PRMVFYOP=promote_verify_user_exit_options]
[,PRMCPY=promote_copy_user_exit_routine]
    [,PRMCPYDS=promote_copy_user_exit_dataset]
    [,PRMCPYCM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,PRMCPYOP=promote_copy_user_exit_options]
    [,PRMPURGE=promote_purge_user_exit_routine]
    [,PRMPRGDS=promote_purge_user_exit_dataset]
    [,PRMPRGCM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,PRMPRGOP=promote_purge_user_exit_options]
[,DELINIT=initial_delete_exit_routine]
    [,DELINIDS=initial_delete_exit_dataset]
    [,DELINICM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,DELINIOP=initial_delete_exit_options]
    [,DELVFY=verify_delete_exit_routine]
    [,DELVFYDS=verify_delete_exit_dataset]
    [,DELVFYCM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,DELVFYOP=verify_delete_exit_options]

[,DELNTF=notify_delete_exit_routine]
    [,DELNTFDS=notify_delete_exit_dataset]
    [,DELNTFCM=LINK|ATTACH|TSOLNK|ISPLNK]
    [,DELNTFOP=notify_delete_exit_options]
```

FLMCPYLB - Identify Additional Data Sets to Be Concatenated to a DDname

Macro Format

```
FLMCPYLB dataset_name|NULLFILE
```

FLMCPYLB - FLMINCLS

FLMGROUP - Define One Group in the Project Definition

Macro Format

```
name FLMGROUP
  [AC=(code1,code2,...)]
  [,ALTC=group_control_options]
  [,KEY=N|Y]
  [,PROMOTE=next_group]
```

FLMINCLS - Associate Include-Sets with Types in the Project Hierarchy

Macro Format

```
name FLMINCLS
  [SAMEAS=flmincls_name_ | Types=(list_of_types)]
  [CROSLANG=Y|N]
```

FLMLANGL - Define a Language to SCLM

Macro Format

```
FLMLANGL LANG=language
  [,ALCSYSLIB=N|Y]
  [,ARCH=N|Y]
  [,BUFSIZE=buffer_size|100]
  [,CANEDIT=Y|N]
  [,CHKSYSLB=PARSE|BUILD|IGNORE]
  [,COMPOOL=N|Y]
  [,DEPPRC=Y|N]
  [,DFLTRCF=default_CREF_reference]
  [,DFLTRSF=default_source_reference]
  [,SCOPE=LIMITED|NORMAL|SUBUNIT|EXTENDED]
  [,VERSION=language_version]
  [,MBRLMT=0]
```

FLMSYSLB - Define a Set of Data Sets for a Language Containing Project Macros or Included Members

Macro Format

```
[language] FLMSYSLB dataset_name
  [,INCLS=include_set_name]
```

FLMTCOND - Select Build Translators Based on Group and Return Codes

Macro Format

```
FLMTCOND
  [ GROUP=group_list|NOTGROUP=group_list]
  [,WHEN=relations_list]
  [,ACTION=RUN|SKIP]
```

FLMTOPTS - Select the Options Based on Group

Macro Format

```
FLMTOPTS OPTIONS=options_list
  [,GROUP=group_list|NOTGROUP=group_list]
  [,ACTION=APPEND|REPLACE]
```

FLMTRNSL - Define Once for Each Translator to Be Invoked for a Language

Macro Format

```
[translator label] FLMTRNSL CALLNAM='call_name'
[,FUNCTN=PARSE|VERIFY|BUILD|COPY|PURGE]
,COMPILE=translator_name
[,DSNAME=translator_dataset_name]
[,GOODRC=good_return_code|0]
[,NOSVEXT=no_save_external_rc|0]
[,OPTFLAG=N|Y]
[,OPTIONS=option_list]
[,PARMKWD=parameter_keyword]
[,PDSDATA=Y|N]
[,PORDER=0|1|2|3]
[,VERSION=translator_version]
[,CALLMETH=ATTACH|LINK|TSOLNK|ISPLINK]
[,TASKLIB=translator_ddname]
[,INPLIST=N|Y]
[,MBRRC=maximum_good_return_code]
```

Note: Refer to the *ISPF Software Configuration and Library Manager (SCLM) Reference* for information about the two translators FLMTPRE and FLMTPOST.

FLMTYPE - Define One FLMTYPE in the Project Definition

Macro Format

```
name FLMTYPE [EXTEND=extended_type]
```

FLMTYPE - FLMWKST

Chapter 5. System Variables

The system variables are described with type and pool information in the following tables. The variables are also discussed with the ISPF service to which they apply.

Commonly used system variables that a dialog can access are listed below. They are grouped by topic.

The first column gives the name of the variable. The second column indicates in which pool the variable resides. The following abbreviations are used:

func Function pool
shr Shared pool
prof Profile pool
any Any pool.

The third column indicates the variable's type. The following abbreviations are used:

in Input variable, set by a dialog to provide information to ISPF
out Output variable, set by ISPF to provide information to dialogs
non Non-modifiable output variable
i/o Both an input and an output variable.

The fourth column gives the length of the variable.

The fifth column gives a brief description of the variable.

Numeric system variables set by ISPF are right-justified and padded with zeros on the left, if necessary. If a program function uses the VCOPY service to access the variable, the value will be in character string format rather than in fixed binary format.

Time and Date

Name	Pool	Type	Len	Description
ZDATE	shr	non	8	Current date. The format of ZDATE depends on the current national language (see ZDATEF and ZDATEFD).
ZDATEF	shr	non	8	Current national language date format using the characters DD for day, MM for month, and YY for year. ZDATEF contains the national language delimiter. For example, DD/MM/YY, YY/MM/DD, MM.DD.YY. For countries that use a delimiter other than a slash (/), that delimiter replaces the slash in the date representation.
ZDATEFD	shr	non	8	The date format as described under ZDATEF but with the national language convention instead of DD, MM, and YY.
ZDATESTD	shr	non	8	Current date with a 4-digit year (YYYY/MM/DD). The format of ZDATESTD depends on the current national language (see ZDATEF and ZDATEFD).
ZDAYOFWK	shr	non	8	The name of the day of the week.
ZDAY	shr	non	2	Day of month (2 characters)
ZJDATE	shr	non	6	Day-of-year date (format yy.ddd)

System Variables

Name	Pool	Type	Len	Description
ZJ4DATE	shr	non	8	Day-of-year date (format yyyy.ddd)
ZMONTH	shr	non	2	Month of year (2 characters)
ZSTDYEAR	shr	non	4	All 4 digits of the current year (4 characters).
ZTIME	shr	non	5	Time of day (format hh:mm)
ZTIMEL	shr	non		Time of day (format hh:mm:ss:TQ —where <i>T</i> is tenths of a second, and <i>Q</i> is hundredths)
ZYEAR	shr	non	2	Year (2 characters)

The current date is displayed in the appropriate format for the session language, where DD=DAY, MM=MONTH, and YY=YEAR. For countries that use a delimiter other than a slash (/), that delimiter replaces the slash in the date representation.

General

Name	Pool	Type	Len	Description
Z	shr	non	0	Null Variable
ZACCTNUM	shr	non	40 ²	The MVS account number specified at logon time.
ZAPLCNT	shr	non	4	Number of times APL invoked for a logical screen
ZAPPLID	shr	non	8	Application identifier
ZAPPTTL	any	in	N/A	When running in GUI mode, the title to be displayed in the window frame. Note: If the panel is to be displayed in a pop-up window, the value specified in ZWINTTL will be used instead of ZAPPTTL.
ZBDMAX	shr	i/o	9	Maximum number of displays that can occur within a batch mode session
ZBDMXCNT	shr	non	9	Count of current number of displays in a batch mode session
ZCS	shr	non	5	NLS currency symbol
ZCSDLL	shr	non	8	Filename of the DLL required for this level of code for the Client/Server
ZDECS	shr	non	1	NLS decimal separator character
ZDEL	shr	i/o	1	The delimiter is used to separate stacked commands. The default delimiter is a semicolon (;).
ZENTKTX	any	in	12	When you are running in GUI mode, the name that appears on the Enter key push button. If this variable is not found, <i>Enter</i> appears on the push button.

². 40 is the maximum length.

System Variables

Name	Pool	Type	Len	Description
ZENVIR	shr	non	32	<p>Environment description:</p> <ul style="list-style-type: none"> • 1 to 8 contain the product name and sequence number, ISPF x.y. The sequence number x.y indicates the following. If the sequence number: <ul style="list-style-type: none"> - <= 4.2 means the x.y version.release of ISPF - = 4.3 means ISPF for OS/390 Release 2 - = 4.4 means ISPF 4.2.1 and ISPF OS/390 Release 3 <p>System variable ZISPFOS will contain the release of ISPF for z/OS on your system. System variable ZOS390RL will contain the release of z/OS on your system.</p> <ul style="list-style-type: none"> • 9 to 16 contain the generic operating system name (MVS) • 17 to 24 contain the operating system environment (TSO or BATCH) • 25 to 32 contain blanks and are reserved.
ZEURO	shr	non	1	The EURO currency symbol.
ZGUI	shr	non	68	Workstation address or name (in character format) if ISPSTART is issued with the GUI parameter or if specified on the Settings GUI invocation panel. ZGUI will be set to blank if ISPSTART is issued without the GUI parameter or if GUI is not invoked from the Settings panel.
ZISPFOS	shr	non	30	The level of ISPF code that is running as part of z/OS on your system. This level might or might not match the z/OS level found in ZOS390RL.
ZISPFRC	shr	in	8	Return code from ISPSTART-selected dialog to invoking application.
ZKEYHELP	any	in	8	Keys help panel identifier. If a keys help panel is not specified on the referenced keylist, the application can provide the keys help panel name in this variable. If the help panel name is present as part of the referenced keylist definition, it takes precedence over the ZKEYHELP value. This system variable must be redefined each time the keys help panel is to change.
ZLANG	prof	non	8	Session language
ZLOGO	shr	non	3	Indicates whether the user has requested bypass of LOGO panel. NO indicates that the user has specified the NOLOGO keyword at the time ISPF was called, thus, requesting that the LOGO panel be bypassed. Otherwise, the value of the variable will be YES.
ZLOGON	shr	non	8	Stepname of TSO logon procedure
ZOS390RL	shr	non	16	Indicates the z/OS release running on your system.
ZPANELID	shr	non	8	The name of the currently displayed panel.
ZPFKEY	shr	non	4	The name of the PFkey (PFxx) in effect when the user exits the panel. If ZPFKEY = PF00 then no PFkey is in effect.
ZPLACE	prof	i/o	7	Command line placement (ASIS or BOTTOM)
ZPREFIX	shr	non	8	TSO user prefix
ZPROFAPP	prof	in	8	Name of application profile pool extension table
ZSCRCUR	shr	non	4	Displays the number of logical screens currently in use.
ZSCREENC	shr	non	5	Cursor position within the logical screen data.
ZSCREENI	shr	non	?	Logical screen data. Size depends upon your screen size.

System Variables

Name	Pool	Type	Len	Description
ZSCRNAME	shr	in	8	Screen name set by dialog. The screen name is in effect only for the select level in which it was defined. Option 7.3 can alter ZSCRNAME, but this will have no impact.
ZSCRMX	shr	non	4	Displays the number of logical screens allowed by the installation.
ZSCTPREF	shr	non	4	Site command table prefix
ZSCTSRCH	shr	non	1	Search order for site command table relative to system command table. Set to either B (Before ISP) or A (After ISP).
ZSYSICON	shr	non	8	The 8-character variable that contains the command to be executed when the system icon is double-clicked or close is selected.
ZSYSID	shr	non	8	The 8-character SYSNAME obtained from the SYS1.PARMLIB member IEASYSxx which is read at IPL time. NONAME is the default value of SYSNAME. The operator can change this value at IPL time. See the <i>MVS/ESA System Programming Library: Initialization and Tuning</i> (GS28-1828-2 for more information.
ZSYSNODE	shr	non	12	<p>The network node name of your installation's JES. This name identifies the local JES in a network of systems or system complexes being used for network job entry (NJE) tasks. The node name returned in ZSYSNODE derives from the NODE initialization statement of JES.</p> <p>If the system finds that the subsystem is not active, the ZSYSNODE variable contains the string —INACTIVE— (note the string delimiters).</p> <p>If the system finds that the subsystem is neither JES2 4.3 or later, nor JES3 5.1.1 or later, the ZSYSNODE variable contains the string '—DOWNLEVEL—' (note the string delimiters).</p> <p>The value in ZSYSNODE remains the same throughout the ISPF session.</p> <p>Note: If, for instance, the JES subsystem is taken down during an ISPF session and the node name is changed, the value in ZSYSNODE will still contain the value as determined at ISPF initialization.</p>
ZSYSPLEX	shr	non	8	The MVS sysplex name as found in the COUPLExx or LOADxx member of SYS1.PARMLIB . If no sysplex name is specified in SYS1.PARMLIB, ZSYSPLEX contains blanks.
ZTEMPF	shr	non	44	Name of temporary data set for file tailoring output
ZTEMPN	shr	non	8	DDNAME of temporary data set for file tailoring output
ZTERMCID	shr	non	5	CCSID coded character set identifier of the terminal. Set by ISPF based on the code page and character set of the terminal. If the terminal code page and character set cannot be queried or if they are not supported by ISPF, this variable will be blank.
ZTERMCP	shr	non	4	CECP support 4-digit code page. Note: ZTERMCS is defined as character length 4. It cannot handle 5-character Character Sets. For example, the Character Set 65535 is displayed in ZTERMCS as "5535". This does not mean that ISPF has defined Character Set 5535 (X'159F'). Two other Z variables, ZTERMCS5 and ZTERMCP5, for Character Set and Code Page respectively, were created to handle 5-character Character Sets and Code Pages. For example, the Character Set 65535 is displayed in ZTERMCP5 as 65535.
ZTERMCP5	shr	non	5	CECP support 5-digit code page

Name	Pool	Type	Len	Description
ZTERMCS5	shr	non	5	CECP support 5-character set
ZTERMCS	shr	non	4	CECP support 4-digit character set
ZTHS	shr	non	1	NLS thousands separator character
ZTS	shr	non	1	NLS time separator character
ZTSICMD	shr	non	32767 ³	The entire initial invocation command string which invoked the ISPF environment. If storage cannot be obtained at startup, only the first 50 characters will be saved.
ZTSSCMD	shr	non	32767 ³	SELECT portion of the initial invocation command.
ZUCTPREF	shr	non	4	User command table name
ZUSER	shr	non	8	User ID
ZVERB	shr	out	8	Command verb after a SETVERB command table action
ZWINTTL	any	in	N/A	Title to be displayed in pop-up window frame
ZWSCDPG	shr	non	4	When running in GUI mode, the code page of the workstation. When not running in GUI mode, value will be blank.
ZWSCON	shr	non	68	TCP/IP or APPC address when ISPF session is connected to a workstation.
ZWSOPSYS	shr	non	16	Operating system of workstation to which the session is connected. The first 10 characters are the operating system name, followed by a blank, followed by two 2-digit numbers separated by a blank. These numbers are returned to ISPF from the operating system and change by version and release.

Terminal and Function Keys

Name	Pool	Type	Len	Description
ZCOLORS	shr	non	4	Number of colors supported by the terminal type (either 1 or 7)
ZDBCS	shr	non	3	DBCS terminal capability (YES or NO)
ZFKA	prof	non	8	Current state of the function key area form (LONG, SHORT, OFF (no display))
ZGE	shr	non	3	Terminal support for graphic escape order: <ul style="list-style-type: none"> • YES — graphic escape is supported • NO — graphic escape is not supported. Note: If you are running in GUI mode, ZGE will be set to Off.
ZHILITE	shr	non	3	Extended highlighting availability (YES or NO)
ZKEYS	prof	out	4	Number of Function keys
ZKLAPPL	shr	non	4	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains the application id where the current keylist came from.

3. 32767 is the maximum length.

4. 255 is the maximum length.

System Variables

Name	Pool	Type	Len	Description
ZKLNAME	shr	non	8	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains the name of the current keylist.
ZKLTYPE	shr	non	1	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains either P (for Private) or S (for Shared) for the current keylist.
ZKLUSE	prof	i/o	1	If KEYLIST is ON this contains Y, if it is OFF, it contains an N.
ZPFCTL	prof	i/o	5	User authorization to use PFSHOW command <ul style="list-style-type: none"> • USER—User controls function key display with PFSHOW command • ON—Display function key definitions on all panels • OFF—Do not display function key definitions
ZPFFMT	prof	i/o	4	Number of Function key definitions displayed per line <ul style="list-style-type: none"> • SIX—Always display six keys per line • MAX—Display as many keys as will fit on each line
ZPFSET	prof	i/o	4	Function key definition set displayed <ul style="list-style-type: none"> • PRI—Primary set (1-12) • ALT—Alternate set (13-24) • ALL—All keys (1-24)
ZPFSHOW	prof	out	4	PFSHOW command status
ZPFxx	prof	i/o	255 ⁴	Setting for Function keys: ZPF13-ZPF24 contain settings for the primary keys (for 12-key terminals: physical keys 1-12; for 24-key terminals: physical keys 13-24) ZPF01-ZPF12 contain settings for the alternate keys (for 24-key terminals only: physical keys 1-12)
ZPFLxx	prof	i/o	8	Setting for Function key labels: ZPFL13-ZPFL24 contain labels for the primary keys ZPFL01-ZPFL12 contain labels for the alternate keys
ZPRIKEYS	prof	i/o	4	Indicates the set of Function keys that will be the primary keys <ul style="list-style-type: none"> • LOW—1 to 12 are primary keys • UPP—13 to 24 are primary keys
ZSCREEN	shr	non	1	Logical screen number up to 32 screens (1-9, A-W)
ZSCREEND	shr	non	4	Screen depth available for dialog use. In batch mode, this variable is set by the value specified for BATSCRD on the ISPSTART call.

Name	Pool	Type	Len	Description
ZSCREENW	shr	non	4	Screen width available for dialog use. In batch mode this variable is set by the value specified for BATSCRW on the ISPSTART call. ZSCREEND and ZSCREENW are generally the dimensions of the physical display screen. There are two exceptions: 1. On a 3290, if a dialog is executing on a display with a width of 160 characters and the user does a vertical split, then ZSCREENW is 80. 2. On a 3278 model 5, if a user has specified SCREEN FORMAT IS STD, then ZSCREENW is 80 and ZSCREEND is 24, rather than the maximum physical size of 132 by 27.
ZSCRMAXD	shr	non	4	Maximum screen depth available for dialog use. In batch mode, this variable is set by the value specified for BATSCRD on the ISPSTART call.
ZSCRMAXW	shr	non	4	Maximum screen width available for dialog use. In batch mode, this variable is set by the value specified for BATSCRW on the ISPSTART call. ZSCRMAXD and ZSCRMAXW are identical to ZSCREEND and ZSCREENW, except for terminals on which an alternate size is available. In that case, ZSCRMAXD and ZSCRMAXW contain the screen configuration size that produces the largest screen. For the 3290, these variables contain sizes of the hardware partition on which ISPF is operating.
ZSPLIT	shr	non	3	Split-screen mode in effect (YES or NO)
ZTERM	prof	out	8	Terminal type as defined by option 0

Scrolling

Name	Pool	Type	Len	Description
ZSCBR	prof	i/o	4	Scroll amount for the BROWSE service
ZSCED	prof	i/o	4	Scroll amount for the EDIT service
ZSCML	prof	i/o	4	Scroll amount for member lists
ZSCROLLA	shr	out	4	Value from scroll amount field (PAGE, MAX, number)
ZSCROLLD	any	in	4	Value to be used as default scroll value for scrollable dynamic areas and table display
ZSCROLLN	shr	out	4	Scroll number as computed from the value in the scroll amount field

PRINTG Command

Name	Pool	Type	Len	Description
ZASPECT	func	in	4	Aspect ratio of printed output from PRINTG
ZDEVNAM	func	in	8	Device name for PRINTG
ZFAMPRT	func	non	4	Family printer type for PRINTG

System Variables

Table Display Service

Name	Pool	Type	Len	Description
ZTDADD	func	out	3	More rows needed to satisfy scroll request (YES NO)
ZTDAMT	func	out	4	Number of rows that the dialog should add to satisfy scroll
ZTDLROWS	func	in	6	Number of rows in the logical table (dynamic table expansion)
ZTDLTOP	func	in	6	Maps current top row in physical table to its position in logical table.
ZTDMARK	any	in	note ⁵	User-defined text for table display Bottom-of-Data marker
ZTDMSG	any	in	8	User-defined message ID for table display top-row-displayed indicator
ZTDRET	func	in	8	Defines whether dialog wants to use scroll return feature.
ZTDROWS	func	out	6	Number of table rows upon return from table display
ZTDSCRIP	func	in/out	6	CRP of top row to be displayed after the scroll
ZTDSELS	func	out	4	Number of selected table rows upon return from each table display
ZTDSIZE	func	out	4	Size (number of model sets) of the table display scrollable section
ZTDSRID	func	out	6	Rowid of the row pointed to by ZTDSCRIP
ZTDTOP	func	out	6	Row number (CRP) of top row displayed during most recent table display

LIST Service

Name	Pool	Type	Len	Description
ZLSTLPP	shr	non	4	Number of lines per page in list data set
ZLSTNUML	shr	non	4	Number of lines written to current list data set page
ZLSTTRUN	shr	non	4	List data set record length truncation value

LOG and LIST Data Sets

Name	Pool	Type	Len	Description
ZLOGNAME	shr	non	44	Contains the fully qualified data set name of the log data set.
ZLSTNAME	shr	non	44	Contains the fully qualified data set name of the list data set.

Dialog Error

Name	Pool	Type	Len	Description
ZERRALRM	func	out	3	Message alarm indicator (YES or NO)
ZERRHM	func	out	8	Name of help panel associated with error message
ZERRLM	func	out	512	Long error message text

5. Any length not more than the screen width.

Name	Pool	Type	Len	Description
ZERRMSG	func	out	8	Error message-id
ZERRSM	func	out	24	Short error message text
ZERRTYPE	func	out	8	Error message type
ZERRWIND	func	out	6	Error message window type

Tutorial Panels

Name	Description
ZCONT	Name of next continuation panel
ZHINDEX	Name of first index panel
ZHTOP	Name of top panel
ZIND	YES specifies an index page
ZUP	Name of parent panel

Selection Panels

Name	Description
ZCMD	Command input field
ZPARENT	Parent menu name (when in <i>explicit chain mode</i>)
ZPRIM	YES specifies panel is a primary option menu
ZSEL	Command input field truncated at first period

DTL Panels or Panels Containing a)PANEL Section

Name	Pool	Type	Len	Description
ZCURFLD	func	out	8	Name of field (or list column) containing the cursor when the user exits the panel.
ZCURINX	func	out	8	For table display panels, the current row number of the table row containing the cursor. The value ZCURINX is in character format. If the cursor is not within a table row, this value will be 0.
ZCURPOS	func	out	4	Position of the cursor within the field specified by ZCURFLD when the user exits the panel. The value in ZCURPOS is in character format. If the cursor is not within a field, ZCURPOS will contain a 1.

Note: These variables will contain the values that would result if they were set to `.CURSOR`, `.CSRPOS`, and `.CSRROW`, as the first statements in the panel's `)PROC` section.

System Variables

Chapter 6. Dialog Variables

This appendix describes the ISPF dialog variables.

The following table lists the dialog function pool variables that are both read from and written to by several of the PDF library access services. The variables are listed in alphabetical order.

The first column lists the variable name. The second column indicates the variable's type, which corresponds to the format parameter of the ISPF VDEFINE service. The third column specifies the variable's length, which corresponds to the length parameter of the VDEFINE service.

The fourth column lists the PDF services that either read from or write to the variable. An *R* in parentheses after a service name indicates that the service, when called, reads from the given variable. A *W* in parentheses after a service name indicates that the service, when called, writes to the given variable. All variables are available to a dialog unless otherwise indicated.

The last column contains a brief description of the contents of the variable and any restrictions on the value of the variable.

Variable Name	Format	Length	Service (Access)	Description
ZCMD	Char	256	LMMDISP(W)	Primary Command field from member list panel if the command is not a valid ISPF or PDF primary command.
ZDLBLKSZ	Char	5	LMDLIST(W)	Block size.
ZDLCDATE	Char	10	LMDLIST(W)	Creation date.
ZDLDEV	Char	8	LMDLIST(W)	Device type.
ZDLDSNTP	Char	8	LMDLIST(W)	DS name type ('PDS', 'LIBRARY', or ' ').
ZDLDSORG	Char	4	LMDLIST(W)	Data set organization.
ZDLEDATE	Char	10	LMDLIST(W)	Expiration date.
ZDLEXT	Char	3	LMDLIST(W)	Number of extents used.
ZDLLRECL	Char	5	LMDLIST(W)	Logical record length.
ZDLMIGR	Char	3	LMDLIST(W)	Whether the data set is migrated ('YES' or 'NO').
ZDLRDATE	Char	10	LMDLIST(W)	Date last referenced.
ZDLRECFM	Char	5	LMDLIST(W)	Record format.
ZDLSIZE	Char	6	LMDLIST(W)	Data set size in tracks.
ZDLSPACU	Char	10	LMDLIST(W)	Space units, one of the following: CYLINDERS, MEGABYTES, KILOBYTES, BYTES, BLOCKS or TRACKS.
ZDLUSED	Char	3	LMDLIST(W)	Percentage of used tracks or pages (PDSE).
ZDLVOL	Char	6	LMDLIST(W)	Volume serial.

Dialog Variables

Variable Name	Format	Length	Service (Access)	Description
ZDSN	Char	44	LMMDISP(W)	Name of the first or only data set in the concatenation of the member list being displayed. This variable is only available for member list panels.
ZDST	Char	54	BRIF (W) EDIF (W)	Title line data name for EDIF and BRIF.
ZEDBDSN	Char	44	EDIT (R) EDREC(W)	Backup data set name for standard edit recovery.
ZEDITCMD	Char	8	Any EDIT macro	The last primary command entered in Edit.
ZEDROW	Fixed	4	EDIT (R) EDREC(W)	Row number of entry in standard edit recovery table.
ZEDSAVE	Char	8	Data_changed EDIT macro command	END command will save data (SAVE or NOSAVE).
ZEDTDSN	Char	44	EDIT (R) EDREC(W)	Target data set name for standard edit recovery.
ZEDTMCMD	Char	8	Any Edit macro	The edit command entered that caused an edit macro to run. Can be the macro name or other name is the edit DEFINE command was used to define an alias.
ZEDTMEM	Char	8	EDIT (R) EDREC(W)	Target member name (if applicable) for standard edit recovery.
ZEDTRD	Char	6	EDIT (R) EDREC(W)	Volume serial of target data set for standard edit recovery.
ZEDUSER	Char	6	EDIT (R) EDREC(W)	User data table extension for standard edit recovery.
ZEIBSDN	Char	54	EDIF (R) EDIREC(W)	Backup data name for EDIF edit recovery.
ZEIROW	Fixed	4	EDIF (R) EDIREC(W)	Row number of entry in EDIF edit recovery table.
ZEITDSN	Char	54	EDIF (R) EDIREC(W)	Target data name for EDIF edit recovery.
ZEIUSER	Char	6	EDIF (R) EDIREC(W)	User data table extension variable for EDIF edit recovery.
ZERRALRM	Char	3	ALL(W)	The value YES if an alarm was specified in the message definition; otherwise, the value NO. Set when ISPF services issue a return code of 8 or greater.
ZERRHM	Char	8	ALL(W)	The name of a Help panel, if one was specified in the message definition. Set when ISPF services issue a return code of 8 or greater.

Dialog Variables

Variable Name	Format	Length	Service (Access)	Description
ZERRLM	Char	512	ALL(W)	Long-message text in which variables have been resolved. Set when ISPF services issue a return code of 8 or greater.
ZERRMSG	Char	8	ALL(W)	Message ID. Set when ISPF services issue a return code of 8 or greater.
ZERRSM	Char	24	ALL(W)	Short-message text in which variables have been resolved. Set when ISPF services issue a return code of 8 or greater.
ZGRPLVL	Char	8	LMHIER (W)	ISPF table variable that contains the level of this ISPF library in the controlled hierarchy.
ZGRPNAME	Char	8	LMHIER (W)	ISPF table variable that contains the ISPF library group name.
ZLAC	Char	2	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Authorization code of the member.
ZLALIAS	Char	8	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Name of the real member of which this member is an alias.
ZLAMODE	Char	3	LMMDISP(W) LMMFIND(W) LMMLIST(W)	AMODE of the member.
ZLATTR	Char	20	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Load module attributes. Refer to the <i>ISPF Services Guide</i> .
ZLCDATE	Char	8	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Date on which the specified member was created. A character string in the national format. For example, yy/mm/dd or mm/dd/yy. If no value exists for this variable, the PDF component will set the value to blanks.
ZLC4DATE	Char	10	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(W)	Date on which the specified member was created, in 4-character year format. A character string in the national format. For example, yyyy/mm/dd or mm/dd/yyyy. If no value exists for this variable, the PDF component will set the value to blanks.
ZLCNORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Current number of records in the specified member. A number from 0 to 65 535. If no value exists for this variable, the PDF component will set the value to blanks.

Dialog Variables

Variable Name	Format	Length	Service (Access)	Description
ZLINORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Number of records in the specified member when it was first created. A number from 0 to 65 535.
ZLLIB	Fixed	4	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Position of the specified member in the concatenated data sets. A number from 1 to 4.
ZLMDATE	Char	8	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Date on which the specified member was last modified. A character string in the national format. (For example, <i>yy/mm/dd</i> or <i>mm/dd/yy</i> .) If no value exists for this variable, the PDF component will set the value to blanks.
ZLM4DATE	Char	10	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(W)	Date on which the specified member was last modified, in 4-character year format. A character string in the national format. (For example, <i>yyyy/mm/dd</i> or <i>mm/dd/yyyy</i> .) If no value exists for this variable, the PDF component will set the value to blanks.
ZLMEMBER	Char	8	LMMDISP(W)	Name of the current selected member.
ZLMNORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	The number of records that have been modified in the specified member. A number from 0 to 65 535.
ZLMOD	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Modification level of the specified member. A number from 0 to 99.
ZLMTIME	Char	5	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Time when the specified member was last modified. A character string in the form hh:mm.
ZLMSEC	Char	2	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Seconds value of last modified time.
ZLPDSUDA	Char	62	LMMDISP(W)	A character string containing the contents of the user data area in the PDS directory entry of the specified member if the member's statistics are not in PDF format.

Dialog Variables

Variable Name	Format	Length	Service (Access)	Description
ZLRMODE	Char	3	LMMDISP(W) LMMFIND(W) LMMLIST(W)	RMODE of the member.
ZLSIZE	Char	8	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Load module size (in Hex).
ZLTTR	Char	6	LMMDISP(W) LMMFIND(W) LMMLIST(W)	TTR of the member.
ZLUSER	Char	7	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	User ID of user who last modified the specified member.
ZLVERS	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	Version number of the specified member. A number from 1 to 99. If no value exists for this variable, the PDF component will set the value to blanks.
ZMEMCNT	Char	8	LMMLIST(W)	Number of members in the member list.
ZMLCOLS	Char	80	LMMDISP(W)	A character string that contains the member statistics column headings that appear on the member list panel display. This variable is only available for member list panels.
ZMLCR	Fixed	4	LMMDISP(W)	The relative number in the member list of the member that appears at the top of the member list display. Its range is from 1–99 999. This variable is only available for member list panels.
ZMLTR	Fixed	4	LMMDISP(W)	Number of members in the member list. Its range is from 1–99 999. This variable is only available for member list panels.
ZSCALIAS	Char	1	LMINIT(W)	Data set name is an alias ('Y' or 'N').
ZSCLM	Char	1	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Last updater of member. 'Y' indicates SCLM was last updater. 'N' indicates PDF.
ZSCMVOL	Char	1	LMINIT(W)	Data set name is multivolume ('Y' or 'N').
ZUSERMAC	Char	9	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	Application-wide edit macro.

6. Length limited only by ISPF restrictions on the length of table extension variables.

Dialog Variables

PDF Non-Modifiable Variables

The following read-only variables are available to PDF component dialogs:

Variable Name	Format	Length	Service (Access)	Description
ZCUNIT	Char	8	none	Unit name to be used for temporary allocations. This variable comes from ISPF configuration table keyword PDF_DEFAULT_UNIT.
ZCUSIZE	Fixed	4	none	Number of kilobytes available for use by the edit UNDO command when running in SETUNDO STORAGE mode. This variable comes from ISPF configuration table Keyword UNDO_STORAGE_SIZE. See <i>ISPF Edit and Edit Macros</i> for further information.
ZICFPRT	Char	3	none	ICF indicator. 'YES' - All foreground print requests will be processed using ICF. 'NO' - ICF will not be used. This variable comes from ISPF configuration table keyword PRINT_USING_ICF.
ZPDFREL	Char	8	none	PDF version number in the form "PDF x.y ". The x.y is a sequence number. If x.y: <ul style="list-style-type: none">• <= 4.2 means the x.y version.release of PDF• = 4.3 means ISPF for OS/390 Release 2• = 4.4 means PDF 4.2.1 and ISPF OS/390 Release 3
ZSESS	Char	8	none	Session manager indicator. 'Y' - Use session manager panels in options 4 and 6. 'N' - Use standard panels in options 4 and 6. This variable comes from ISPF configuration table keyword USE_SESSION_MANAGER.
ZSWIND	Char	4	none	Sliding window value used by PDF for determining the century of 2-character years. This variable comes from ISPF configuration table keyword YEAR_2000_SLIDING_RULE. Dates less than or equal to this value are 20xx. Dates greater than this value are 19xx.

Chapter 7. Dialog Tag Language (DTL) Tags

Tag Summary

The following table is an alphabetic summary of the supported Dialog Tag Language (DTL) tags for z/OS V1R2.0 ISPF. The table shows the tag, tells whether an end tag is required (Yes) or optional (No), and lists the tag's attributes (if any) and the tag content (if any) in italics. The table also lists which tags you can nest within the tag, as well as which tags you can code the tag within.

Table 2. Tag summary

Tag	End tag	Attributes	Nested tags	Used within
AB	Yes	MNEMGEN= <u>YES</u> NO ABSEPSTR=ab-separator-string ABSEPCHAR=ab-separator-character	ABC	PANEL
ABC	No	HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname PDCVAR=pcdc-variable-name <i>choice-description-text</i>	COMMENT M PDC PDSEP SOURCE	AB
ACTION	No	RUN=internal-command-name %varname PARM=parameters %varname APPLCMD= <u>NO</u> YES TYPE= <u>CMD</u> PGM PANEL WSCMD WSCMDV EXIT NEWAPPL NEWAPPL=application-id NEWWINDOW PASSLIB NEWPOOL SUSPEND SCRNAME=screen-name NOCHECK ADDPop OPT=option %varname MODE=LINE FSCR LANG=APL CREX BARRIER NEST WSDIR=ws-directory WSINVOKE= <u>MODELESS</u> MODAL WSSIZE= <u>MAX</u> MIN WSVIEW= <u>VIS</u> INVIS SETVAR=variable-name VALUE= <u>1</u> string %varname TOGVAR=variable-name VALUE1= <u>0</u> string %varname VALUE2= <u>1</u> string %varname		CHOICE PDC

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
AREA	Yes	MARGINW= <u>1</u> n MARGIND= <u>0</u> INDENT=n DEPTH=n * EXTEND= <u>OFF</u> ON FORCE DIV= <u>NONE</u> BLANK SOLID DASH TEXT DIVWIDTH= <u>MAX</u> MIN FORMAT= <u>START</u> CENTER END TEXT=divider-text WIDTH=n DIR= <u>VERT</u> HORIZ	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELFLD SOURCE	HELP PANEL
ASSIGNI	No	VALUE=test-value RESULT=assigned-value		ASSIGNL
ASSIGNL	Yes	DESTVAR=destination-variable-name	ASSIGNI	DTAFLD
ATTENTION	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
ATTR	No	ATTRCHAR=code TYPE=DATAIN DATAOUT CHAR INTENS=HIGH LOW NON %varname CAPS=OFF ON IN OUT %varname JUST=ASIS LEFT RIGHT %varname PAD=NULLS USER char %varname PADC=NULLS USER char %varname SKIP=OFF ON %varname GE=OFF ON %varname COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname HILITE=USCORE BLINK REVERSE %varname NUMERIC=OFF ON %varname FORMAT=EBCDIC DBCS MIX %varname OUTLINE=NONE L R O U BOX %varname PAS=OFF ON %varname CKBOX=OFF ON %varname CUADYN=CEF EE LEF NEF VOI LID LI CH CT DT ET FP NT PIN PT SAC SI SUC WASL WT %varname CSRGRP=NO YES n ATTN=OFF ON %varname		DA
BOTINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL
CAUTION	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
CHDIV	No	TYPE=NONE SOLID DASH TEXT GUTTER=1 n FORMAT=START CENTER END <i>divider-text</i>	HP	SELFLD CHOICE

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CHECKI	No	TYPE= RANGE PARM1=low-bound %varname PARM2=high-bound %varname ALPHA CHARS PARM1=EQ PARM2=character-set VALUES PARM1=EQ PARM2=value-list VALUESX PARM1=NE PARM2=value-list BIT NAME NAMEF PICT PARM1=EQ PARM2=pictstring PICTCN PARM1=mask-character PARM2=field-mask PARM3=string NUM DBCS LISTV PARM1=EQ PARM2=%varlist LISTVX PARM1=NE PARM2=%varlist ALPHAB LEN PARM1=operator %varname PARM2=length %varname EBCDIC ENUM DSNAME DSNAMEF DSNAMEFEM DSNAMEPQ DSNAMEEQ MIX HEX FILEID INCLUDE PARM1=IMBLK PARM2=ALPHA ALPHAB NUM PARM3=ALPHA ALPHAB NUM IDATE STDDATE JDATE JSTD ITIME STDTIME IPADDR4		CHECKL

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CHECKL	Yes	MSG=message-identifier	CHECKI	VARCLASS
CHOFLD	No	DATAVAR=field-data VARCLASS=variable-class-name HELP=NO YES help-panel-name *help-message-id %varname *%varname USAGE=BOTH IN OUT REQUIRED=NO YES MSG=message-identifier AUTOTAB=NO YES ENTWIDTH=n FLDSPACE=n ALIGN=START CENTER END DISPLAY=YES NO NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=NONE L R O U BOX %varname PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname PAS=%varname EXPAND ATTRCHANGE=NO YES NEW INIT=initial-value IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE=ABOVE BELOW LEFT RIGHT %varname ATTRCHAR=code CAPS=OFF ON <i>choice-description-text</i>	ACTION COMMENT HP PS RP SOURCE	CHOICE
CHOICE	No	NAME=choice-name HELP=NO YES help-panel-name *help-message-id %varname *%varname CHECKVAR=variable-name MATCH=1 string NOMATCH=0 string AUTOTAB=YES NO SELCHAR='char(s),n' PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=NONE L R O U BOX %varname HIDE HIDEX UNAVAIL=variable-name UNAVAILMAT=1 string TRUNC=n AUTOSEL=YES NO <i>choice-description-text</i>	ACTION CHOFLD COMMENT HP PS RP SOURCE	SELFLD
CMD	No	NAME=internal-command-name ALTDESCR=command-description <i>external-command-name</i>	CMDACT T	CMDBL

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CMDACT	No	ACTION= 'SELECT=select-parameters' 'ALIAS=internal-command-name parameters' PASSTHRU SETVERB BACKWARD CANCEL EXIT EXHELP FKA FORWARD HELP PANELID RETRIEVE %varname application-command ASIS		CMD
CMDAREA	No	HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname PMTLOC= <u>BEFORE</u> NOINIT PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname NAME=cmdarea-variable-name ENTWIDTH=n PMTTEXT=YES NO CMDLOC= <u>DEFAULT</u> ASIS CMDLEN= <u>DEFAULT</u> MAX AUTOTAB= <u>NO</u> YES SCROLLVAR=scroll-variable SCRVHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON PSBUTTON=cmd-pb-text PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname CAPS= <u>OFF</u> ON NOJUMP= <u>OFF</u> ON VARDCL= <u>YES</u> NO command-prompt-text	HP	PANEL
CMDTBL	Yes	APPLID=application-identifier SORT= <u>NO</u> YES	CMD	

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
COMMENT	No	TYPE=END CCSID PANEL ATTR ABCINIT ABCPROC INIT REINIT PROC HELP PNTS LIST <i>comment-text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP MSGMBR PANEL PDC REGION SELFLD
COMPOPT	No	REPLACE NOREPLACE SCREEN DISK NODBCS DBCS NOKANA KANA KEYLAPPL=xxxx NOPANEL PANEL NOMSGSUPP MSGSUPP NOCUASUPP CUASUPP PREP NOPREP CUAATTR NOCUAATTR NOLSTVIEW LSTVIEW STATS NOSTATS NOSCRIP SCRIPT NOLISTING LISTING NOFORMAT FORMAT NOMSGEXPAND MSGEXPAND LOGREPL NOLOGREPL LISTREPL NOLISTREPL ACTBAR NOACTBAR GUI NOGUI VERSION NOVERSION NOMERGESAREA MERGESAREA NODISPLAY DISPLAY NODISPLAYW DISPLAYW DSNCHK NODSNCHK GRAPHIC NOGRAPHIC ZVARS NOZVARS NODBALIGN DBALIGN NOMCOMMENT MCOMMENT NOVPADC PADC ADD RESET <i>national-language</i>	None	
COPYR	No	<i>copyright-text</i>		

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DA	Yes	NAME=varname EXTEND= <u>OFF</u> ON FORCE LVLIN <u>E</u> =variable-name SCROLL= <u>OFF</u> ON CMDLINE USERMOD=usermod-code %varname DATAMOD=datamod-code %varname DEPTH=n * WIDTH=n SHADOW=shadow-name DIV= <u>NONE</u> BLANK SOLID DASH TEXT FORMAT=START CENTER END TEXT=divider-text SCROLLVAR=scroll-variable SCRHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON INITATTR= <u>NT</u> CT ET WT WASL HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname	ATTR COMMENT SOURCE	AREA PANEL REGION
DD	No	<i>definition-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	DL
DDHD	No	<i>definition-description-header</i>	HP PS RP	DL
DIVIDER	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n NOENDATTR FORMAT=START CENTER END <i>divider-text</i>	HP	AREA DTACOL PANEL REGION

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DL	Yes	TSIZE= <u>10</u> 'S1, S2,... Sn' BREAK= <u>NONE</u> FIT ALL COMPACT NOSKIP INDENT= <u>n</u> FORMAT= <u>START</u> CENTER END DIVEND= <u>NO</u> YES	DD DDHD DLDIV DT DTHD DTDIV DTHDIV	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
DLDIV	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n FORMAT= <u>START</u> CENTER END <i>divider-text</i>	HP	DL
DT	No	FORMAT= <u>START</u> CENTER END NOSKIP <i>definition-term</i>	HP PS RP	DL
DTACOL	Yes	PMTWIDTH= <u>n</u> * ** ENTWIDTH= <u>n</u> DESWIDTH= <u>n</u> * SELWIDTH= <u>n</u> * FLDSPACE= <u>n</u> PAD= <u>NULLS</u> USER char %varname PADC= <u>NULLS</u> USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PMTFMT= <u>CUA</u> ISPF NONE END AUTOTAB= <u>NO</u> YES ATTRCHANGE= <u>NO</u> YES NEW PMTLOC= <u>BEFORE</u> ABOVE DBALIGN= <u>YES</u> NO PROMPT FIELD FORCE VARCLASS= <u>variable-class-name</u> REQUIRED= <u>NO</u> YES CAPS= <u>OFF</u> ON VARDCL= <u>YES</u> NO	COMMENT DIVIDER DTAFLD GRPHDR SELFLD SOURCE	AREA PANEL REGION

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DTAFLD	No	<p>NAME=field-name DATAVAR=field-data VARCLASS=variable-class-name HELP=<u>NO</u> YES help-panel-name *help-message-id %varname *%varname USAGE=<u>BOTH</u> IN OUT REQUIRED=<u>NO</u> YES MSG=message-identifier AUTOTAB=<u>NO</u> YES ENTWIDTH=<u>n</u> PMTWIDTH=<u>n</u> * ** DESWIDTH=<u>n</u> * FLDSPACE=<u>n</u> ALIGN=<u>START</u> CENTER END PMTLOC=<u>BEFORE</u> ABOVE DISPLAY=<u>YES</u> NO NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=<u>NONE</u> L R O U BOX %varname PMTFMT=<u>CUA</u> ISPF NONE END PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname PAS=%varname CSRGRP=<u>NO</u> YES n EXPAND FLDWIDTH=<u>n</u> ATTRCHANGE=<u>NO</u> YES NEW INIT=initial-value DEPTH=<u>n</u> %varname IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE=<u>ABOVE</u> BELOW LEFT RIGHT %varname DBALIGN=<u>YES</u> NO PROMPT FIELD FORCE PMTSKIP=<u>NO</u> YES DESSKIP=<u>NO</u> YES FLDTYPE=<u>CUA</u> ISPF COLOR=<u>WHITE</u> RED BLUE GREEN PINK YELLOW TURQ %varname INTENS=<u>HIGH</u> LOW NON %varname HILITE=<u>USCORE</u> BLINK REVERSE %varname ATTRCHAR=code CAPS=<u>OFF</u> ON NOJUMP=<u>OFF</u> ON AUTOTYPE=<u>PROJECT</u> GROUP1 GROUP2 GROUP3 GROUP4 TYPE MEMBER DSN AUTOVOL=volser-name AUTODMEM=<u>YES</u> NO VARDCL=<u>YES</u> NO <i>prompt-text</i></p>	<p>ASSIGNL COMMENT DTAFLDD HP PS RP SOURCE</p>	<p>AREA DTACOL PANEL REGION</p>

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DTAFLDD	No	<i>description</i>	HP PS RP	DTAFLD
DTDIV	No			DL
DTHD	No	<i>definition-term-header</i>	HP PS RP	DL
DTHDIV	No			DL
FIG	Yes	FRAME= <u>RULE</u> NONE WIDTH= <u>PAGE</u> COL NOSKIP <i>figure-content</i>	DL FIGCAP HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
FIGCAP	No	<i>figure-caption-text</i>	HP PS RP	FIG
GA	No	NAME=graphic-area-name EXTEND= <u>OFF</u> ON FORCE DEPTH= <u>n</u> * WIDTH= <u>n</u> DIV= <u>NONE</u> BLANK SOLID DASH TEXT FORMAT= <u>START</u> CENTER END TEXT=divider-text LVLINE=variable-name		AREA PANEL REGION
GENERATE	Yes		ATTR COMMENT SOURCE	AREA HELP PANEL REGION
GRPHDR	No	FORMAT= <u>START</u> CENTER END NONE WIDTH= <u>n</u> FMTWIDTH= <u>n</u> INDENT= <u>n</u> HEADLINE= <u>NO</u> YES DIV= <u>NONE</u> BLANK SOLID DASH DIVLOC= <u>AFTER</u> BEFORE BOTH COMPACT STRIP <i>group-heading-text</i>	HP PS RP	AREA DTACOL PANEL REGION

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
HELP	Yes	NAME=help-panel-name HELP=hhelp-panel-name %varname HELPDEF=helpdef-id WIDTH=50 n FIT DEPTH=10 n FIT CCSID=n TUTOR KEYLIST=key-list-name KEYLTYPE=PRIVATE SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA=NO YES MSGLINE=YES NO IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname ZUP=zup-id ZCONT=zcont-id <i>help-panel-title</i>	AREA COMMENT DIVIDER GENERATE HP INFO REGION SOURCE TEXTLINE	
HELPDEF	No	ID=helpdef-id HELP=hhelp-panel-name %varname WIDTH=n FIT DEPTH=n FIT CCSID=n KEYLIST=key-list-name KEYLTYPE=PRIVATE SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA=NO YES IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname		
H1	No	COMPACT <i>heading-text</i>		INFO
H2/H3/H4	No	COMPACT <i>heading-text</i>	HP PS RP	INFO

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
HP	Yes	TYPE= <u>ET</u> CH CT FP LEF LI NT PT SAC TEXT WASL WT COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE= <u>USCORE</u> BLINK REVERSE %varname INTENSE=varname <i>phrase-to-be-highlighted</i>		ATTENTION BOTINST CAUTION CHDIV CHOICE CMDAREA DD DDHD DIVIDER DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 HELP LI LINES LP LSTCOL LSTGRP NOTE NT P PANEL PD PNLINST PT SELFLD TOPINST WARNING XMP
INFO	Yes	WIDTH=format-width * INDENT=n	DIVIDER DL FIG H _n LINES NOTE NOTEL NT OL P PARML SL SOURCE UL XMP	AREA HELP PANEL REGION

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
KEYI	No	KEY=virtual-key CMD=internal-command-name CASE=UPPER MIXED FKA= <u>NO</u> YES LONG SHORT PARM=parm-string FKA-text		KEYL
KEYL	Yes	NAME=key-list-name HELP=help-panel-name ACTION=UPDATE DELETE APPLID=application-id	KEYI	
LI	No	SPACE= <u>NO</u> YES NOSKIP item-text	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL
LINES	Yes	NOSKIP text	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
LIT	Yes	literal-display-value		XLATI

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
LP	No	NOSKIP <i>implied-paragraph</i>	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL
LSTCOL	No	DATAVAR=column-data VARCLASS=variable-class-name HELP=NO YES help-panel-name * help-message-id %varname *%varname USAGE=BOTH IN OUT REQUIRED=NO YES MSG=message-id COLWIDTH=data-width ALIGN=START CENTER END AUTOTAB=NO YES LINE=n CLEAR POSITION=n FORMAT=START CENTER END TEXT=descriptive-text TEXTLOC=BEFORE AFTER TEXTFMT=START CENTER END TEXTLEN=n TEXTSKIP=NO YES NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=NONE L R O U BOX %varname PAS=OFF ON %varname CSRGRP=NO YES n ATTRCHANGE=NO YES NEW COLSPACE=n COLTYPE=CUA ISPF EE VOI LID COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS=HIGH LOW NON %varname HILITE=USCORE BLINK REVERSE %varname CAPS=OFF ON DISPLAY=YES NO VARDCL=YES NO <i>column-heading</i>	COMMENT HP PS RP SOURCE	LSTFLD LSTGRP

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
LSTFLD	Yes	RULES= <u>NONE</u> HORIZ VERT BOTH ROWS= <u>NOSCAN</u> SCAN %varname DIV= <u>NONE</u> BLANK SOLID DASH char SCROLLVAR=scroll-variable SCRVHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON ATTRCHANGE= <u>NO</u> YES NEW VARDCL= <u>YES</u> <u>NO</u>	COMMENT LSTCOL LSTGRP LSTVAR SOURCE	AREA PANEL REGION
LSTGRP	Yes	HEADLINE= <u>NO</u> YES DASH ALIGN= <u>CENTER</u> START END <i>column-group-heading</i>	COMMENT HP LSTCOL LSTGRP LSTVAR PS RP SOURCE	LSTFLD LSTGRP
LSTVAR	No	DATAVAR=variable-model-name LINE=n <i>column-heading</i>	COMMENT HP PS RP SOURCE	LSTFLD LSTGRP
M	No	<i>mnemonic-character</i>		ABC PDC
MSG	No	SUFFIX=message-suffix-number HELP=help-panel-name %varname * MSGTYPE= <u>INFO</u> WARNING ACTION <u>CRITICAL</u> %varname LOCATION=AREA MODAL MODAL(L) MODELESS MODELESS (L) %varname DISP= <u>KANA</u> NOKANA ALARM= <u>NO</u> YES %varname ABBREV= <u>NONE</u> KEYWORD VALUE BOTH FORMAT= <u>FLOW</u> ASIS SMSG=short-message-text <i>message-text</i>	VARSUB	MSGMBR
MSGMBR	Yes	NAME=message-member-name CCSID=n WIDTH= <u>76</u> 68	COMMENT MSG	
NOTE	No	NOSKIP TEXT=alternate-note-heading <i>note-text</i>	HP PS RP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
NOTE	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TEXT=alternate-note-heading	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
NT	Yes	NOSKIP TEXT=alternate-note-heading <i>note-text</i>	DL FIG HP LINES OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
OL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TEXT=OL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
P	No	COMPACT INTENSE= <u>varname</u> INDENT= <u>n</u> <i>paragraph-text</i>	ATTENTION CAUTION HP PS RP WARNING	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PANDEF	No	ID=pandef-id HELP=help-panel-name %varname DEPTH=n FIT WIDTH=n FIT %varname KEYLIST=key-list-name KEYLTYPE=PRIVATE SHARED APPLID=application-id CCSID=n WINDOW=YES NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=NONE L R O U BOX %varname EXPAND=xy MERGESAREA=NO YES ENTKEYTEXT=enter-key-text IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname TMARGIN=n BMARGIN=n		

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PANEL	Yes	<p>NAME=panel-name HELP=help-panel-name %varname PANDEF=pandef-id DEPTH=22 n FIT WIDTH=76 n FIT %varname KEYLIST=key-list-name KEYLTYPE=PRIVATE SHARED APPLID=application-id CURSOR=cursor-field CSRINDEX=index-value CSRPOS=position-value CCSID=n MENU PRIME TUTOR WINDOW=YES NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=NONE L R O U BOX %varname EXPAND=xy MSGLINE=YES NO TITLINE=YES NO CMDLINE=YES NO ATTRUSE=NO YES ALL ENDATTR=DEFAULT TEXT TYPE=BOTH GUI NOGUI MSG=short-msg-fieldname LMSG=long-msg-fieldname ASIS ACTBAR MERGESAREA=NO YES PANELSTMT=YES NO ENTKEYTEXT=enter-key-text IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname TMARGIN=n BMARGIN=n ERRORCHECK=NO YES ZUP=zup-id ZCONT=zcont-id AUTONRET=NO YES AUTOTCMD=NO YES panel-title-text</p>	<p>AB AREA BOTINST CMDAREA COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR HP INFO LSTFLD PNLINST REGION SELFLD SOURCE TEXTLINE TOPINST</p>	

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PARML	Yes	TSIZE= <u>10</u> 'S1 S2... Sn' BREAK= <u>ALL</u> FIT NONE COMPACT SKIP INDENT= <u>n</u> FORMAT= <u>START</u> CENTER END DIVEND= <u>NO</u> YES	PLDIV PT PTDIV PD	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
PD	No	<i>parameter-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	PARML
PDC	No	HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname UNAVAIL= <u>unavail-variable-name</u> CHECKVAR= <u>check-variable-name</u> MATCH= <u>1</u> match-string ACC1= <u>key1</u> ACC2= <u>key2</u> ACC3= <u>key3</u> <i>pull-down-description-text</i>	ACTION COMMENT M SOURCE	ABC
PDSEP	No			PDC
PLDIV	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n FORMAT= <u>START</u> CENTER END <i>divider-text</i>	HP	PARML
PNLINST	No	COMPACT <i>instruction-text</i>	HP PS RP	AREA REGION PANEL

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PS	Yes	VAR= <u>point-and-shoot-variable-name</u> %varname VALUE= <u>point-and-shoot-value</u> %varname * CSRGRP= <u>NO</u> YES n DEPTH= <u>n</u> %varname IMAPNAME= <u>image-name</u> %varname IMAPNAMEP= <u>image-namep</u> %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname <i>point-and-shoot-text</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP
PT	No	FORMAT= <u>START</u> CENTER END NOSKIP <i>parameter-term</i>	HP PS RP	PARML
PTDIV	No			PARML
REGION	Yes	DIR= <u>VERT</u> HORIZ INDENT= <u>n</u> WIDTH= <u>n</u> * DEPTH= <u>n</u> * EXTEND= <u>OFF</u> ON FORCE ALIGN= <u>YES</u> NO GRPBOX= <u>NO</u> YES GRPWIDTH= <u>n</u> GRPBOXVAR= <u>variable-name</u> GRPBOXMAT= <u>1</u> string LOCATION= <u>DEFAULT</u> TITLE <i>group-box-title</i>	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELFLD SOURCE	AREA HELP PANEL REGION

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
RP	Yes	HELP= help-panel-name help-message-id %varname *%varname <i>reference-phrase</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
SELFLD	Yes	<p>NAME=field-name HELP=<u>NO</u> YES help-panel-name *help-message-id %varname *%varname TYPE=<u>SINGLE</u> MULTI MENU MODEL TUTOR PMTLOC=<u>ABOVE</u> BEFORE PMTWIDTH=n * ** SELWIDTH=n * ENTWIDTH=2 n 'e1 e2...en' REQUIRED=<u>NO</u> YES MSG=message-identifier FCHOICE=1 0 AUTOTAB=<u>YES</u> NO DEPTH=n * EXTEND=<u>OFF</u> ON FORCE TRAIL='trail-var-1 trail-var-2 ... trail-var-n' CHOICECOLS=1 n CHOICEDEPTH=n * CWIDTHS='w1 w2...wn' PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE=<u>NONE</u> L R O U BOX %varname SELMSG=selfld-msg-identifier SELMSGU=selfld-msg-unavailable INIT=<u>YES</u> NO init-value VERIFY=<u>YES</u> NO REFRESH=<u>YES</u> NO SELFMT=<u>START</u> END CHKBOX=<u>YES</u> NO ZGUI=<u>YES</u> NO CSRGRP=<u>NO</u> YES n TSIZE='s1 s2...sn' LISTTYPE=RADIO LISTBOX DDLIST COMBO LISTREF=list-name LISTDEPTH=n DBALIGN=<u>YES</u> NO FIELD FORCE NOSEL=no-selection-value SELDEFAULT=x PMTSKIP=<u>NO</u> YES FLDTYPE=<u>CUA</u> ISPF COLOR=<u>WHITE</u> RED BLUE GREEN PINK YELLOW TURQ %varname INTENS=<u>HIGH</u> LOW NON %varname HILITE=<u>USCORE</u> BLINK REVERSE %varname SELCHECK=<u>NO</u> YES VARDCL=<u>YES</u> NO <i>field-prompt-text</i></p>	<p>CHDIV CHOICE COMMENT HP PS RP SOURCE</p>	<p>AREA DTACOL PANEL REGION</p>

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
SL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TEXT='SL-heading-text'	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
SOURCE	Yes	TYPE= <u>PROC</u> REINIT INIT ABCINIT ABCPROC <i>text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP PANEL PDC REGION SELFLD
T	No			CMD
TEXTLINE	Yes		DTAFLD TEXTSEG	HELP PANEL
TEXTSEG	No	EXPAND= <u>AFTER</u> BEFORE BOTH WIDTH= <u>n</u> <i>text</i>	HP	TEXTLINE
TOPINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL
UL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TEXT=UL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP

Summary of DTL Tags

Table 2. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
VARCLASS	No	NAME=variable-class-name TYPE='CHAR maximum length' 'DBCS maximum length' 'MIXED maximum length' 'ANY maximum length' 'EBCDIC maximum length' '%varname maximum length' ITIME STDTIME IDATE STDDATE JDATE JSTD 'VMASK maximum-length' 'NUMERIC total-digits <u>0</u> fractional-digits' MSG=message-identifier	CHECKL XLATL	
VARDCL	No	NAME=name VARCLASS=variable-class-name		VARLIST
VARLIST	Yes		VARDCL	
VARSUB	No	VAR=variable-name		MSG
WARNING	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
XLATI	No	VALUE=internal-value <i>displayed-value</i>	LIT	XLATL
XLATL	Yes	FORMAT= <u>NONE</u> UPPER TRUNC= <u>n</u> char MSG=message-identifier	XLATI	VARCLASS
XMP	Yes	NOSKIP <i>text</i>	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING

Summary of DTL Tags

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, North Castle Drive, Armonk, NY 10504-1785, USA.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries in writing to

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OR NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact the IBM Corporation, Department TL3B, 3039 Cornwallis Road, Research Triangle Park, North Carolina, 27709-2195, USA. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Programming Interface Information

This book is intended to help application programmers who write programs or command procedures that invoke ISPF and SCLM services, use the PDF editor and edit macros, or build dialogs using the Dialog Tag Language. This book documents General-Use Programming Interface and Associated Guidance information provided by ISPF.

General-use programming interfaces allow the customer to write programs that obtain the services of ISPF.

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, other countries, or both:

BookManager	Language Environment
C++	MVS
DFSMSdfp	MVS/ESA
DFSMSdss	OS/2
DFSMSHsm	OS/390
DFSMSrmm	OS/390 Security Server
DFSMS/MVS	RACF
DFSORT	Resource Access Control Facility
ESCON	SOMobjects
FFST	System View
GDDM	VisualLift
IBM	VTAM

Microsoft and Windows are registered trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.



Program Number: 5694-A01



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC34-4816-01

