

IBM Online Library



Installing, Managing, and Using the Online Library

IBM Online Library



Installing, Managing, and Using the Online Library

Note!

Before using this information and the products it supports, be sure to read the general information under Appendix C, "Notices" on page 77.

| Twenty-eighth Edition (December 2003)

| This edition applies to IBM softcopy collections produced on or after December 2003 containing online books built for viewing with the BookManager READ products or IBM Softcopy Reader.

| This book is available in online format on many of the softcopy collections distributed by the IBM Corporation and from the IBM Publications Center on the World Wide Web (<http://www.ibm.com/shop/publications/order>). The filename of the BookManager BOOK file is AB0IN01H. You can view it with the BookManager READ products and the IBM Softcopy Reader. The name of the corresponding PDF file is also AB0IN01H. This book is also available as INSTALL.TXT (for file viewers), INSTALL.PDF (printable file), INSTALL.BOO (for BookManager readers), and INSTALL.HTM (for Web browsers) in the root directory of many of the IBM softcopy collections.

To order IBM publications, contact your IBM representative or write to the IBM branch office serving your locality. Publications are not stocked at the following address.

IBM welcomes your comments. A form for your comments is provided at the back of this document. If the form has been removed from the printed book or is not accessible in the online book, address your comments to:

IBM Corporation
Department 55JA, Mail Station P384
2455 South Road
Poughkeepsie, NY 12601-5400
U.S.A.

FAX: (International Access Code)+1+845+432-9405

IBMLink (United States customers only): IBMUSM10(MHVRCFS)
Internet: mhvrcfs@us.ibm.com
World Wide Web: <http://www.ibm.com/servers/eserver/zseries/softcopy/feedback.htm>

IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1996, 2003. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

What's New	vii
Streamlined Packaging, Improved Access to Softcopy	vii
August 2003	vii
June 2003	vii
December 2002	vii
June 2002	vii
March 2002	viii
September 2000	viii
IBM Softcopy Reader and IBM Library Readers	viii
December 2003	viii
October 2003	viii
August 2003	ix
March 2003	ix
December 2002	ix
March 2001	ix
IBM SoftCopy Librarian	ix
December 2003	x
October 2003	x
August 2003	x
December 2002	x
June 2002	x
September 2001	x
June 2001	x
Tools No Longer Supported on IBM Softcopy Collections	xi
General Changes and Corrections	xi

Part 1. Introduction 1

Chapter 1. What Is the IBM Online Library?	3
What's in the IBM Online Library?	3
Collections Containing Product Libraries for a Specific Platform	3
Collections Containing Product Libraries for a Specific Function	4
Collections Containing Books for a Specific Subject or Task	4
The Relationship between the Collections	5
Regular Updates to the Collections	5
Directories and Files on IBM Softcopy Collections	5
Using IBM Softcopy Collections in Your Business	6
Direct Access at the Workstation	6
Network Access to a LAN Server	7
Host-System Access for Sharing and Centralizing Softcopy Collections	7
Internet or Intranet Access to BookManager Files via BookServer	7
Internet or Intranet Access to PDF Files	8
AS/400 System Access	8
Browser Access to a Softcopy Repository	8
What Should You Do Next?	8
How IBM Softcopy Collections Are Made Available	8
In the United States	8
In Other Countries	10
How You Can Order IBM Softcopy Collections	10

In the United States and Other Countries	10
In the United States Only	10
For More Information	10
Chapter 2. Introducing the IBM Reader Programs	13
Downloading IBM Readers from the Internet	14
Planning to Install IBM Softcopy Reader	15
Considerations for InfoSeeker	15
Transferring Files to CICS Using READ/GT	15
Chapter 3. PDF Files on IBM Softcopy Collections	17

Part 2. Installing Softcopy Tools 19

Chapter 4. Program for Installing Softcopy Tools	21
Overview	21
System Requirements	21
Software Requirements	22
Hardware Requirements	22
Getting Started	23
Using the Program for Installing Softcopy Tools	23
Reading about Using Softcopy and Tools	23
Installing or Updating Softcopy Tools	24
Installing Tools from a Network Drive	26
Adobe Reader	27
Chapter 5. Installing IBM Softcopy Reader	29
Software and Hardware Requirements	29
Installation Steps	30
Installing IBM Softcopy Reader	30
Specifying Paths to Books, PDFs, Shelves, and Shelf Indexes	31
Installing from an IBM Online Library Collection Kit CD-ROM	31
Installing from the IBM BookManager Pages on the IBM Web Site	32
Starting Book Reader and Shelf Organizer	34
Starting Book Reader	34
Starting Shelf Organizer	35
Removing IBM Softcopy Reader From Your System	36

Part 3. Managing BookManager Softcopy 37

Chapter 6. Introducing the SoftCopy Librarian	39
What the SoftCopy Librarian Can Do for You	39
Some Terms You Should Know	41
Overview of Setting Up the SoftCopy Librarian	42
Overview of Using the SoftCopy Librarian	42
Hardware and Software Requirements	43
Hardware and Software Requirements for Your Workstation	43
Hardware and Software Requirements for Your OS/390, or z/OS Host Repository	43
Hardware and Software Requirements for a Unix-like Repository	44
Hardware and Software Requirements for Your PC or LAN Repository	44
Planning for Your Repositories	44

What Does the SoftCopy Librarian Manage?	45
How Many Repositories Might I Need?	45
Where Can I Locate My Repositories?	46
What Information Must I Gather before I Can Define a Repository	46
Installing the SoftCopy Librarian	47
Locating the SoftCopy Librarian Package	47
Determining If a Later Version Is Available for Download	47
Installing the SoftCopy Librarian on a Windows Workstation	48

Part 4. Using BookManager and PDF Softcopy Files 51

Chapter 7. Setting Autorun Preferences for Collection Discs	53
Chapter 8. Using the Softcopy Collection Index with a Softcopy Repository	55
Chapter 9. Learning to Use IBM Softcopy Reader and Other IBM Readers	57
Chapter 10. Printing Hardcopy from Softcopy Files	59
Printing from a BOOK File	59
Using IBM Softcopy Reader	59
Using the z/OS or OS/390 Internet Library	60
Using BookManager READ	61
Printing a PDF File	61
Using an Adobe Reader	61
Using a LAN- or Host-attached AFP Printer	62
Chapter 11. Using IBM Softcopy Collections on Your z/OS, OS/390, z/VM, or VM Host	63
Making Bookshelves Available on z/OS or OS/390	63
Making Bookshelves Available on z/VM or VM	64
Chapter 12. Sharing IBM Softcopy Collections with Your VSE Host	65
Distributing IBM Softcopy Collections to VSE Workstations	65
Distributing IBM Softcopy Collections Using Diskettes	65
Uploading Books, Bookshelves, and Indexes to the PUN Queue	65
Receiving Books, Bookshelves, and Indexes from the PUN Queue	66
Chapter 13. Using IBM Softcopy Collections on an AS/400 System	67
Installing and Using InfoSeeker on Your AS/400 System	67
Using Directories on the AS/400 System to Share Softcopy Collections	68
Using the SCRT to Install Books to an AS/400 System Directory	68
Copying IBM Books to an AS/400 System Directory	68
Installing Books on OS/400 Version 3 Release 6 or Later	69

Part 5. Appendixes 71

Appendix A. Installing IBM Softcopy Collections on a LAN Server	73
Planning for LAN Setup	73
Appendix B. Setting Up a Walk-Up-and-Use Library Kiosk	75

Appendix C. Notices	77
Terms and Conditions for Items in the Online Library	78
Using and Copying Online Books	78
Using and Distributing the IBM Softcopy Reader Program	78
Trademarks	79
Index	81
Do You Have Questions, Problems, or Suggestions?	83
Softcopy Reader and SoftCopy Librarian	83
Other Topics	83
In the U.S.A.	83
In Other Countries	83
In All Locations	83

What's New

This section summarizes the changes made to this book.

Streamlined Packaging, Improved Access to Softcopy

August 2003

The program for setting autorun preferences has been updated for IBM Softcopy Reader 3.0.0 (or later), which supports extended shelves (XKS files) for PDFs. Extended shelves enable users to access groups of PDFs through the Shelf Organizer in Softcopy Reader.

See Chapter 7, “Setting Autorun Preferences for Collection Discs” on page 53 for more information.

June 2003

The program for setting autorun preferences has been:

- Updated to support the latest level of IBM Softcopy Reader (which was repackaged to eliminate the prerequisite for the Java Runtime Environment on the client machine)
- Recoded to comply with accessibility standards
- Renamed from SETUP.EXE to AUTORUN.EXE

See Chapter 7, “Setting Autorun Preferences for Collection Discs” on page 53 for more information.

December 2002

Information about copying the interface to the softcopy collection index has been updated. For details, see Chapter 8, “Using the Softcopy Collection Index with a Softcopy Repository” on page 55.

June 2002

Starting in June 2002, collections containing both BookManager and PDF files include an additional index for just the PDF files in the collection. The index is available in both HTML and text formats (PDFINDEX.HTM and PDFINDEX.TXT) in the root directory of the discs containing the softcopy files.

Information about copying interfaces from softcopy collections has been added.

- For information about the interface and executables for installing softcopy tools, see “Installing Tools from a Network Drive” on page 26.
- For information about the interface to the softcopy collection index, see Chapter 8, “Using the Softcopy Collection Index with a Softcopy Repository” on page 55.

Netscape is no longer shipped on softcopy collections. Internet Explorer 4.0 or later is recommended to take advantage of all the functions provided in the HTML interface to the softcopy collection index.

March 2002

Starting in March 2002, you can set autorun preferences for the programs to run when a collection disc is inserted in your CD-ROM drive. For example, you can choose to automatically start Softcopy Reader, the softcopy index for the entire collection, or the softcopy index for a single disc when you insert a disc containing softcopy files. Or, you can choose not to have anything start automatically. See Chapter 7, “Setting Autorun Preferences for Collection Discs” on page 53 for more information.

To provide more options for accessing softcopy, multi-disc collections include single-disc softcopy indexes for each disc in the collection, as well as a softcopy index for the entire collection.

September 2000

Starting in September 2000, many IBM softcopy collections include a new program to simplify installation of softcopy tools and improve access to the softcopy collection index files included on the collections. Here are the highlights of these redesigned collections:

- Instead of hardcopy collection indexes (booklets), softcopy versions are provided in the root directory of each disc. The softcopy collection index is automatically displayed when you insert a disc containing softcopy publications.
- Instead of a hardcopy version of this manual (*Installing, Managing, and Using the Online Library*), softcopy versions are provided in the root directory of each disc.
- All the softcopy tools are on a separate tools disc, instead of on each disc. For a single-disc library or collection, the tools are on the same disc as the softcopy publications.
- A new program helps you install or update softcopy tools.

The new program for installing softcopy tools runs only on Windows 95 (or later), or on Windows NT 4.0 (or later).

Users of other operating systems can still manually install or update the tools on the tools disc and directly view the softcopy versions of the collection index and this installation book.

See Chapter 4, “Program for Installing Softcopy Tools” on page 21 for details.

IBM Softcopy Reader and IBM Library Readers

December 2003

Changes were made to the chapter on installing Softcopy Reader (see Chapter 5, “Installing IBM Softcopy Reader” on page 29).

October 2003

Starting in October 2003, Softcopy Reader for Windows is supported only on Windows™ 2000 and Windows XP.

August 2003

Starting in August 2003, a new release (3.0.0) of the Softcopy Reader for Windows is being shipped on softcopy collections. This release supports extended shelves (XKS files) for PDFs. Extended shelves enable users to access groups of PDFs through the Shelf Organizer in Softcopy Reader.

Softcopy Reader's Bookshelf Organizer has been renamed to "Shelf Organizer," in recognition of the capabilities of the new extended shelf (XKS file) format. The shelf organizer can now launch the user's choice of PDF file readers (for example, Adobe® Reader™). The Shelf Organizer can also create and modify extended shelves.

Initially, extended shelves include only PDF publications. Additional publication formats are expected to be added to the extended shelf format in the future.

For more information, see Chapter 5, "Installing IBM Softcopy Reader" on page 29.

March 2003

Starting in March 2003, a new release (2.4.0) of the Softcopy Reader for Windows is being shipped on softcopy collections. This release has been repackaged using a special tool to link the Java Runtime functions along with the Softcopy Reader application code, building it into a Windows executable instead of a jar file. In addition to eliminating the prerequisite for the Java Runtime Environment on the client machine, this change has significantly improved runtime performance.

Information about installing Softcopy Reader has been updated. For details, see Chapter 5, "Installing IBM Softcopy Reader" on page 29.

December 2002

Information about installing Softcopy Reader has been updated. For details, see Chapter 5, "Installing IBM Softcopy Reader" on page 29.

March 2001

- Starting in March 2001, the IBM Library Readers for Windows, OS/2, and DOS are not being shipped on IBM softcopy collections and are no longer supported. Instead, only the IBM Softcopy Reader is included on the collections.

The IBM Library Readers will continue to be available on an as-is basis from the IBM BookManager Web site for those users who choose to continue using them.

For more information about BookManager products, including the latest news, go to this address:

<http://www.ibm.com/software/office/bkmgr/>

IBM SoftCopy Librarian

December 2003

Changes were made to the chapter on installing SoftCopy Librarian (see Chapter 6, “Introducing the SoftCopy Librarian” on page 39).

October 2003

Starting in October 2003, SoftCopy Librarian is supported only on Windows™ 2000 and Windows XP.

August 2003

Starting in August 2003, a new release (4.2) of SoftCopy Librarian supports downloading and management of PDFs via extended shelves (XKS files).

This release has been repackaged using a special tool to link the Java Runtime functions along with the SoftCopy Librarian application code, building it into a Windows executable instead of a jar file. In addition to eliminating the prerequisite for the Java Runtime Environment on the client machine, this change has significantly improved runtime performance.

For more information, see Chapter 6, “Introducing the SoftCopy Librarian” on page 39.

December 2002

Information about SoftCopy Librarian has been updated. For details, see Chapter 6, “Introducing the SoftCopy Librarian” on page 39.

June 2002

Starting in June 2002, SoftCopy Librarian (SCL) Version 3 is no longer included on softcopy collections. Only SCL Version 4 is included. Support for SCL Version 3 will be discontinued after September 30, 2002.

If you have been using SCL Version 3, use SCL Version 4 instead.

September 2001

The Softcopy Receiver Tool (SCRT) is no longer supported. It is being shipped for the last time on the September and October 2001 softcopy collections. You should start using the SoftCopy Librarian (SCL) instead.

SCL for OS/2 is no longer supported and is provided on an as-is basis. The product code is available for downloading from:

<ftp://ftp.software.ibm.com/ps/products/ibmreader/tools/ebrscl2.exe>

June 2001

The Java version of the SoftCopy Librarian, IBM SoftCopy Librarian V4.0 for Windows 95 and NT, is now available on IBM softcopy collections and can also be downloaded from this IBM Web site:

<http://publib.boulder.ibm.com/epubs/df/ebrsclwj.exe>

For details, see Chapter 6, “Introducing the SoftCopy Librarian” on page 39.

Tools No Longer Supported on IBM Softcopy Collections

As of September 2001, the Softcopy Receiver Tool (SCRT) is no longer supported. It was shipped for the last time on the September and October 2001 softcopy collections. You should start using the SoftCopy Librarian (SCL) instead.

As of December 1, 1999, IBM has discontinued support for a number of tools that used to be included on IBM softcopy collections. These include:

- Online Message Facility (OMF) and associated message parsing template (MPT) files
- Optical Media Attach (OMA)
- SCRT/VM and SCRT/MVS
- Upload utility

Information about these tools has been deleted from this book. The tools continue to be available on an “as-is” basis from this FTP server:

<ftp://ftp.software.ibm.com/ps/products/ibmreader/tools/>

General Changes and Corrections

- In the October 2003 edition, references to "Adobe Acrobat Reader" have been changed to the more general term "Adobe Reader."
- In the March 2003 edition, information about cross-book links in PDFs was added. For details, see Chapter 3, "PDF Files on IBM Softcopy Collections" on page 17.
- In the June 2001 edition, all references to MVS as an operating system, server, or host have been removed. As of March 30, 2001, the last releases of MVS as an operating system went out of service worldwide.

Part 1. Introduction

Chapter 1. What Is the IBM Online Library?	3
Chapter 2. Introducing the IBM Reader Programs	13
Chapter 3. PDF Files on IBM Softcopy Collections	17

Chapter 1. What Is the IBM Online Library?

The “IBM Online Library” contains IBM publications and product books in softcopy format, organized into collections and packaged on CD-ROMs or DVDs. Originally, the softcopy collections contained only books available in BookManager format. Increasingly, collections also contain books available in other formats, such as Portable Data Format (PDF) and HTML.

All the BookManager books in these softcopy collections can be viewed and searched electronically, without changing them, on workstations and portable laptop PCs (running Windows), host systems (running z/OS, OS/390, z/VM, VM, or CICS), and the AS/400 System. The same book can be viewed at your workstation or terminal using any of the following methods:

- The IBM Softcopy Reader, which is provided at no charge with the library on the softcopy collections
- The IBM BookManager READ component of z/OS or OS/390
- The IBM BookManager READ licensed program for VM
- The IBM BookManager BookServer component of z/OS, z/OS.e, or OS/390
- The IBM BookManager BookServer for World Wide Web licensed programs for Linux, AIX, Windows, or OS/2
- AS/400 InfoSeeker, which is provided as a part of the Operating System/400 in Version 3 and through, but not beyond, Version 4 Release 3

Think of the IBM Online Library as you would think of the public library in your community. A public library houses large numbers of books organized into a variety of collections by subject. Each collection occupies one or more bookshelves. The bookshelves contain the books. The public library has a librarian and tools to help you discover what is available, and find what you want. The IBM Online Library, like your community library, also contains large numbers of publications and product books organized into collections. But, the IBM Online Library is not a big building or a large room; it's little packages of CD-ROMs and DVDs. It's not on long rows of shelves and stacks of books; it's online. It's not up the street or down the hall; it's right under your fingertips.

What's in the IBM Online Library?

The Online Library is a variety of softcopy collections that are organized to meet specific information needs, usually for a specific IBM product or operating platform. In addition to books, some of the collections also contain online presentations, interactive demonstrations, and actual products.

Collections Containing Product Libraries for a Specific Platform

These collections contain all the product libraries related to a specific IBM operating platform. They are useful to anyone who must administer or maintain an entire system or maintain a large online library for others to use.

- z/OS V1Rx, SK3T-4269
- z/OS Software Products, SK3T-4270
- z/OS V1Rx and Software Products DVD, SK3T-4271

- OS/390, SK2T-6700
- VM, SK2T-2067
- VSE, SK2T-0060
- AS/400 V2R3.0, SK2T-8250
- AS/400 V3, SK2T-2171
- AS/400 V3R6.0, SK2T-2839
- AS/400 V3R7, SK2T-8290
- AS/400 V4, SK3T-2027

For example, the z/OS V1Rx and Software Products DVD contains all the available libraries for z/OS elements and features, plus software products that run on z/OS, regardless of the type of product.

Collections Containing Product Libraries for a Specific Function

These collections contain product libraries that are functionally related regardless of their operating system. They are useful to anyone who must specialize in a particular computing activity such as administering a network, developing applications, or maintaining a data base.

- Decision Support Systems, SK2T-0138
- Printing and Publishing, SK2T-2921
- Retail Store Solutions, SK2T-0331
- Transaction Processing and Data, SK2T-0730

For example, the Transaction Processing and Data Collection contains libraries for CICS, IMS, DB2, and other IBM transaction processing and database products.

Collections Containing Books for a Specific Subject or Task

These collections contain individual books from a variety of product libraries and other sets of books that are related to specific subjects or tasks. They are useful to anyone who has a specific task to perform such as integrating products, performing security administration, or learning about system architecture.

- z/OS Security Server RACF Collection, SK3T-4272
- OS/390 SecureWay Security Server RACF Information Package, SK2T-2180 (discontinued; see z/OS Security Server RACF Collection)
- IBM eServer iSeries 400 Redbooks, SK2T-2849
- IBM eServer zSeries Redbooks, SK3T-7876
- IBM Redbooks Data Management, SK2T-8038
- Application Development Redbooks, SK2T-8037
- Best of APPC, APPN, CPI-C, SK2T-2013
- Networking and Systems Management Redbooks, SK2T-6022
- Messages and Codes, SK2T-2068 (discontinued)

For example, the z/OS Security Server RACF Collection contains books from any z/OS product library that includes RACF information, regardless of the type of product.

The Relationship between the Collections

Some product libraries appear in more than one collection. The GDDM library is in the z/OS, OS/390, VSE, and VM platform collections because it is a product that runs on z/OS, OS/390, VSE, and VM. It is also in the Transaction Processing and Data Collection because it is used by IBM transaction processing and database products.

Even though product libraries and individual books appear in more than one collection, all the collections that are issued at the same time contain libraries and books that are at the same level.

Regular Updates to the Collections

Most IBM softcopy collections are revised regularly. Each update can include new products, new versions of existing products, updates to the existing libraries, enhancements to the Softcopy Reader program used for viewing the online libraries, and enhancements to the SoftCopy Librarian program used for managing updates to online libraries.

Many collections are revised to coincide with the release of specific products. Sometimes books or product libraries are updated sooner than the next planned updates to the collections.

- Increasingly, products are delivering the latest updates to their books on the Internet as soon as they are available. Sometimes these updates are provided for the product's general availability (GA). Sometimes they are provided to get important information to users as quickly as possible.
- Individual product libraries are sometimes provided on product-specific CD-ROMs or on DVDs with some of the new products you order. This ensures that the latest books for a product physically accompany that product when it is released for general availability (GA).

Internet updates and updated product libraries are generally included in the next update of the IBM softcopy collections to which they apply.

Directories and Files on IBM Softcopy Collections

The following table shows the directories and files common to IBM softcopy collections. Some collections have additional directories and files for features unique to that particular collection. Softcopy collections that include multiple discs might have the following files on only one disc in the collection.

Information Files

SCINDEX.xxx	Softcopy collection index, which lists and links to all the softcopy books on a collection
PDFINDEX.xxx	PDF index, which lists and links to all the the PDF files on a collection that contains both BookManager and PDF files
DISC.HTM	Disc-specific, single-disc softcopy index, which lists and links to all the softcopy books on the disc that contains this file
INSTALL.xxx	Various formats of of <i>Installing, Managing, and Using the Online Library</i>
BOOKENG.AGR	Terms for using softcopy collections
PLALRENG.AGR	License agreement for IBM Softcopy Reader

Readers (directories)

ILRJAVA Program for installing IBM Softcopy Reader

Softcopy Libraries (directories)

BOOKS The books and bookshelf search indexes on the disc
SHELVES The bookshelves and extended shelves on the disc
PDF The PDF files on the disc

Uploading and File Management Programs (directories)

SCL Program for installing IBM SoftCopy Librarian

Utilities

SCTOOLS.EXE Program for installing and updating softcopy tools; related files in AUTOHTML directory
AUTORUN.EXE Program for setting or changing autorun preferences for the programs to run when a
 collection disc is inserted

Optional Directories and Files (might not be in your softcopy collection)

Security management and performance tools
Multimedia product demos and overviews
Other file formats for books

Using IBM Softcopy Collections in Your Business

You can set up an IBM softcopy collection on your Windows workstation for yourself or you can share it with your co-workers. You can distribute the collection throughout your organization to individual workstations or to a few conveniently located, walk-up-and-use “information kiosks.” You can centralize it on your z/OS, z/OS.e, OS/390, z/VM, or VM host or on a LAN server and share it within your entire enterprise. IBM softcopy collections have been designed so that you can distribute them as widely as you need inside your enterprise.

With IBM softcopy collections, you can receive your documentation electronically, and use the SoftCopy Librarian to set up an electronic document repository to manage, update, and distribute online books throughout your business. In addition, you can use the IBM BookManager technology to build and view your own documentation, thus creating a consistent, seamless information environment for your customers.

Direct Access at the Workstation

If you have a CD-ROM or DVD drive directly attached to your Windows workstation, you can install the IBM Softcopy Reader for viewing the books and either:

- Use the CD-ROM or DVD as the storage device, and insert it whenever you need to view the books.
- Download libraries or individual books from the CD-ROM or DVD to your workstation hard drive. This can improve your access time.

- Do both: move the most frequently used libraries or individual books to your hard drive and use the remainder on the CD-ROM or DVD.

Network Access to a LAN Server

If you have a network of workstations attached to a Windows LAN server, you can:

- Use the CD-ROM or DVD as the storage device to hold all of the libraries and let your customers select the online books to open and view when they want them. Multi-disc CD-ROM drives are available so you can make a number of CD-ROMs available to your network customers.
- Download libraries or individual books from the CD-ROM or DVD to your server hard drive. This can improve your access time.
- Download libraries or individual books and reader programs from the CD-ROM or DVD to user workstations on the network.
- Do a combination: move the most frequently used libraries or individual books to your server hard drive or user workstations and use the remainder on the CD-ROM or DVD.

Host-System Access for Sharing and Centralizing Softcopy Collections

You can use a workstation to copy libraries from the CD-ROM or DVD to your host system to share and centralize online libraries for a group of users. For example, you can:

- Upload the books from a workstation to a z/OS or OS/390 host and view them from an attached terminal or workstation with the IBM BookManager READ component of z/OS or OS/390.
- Upload the books from a workstation to a z/VM or VM host and view them from an attached terminal or workstation with the IBM BookManager READ/VM licensed program. This licensed program is not provided on IBM softcopy collections.
- Upload the books and the reader installation package to a z/OS, OS/390, z/VM, or VM host, download them, and install them on a workstation that doesn't have a CD-ROM or DVD drive.

Internet or Intranet Access to BookManager Files via BookServer

If you have a z/OS, z/OS.e, OS/390, OS/2, Windows, AIX, or Linux-based server, you can upload the books and bookshelves to the server and use BookManager BookServer to serve the BookManager files to Web browsers for viewing over the Internet or an intranet. BookManager BookServer converts the BookManager files to HTML dynamically, as you read them.

BookServer now also provides limited support for PDF files when a companion BookManager Book file is present. When such a PDF is selected, BookManager BookServer launches the Adobe® Reader™ for that PDF file.

Internet or Intranet Access to PDF Files

If you have a z/OS, OS/390, OS/2, Windows, or AIX server, you can upload PDF files from an IBM softcopy collection to the server and use a Web server to serve the PDF files to Web browsers for viewing over the Internet or an intranet. You can use FTP to send the PDFs to the server as binary, VB 4096 data sets. On a z/OS or OS/390 server, users can print the PDFs via InfoPrint Server. On an OS/2, Windows, or AIX server, users can view and print the PDFs with an Adobe Reader.

AS/400 System Access

You can use your workstation to copy libraries from the CD-ROM or DVD to your AS/400 system, and then:

- Create shared folders of books from IBM softcopy collections on an AS/400, and view them using OS/400 InfoSeeker
- View the books directly from the CD-ROM or DVD using OS/400 InfoSeeker

Note: OS/400 support of InfoSeeker exists through, but not beyond, Version 4 Release 3 of the base operating system.

Browser Access to a Softcopy Repository

To improve user access to online books copied from a softcopy collection, you might want to provide a browser interface by copying the softcopy collection index that was provided on that collection. For more information, see Chapter 8, “Using the Softcopy Collection Index with a Softcopy Repository” on page 55.

What Should You Do Next?

For more information about the BookManager family of products, call 1+800+IBM-CARY (1+800+426-2279) or FAX 1+919+469-7423. You can also learn more about BookManager by accessing the World Wide Web at:

<http://www.ibm.com/software/office/bkmgr/>

If you are ready to start building your online libraries using IBM softcopy collections, see “How You Can Order IBM Softcopy Collections” on page 10.

How IBM Softcopy Collections Are Made Available

IBM softcopy collections are made available, like hardcopy books, in a variety of ways: as a feature of a product or by direct purchase of single copies or subscriptions.

In the United States

Collections are made available in the following ways:

- **Nonbillable (Entitled Basic) Product Feature Codes**

If you are a license holder for certain IBM products, such as z/OS, you can receive some collections as basic, nonbillable *features* of those products. Basic, nonbillable features are entitled and are shipped automatically. You do not need to specify any feature codes when you order the product in order to receive them. For example, the z/OS V1Rx Collection is shipped automatically with z/OS V1Rx.

- **Nonbillable (Entitled Optional) Product Feature Codes**

If you are a license holder for an IBM product that runs on AS/400, VM, or VSE, you can receive some collections as optional, nonbillable *features* of those products or prerequisite products. Optional, nonbillable features are entitled, but they are not shipped unless you specify the appropriate feature code when you order the product.

If you did not specify the optional, nonbillable feature code when you ordered the product, you can still get these entitled collections by ordering them later. Call IBM at 1+800+879-2755. There is no charge for these optional, nonbillable features. If you do not have a license for any of the products that entitle a collection, you are not entitled to an optional, no-fee collection.

- **Billable (Non-entitled) Product Feature Codes**

Some collections are available as optional, billable features of products. Optional, billable features are not entitled, and they are not shipped unless you specify the appropriate feature code when you order the product. If you did not specify the optional billable feature code when you ordered the product, you can order them later. You are billed when the collection is shipped initially. If you do not have a license for any of the products that feature the collection you want, you cannot order that collection as an optional, billable feature.

Special discounts might be available. Currently, discount subscriptions are available for the following collections:

- IBM eServer zSeries Redbooks Collection, through a feature code on z/OS
- The z/OS Security Server RACF Collection, through a feature code on z/OS
- The z/OS Software Products Collection, through a feature code on z/OS
- The z/OS and Software Products DVD Collection, through a feature code on z/OS

- **Single-Copy Purchase**

You can also purchase single copies of a collection with no updates. You can order single copies in the same way that you order any printed book from IBM. You only need to know the order number of the collection you want. You are billed for each collection you order. For more information, see “How You Can Order IBM Softcopy Collections” on page 10.

- **Subscription through the Publication Notification System (PNS)**

The Publication Notification System (PNS), an up-to-date notification application, replaced the previous System Library Subscription Service (SLSS). The PNS application is accessible from the World Wide Web at this URL:
<http://www.ibm.com/shop/publications/pns/>

PNS users are sent electronic notifications of updated publications in their profiles and they have the option of ordering the updates using the IBM Publications Center or any other IBM publication ordering channel. Currently, no automatic shipments of publications are sent with PNS. Updated publications are only sent and billed if you respond to the electronic notification.

In Other Countries

Contact your IBM representative.

How You Can Order IBM Softcopy Collections

You can order IBM softcopy collections using the IBM ordering systems normally used to order hardcopy publications or software feature codes. Specify the appropriate order number or the software feature code, where applicable. Ordering options include the Internet, toll-free numbers, and your IBM representative.

In the United States and Other Countries

To order collections for a specific country, do one of the following:

- Go to the IBM Publication Center on the World Wide Web at:

<http://www.ibm.com/shop/publications/order>

and select a country, then select Search for publications, and type the publications number. Payment options are via customer number or credit card. You can also read and download online publications in various formats free of charge at this Web site.

- Contact an IBM representative or call the local IBM office and ask for the literature department.

In the United States Only

In addition to the ordering options listed above, use any of the following methods:

- Call the IBM toll-free number 1+800+879-2755 and select the Publications option (press 1). If you are using a rotary phone, wait for assistance.
- Send an order form to IBM as follows:

- By FAX at 1+800+445+9269
- By direct mail to:

IBM Corporation
P.O. Box 29570
Raleigh, NC 27626-0570

To order a collection as a feature of a product, contact your IBM representative or call IBM Direct at 1+800+426-2255 and mention priority code LE001.

For More Information

You can obtain more information about the collections that are available, product feature codes, and ordering collections.

- If you have specific questions about IBM softcopy collections or need more information about the collections, contact IBM by any of the following methods:
 - FAX: International Access Code+1+845+432+9405
 - Internet: mhvrfs@us.ibm.com
 - World Wide Web:
<http://www.ibm.com/servers/eserver/zseries/softcopy/feedback.htm>
 - Your IBM representative

- For news about updated collections, visit <http://www.ibm.com/servers/eserver/zseries/softcopy/whatsnew.htm>
- To view the contents (catalogs) of the collections, visit <http://www.ibm.com/servers/eserver/zseries/softcopy/whatsnew.htm> and select the specific collection name for the desired edition, then select Collection Index in the desired format.

Chapter 2. Introducing the IBM Reader Programs

The following table lists the readers available, by operating system, for viewing online books in BookManager format. This includes online books on IBM softcopy collections, and also online books that you can build yourself using BookManager BUILD programs or that you receive from companies other than IBM that do not provide IBM reader programs.

IBM Softcopy Reader, listed in the second column, is included at no charge on IBM softcopy collections.

Note: Softcopy Reader 3.0.0 (or later) can also be used to access groups of PDFs via extended shelves (XKS files). However, reading the PDF files still requires a separate program, such as Adobe® Reader™. Also, you cannot use Softcopy Reader to search individual PDFs or extended shelves of PDFs.

The BookManager READ products, listed in the third column of the table, are available from IBM for a fee. The program number for ordering them is listed in the table.

For more information about BookManager products, including the latest news, see this Web site:

<http://www.ibm.com/software/office/bkmgr/>

Notes about the IBM Library Readers:

1. Starting in March 2001, the IBM Library Readers for Windows, OS/2, and DOS are not being shipped on IBM softcopy collections and are no longer supported. Instead, only the IBM Softcopy Reader is included on the collections.

The IBM Library Readers will continue to be available on an as-is basis from the BookManager pages of the IBM Web site for those users who choose to continue using them.

2. If your current IBM Library Reader is from before March 1999, make sure to install IBM Softcopy Reader. The IBM Library Readers from before March 1999 could view only the stamped books on IBM Online Library CD-ROMs. Because the books on IBM softcopy collections are no longer stamped, pre-1999 IBM Library Readers cannot open those books.

Operating System	Free reader programs (included on this softcopy collection)	IBM BookManager Readers (available from IBM)	Program Number for IBM BookManager Readers
Windows	Softcopy Reader		
Windows			See Note 4
OS/2			See Note 4
DOS			See Note 4
AIX			See Note 4
z/OS		BookManager READ	See Note 1
OS/390		BookManager READ	See Note 1
z/VM		READ/VM 1.3	5684-062
VM		READ/VM 1.3	5684-062
CICS		READ/GT	See Note 2
OS/400		InfoSeeker	See Note 3

Note:

1. BookManager READ is shipped as a component of z/OS and OS/390.
2. The READ/GT reader is available from GT Software.
3. InfoSeeker is shipped as part of AS/400. OS/400 supports InfoSeeker through, but not beyond, Version 4 Release 3 of the base operating system.
4. The following IBM BookManager products are no longer supported: READ/2, READ for Windows, READ/DOS, READ/6000, IBM Library Reader for Windows, IBM Library Reader/2, IBM Library Reader/DOS.

Downloading IBM Readers from the Internet

You can see if you are using the latest level of IBM Softcopy Reader by taking the "Softcopy Reader for Windows" link on the following page on the IBM Web site and comparing the level of your reader with that listed:

<http://www.ibm.com/software/office/bkmgr/softcopyread.html>

If you do not have the latest level, you can download it from that page.

The latest version of IBM Softcopy Reader is also available electronically by following these instructions.

- 1** FTP to ps.software.ibm.com.
- 2** Log on as anonymous with your e-mail address as the password.
- 3** Go to: /ps/products/bookmanager/tools.
- 4** Refer to the SWINREAD.TXT file in that directory.
- 5** Get the ILRJAVA.EXE file (in binary mode) from that directory.

Planning to Install IBM Softcopy Reader

You must install IBM Softcopy Reader (provided on IBM softcopy collections) in order to view and search the online books and set up an online book library on your workstation. The IBM softcopy collections contain installation programs to help you do this.

- To use the installation program for softcopy tools (which identifies whether you have the latest level of IBM Softcopy Reader), see Chapter 4, “Program for Installing Softcopy Tools” on page 21.
- To use the installation program for IBM Softcopy Reader directly, see Chapter 5, “Installing IBM Softcopy Reader” on page 29.

Code Page Requirement

Make sure you are using code page 850 (the multilingual code page) with the IBM softcopy collections. If you are not using code page 850, BookManager may not run correctly.

Considerations for InfoSeeker

If you already have InfoSeeker installed, you do not need to install an IBM Library Reader program, but you should:

- 1** Run the Library Reader/DOS installation program to update your configuration files to point the BookManager READ program to the devices containing books and bookshelves.
- 2** Update the BookManager environment variable in your CONFIG.SYS file to specify the path to the book and bookshelves by adding the pointers to the BOOKMGR statement in the CONFIG.SYS file. For example, if you want to point to the F drive, enter: **f:\books;f:\shelves** in the BOOKMGR statement.

Transferring Files to CICS Using READ/GT

If READ/GT (available from GT Software) is installed in your CICS host environment, you can transfer BookManager files from your CD-ROM to your mainframe CICS system and use them with READ/GT.

If you have access to GT Software's ASSIST/GT online referencing product, you can reference BookManager files from help windows displayed at the top of CICS application screens.

Chapter 3. PDF Files on IBM Softcopy Collections

Some IBM softcopy collections include printable files in Portable Document Format (PDF) in addition to or instead of books in BookManager form.

You can use an Adobe® Reader™ to view and print the PDF files. For tips on printing PDF files, see “Printing a PDF File” on page 61.

- Starting in September 2000, some IBM softcopy collections include a program to simplify installation of softcopy tools and improve access to the softcopy collection index. An Adobe Reader is one of the tools you can install from these collections. If this reader is not appropriate for your operating system or if you need information on installing and using an Adobe Reader, see the Adobe Web site at:

<http://www.adobe.com>

- Softcopy Reader 3.0.0 (or later) can be used to access groups of PDFs via extended shelves (XKS files). However, reading the PDF files still requires a separate program, such as Adobe Reader. Also, you cannot use Softcopy Reader to search individual PDFs or extended shelves of PDFs.

Sometimes PDF documents on a collection contain cross-book links. In order for these links to work, the PDFs must be in the same directory. If the documents are on CD-ROMs or DVDs, the documents must also be on the same disc.

PDFs link to each other by file name, and IBM changes a document's file name whenever the document is updated. Thus, a link from an unchanged PDF might not connect to a new edition of a target document, because the new edition has a new file name. However, a link from an unchanged PDF will still connect to its original target document. Therefore, if you maintain your own PDF repository, IBM recommends that you keep multiple levels of PDFs together in the same directory, to minimize unresolved links. By contrast, BookManager documents link to each other by their base order numbers, which stay the same from release to release, so an unchanged BOOK file can usually link successfully to an updated target BOOK file.

Part 2. Installing Softcopy Tools

Chapter 4. Program for Installing Softcopy Tools 21

Chapter 5. Installing IBM Softcopy Reader 29

Chapter 4. Program for Installing Softcopy Tools

Starting in September 2000, many IBM softcopy collections include a program to simplify installation of softcopy tools and improve access to the softcopy collection index files included on the collections. Here are the highlights of these redesigned collections:

- Instead of hardcopy collection indexes (booklets), softcopy versions are provided in the root directory of each disc.
- Instead of a hardcopy version of this manual (*Installing, Managing, and Using the Online Library*), softcopy versions are provided in the root directory of each disc.
- For a multi-disc library or collection, all the softcopy tools are on a separate tools disc, instead of on each disc.

For a single-disc library or collection, the tools are on the same disc as the softcopy publications.

- An additional program (SCTOOLS.EXE) helps you install or update softcopy tools.

This chapter introduces the program for installing softcopy tools.

Who can use this install program?

The program for installing softcopy tools runs only on Windows 95 (or later), or on Windows NT 4.0 (or later).

Users of other operating systems can still manually install or update the tools on the collection, and view the softcopy versions of the collection index and this installation book directly.

Overview

The program for installing softcopy tools (SCTOOLS.EXE) helps you:

- Learn about the IBM softcopy tools included on the softcopy collection: IBM Softcopy Reader and IBM SoftCopy Librarian (SCL).
- Install or update these softcopy tools as well as an Adobe Reader.

The install program checks the level of the tools (if any) installed on your computer and gives you the option of installing any tools you do not have and updating any backlevel tools.

System Requirements

Software Requirements

- Supported platforms: Windows 95 (or later), Windows NT 4.0 (or later)
- Software for viewing documents displayed by the install program:
 - **BookManager files:** IBM Softcopy Reader
The program for installing softcopy tools checks whether you have the IBM Softcopy Reader installed. If not, you can choose whether to install the latest level of this reader from the tools disc.
 - **HTML files:** A Web browser with Java Script 1.0 enabled. Internet Explorer 5.0 or later is recommended to take advantage of all the functions provided in the HTML interface to the softcopy collection index.
Note: By default, certain options of the install program display information in HTML format. So, to view this information from the install program, you should have a browser installed.
 - **PDF files:** Adobe Reader (at least 3.0)
The install program checks whether you have an Adobe Reader installed. If not, you can choose whether to install an Adobe Reader from the tools disc.
 - **Text files:** Any workstation file viewer or browser
- Software required for softcopy tools on the tools disc
 - IBM Softcopy Reader: See “Software and Hardware Requirements” on page 29.
 - IBM SoftCopy Librarian: See “Hardware and Software Requirements” on page 43.
 - Adobe Reader: See “Adobe Reader” on page 27.

Hardware Requirements

- Any personal computer capable of running Windows 95 (or later) or Windows NT 4.0 (or later) with an Intel Pentium or compatible processor
- Display device supported by Windows 95 (or later) or Windows NT 4.0 (or later) with VGA or better resolution
- Any pointing device supported by Windows 95 (or later) or Windows NT 4.0 (or later)
- A CD-ROM or DVD reader accessed as a Windows drive
- Additional RAM or hard disk space as required by the softcopy tools on the tools disc (see the chapters on those tools for details)
- Additional hardware requirements for the softcopy tools on the tools disc
 - IBM Softcopy Reader: See “Software and Hardware Requirements” on page 29.
 - IBM SoftCopy Librarian: See “Hardware and Software Requirements” on page 43.
 - Adobe Reader: See “Adobe Reader” on page 27.

Optional Hardware

- A Windows-supported printer

Getting Started

1. Insert the tools disc into your CD-ROM or DVD drive.

- For a multi-disc library or collection, the install program starts automatically if autorun is enabled on your computer.

The install program does not start automatically if autorun is disabled on your computer. In this case, run SCTOOLS.EXE (in the root directory) to start the install program.

- For a single-disc kit, the install program does not start automatically. To start the install program, run SCTOOLS.EXE (in the root directory).

Note: If autorun is enabled on your computer, you can access the files on the tools disc without automatically launching any programs or files and without disabling autorun. Go to My Computer or Windows Explorer, right-click on the icon for your CD-ROM or DVD drive, then click Explore.

2. If desired, read the online documentation provided with the install program (SCREADME.TXT for the install program, or the online version of *Installing, Managing, and Using the Online Library*).

3. Using the install program, install the desired softcopy tools (See “Using the Program for Installing Softcopy Tools” for details.)

4. Exit the install program.

5. Insert a data disc to view the softcopy collection index, which lists and links to the publications in the collection.

Using the Program for Installing Softcopy Tools

When the install program starts, you see a list of the tasks the program can help you with:

- Read about using softcopy and tools
- Install or update softcopy tools

You can also get help for the install program, as well as send feedback on the program or on the IBM softcopy collection.

The following sections describe the tasks in more detail.

Reading about Using Softcopy and Tools

To learn more about the install program, about softcopy in general and the tools that help you use and manage softcopy, or about the specific publications on the softcopy collection in your CD-ROM or DVD drive, click Read about using softcopy and tools. Then choose either of these online documents:

- SCREADME.TXT for the install program

- *Installing, Managing, and Using the Online Library* (the book you are now reading). By default, you see the HTML format of this book, but you can choose to see it in any of these formats:
 - **HTML:** For viewing with a Web browser.
 - **BookManager:** For viewing and searching with the IBM Softcopy Reader. This format provides the best search function of all the formats. It can also be used to print selected sections of the book, but the PDF format is recommended for printing large sections or an entire book.

Note: When you select the BookManager format, you might see a warning message prompting you to select whether to open the file or save it to disk. Select *Open it*. Also, to view BookManager files without being interrupted by this warning, uncheck the box *Always ask before opening this type of file*.
 - **PDF:** For viewing and printing with an Adobe Reader. From this format you can print high-quality output that looks very similar to printed books received from IBM.
 - **Text:** For viewing with a workstation file viewer, such as Notepad.

From this window, you can also choose to view the softcopy collection index for the collection currently in your CD-ROM or DVD drive. This index is available as an HTML file, and also in the additional formats provided for *Installing, Managing, and Using the Online Library*, if available. From the HTML format, you can search for keywords in the file and open the softcopy files for the libraries and publications listed, provided that the disc containing the files is in your CD-ROM or DVD drive.

In addition, you can see Web links (URLs) that are helpful for this IBM softcopy collection. Plus, you can go directly to the *Send feedback* option to provide comments or ask questions about the IBM softcopy collection itself or about the program for installing softcopy tools.

Note: The install program displays the files for this option through a Web browser. If you do not yet have a Web browser installed, you can:

- Select the *Install or update softcopy tools* option to install one.
- Use a workstation file viewer to view the following text files. These files are in the root directory of the tools disc:
 - *INSTALL.TXT*: *Installing, Managing, and Using the Online Library*
 - *SCINDEX.TXT*: softcopy collection index

Installing or Updating Softcopy Tools

To install the tools for viewing and managing the softcopy on this collection, or to be sure you have the latest level of these tools, click *Install or update softcopy tools*.

1. The install program checks which softcopy tools currently exist on your computer and recommends what should be installed or updated to view and manage the collection.

You can deselect (uncheck) what you do not want to install or update.

These are the tools that you can install or update:

- IBM Softcopy Reader. Recommended reader. For more information, see Chapter 5, “Installing IBM Softcopy Reader” on page 29.
 - IBM SoftCopy Librarian. If you plan to copy softcopy publications to a repository, select V4 (Java) of SoftCopy Librarian. V4 requires Java Runtime Environment (JRE) 1.3 or later (from either IBM or Sun Microsystems, Inc.); it will not be installed if minimum level of JRE is not already installed. The install program checks whether the required level of JRE is installed; if not, the install program can help you install it. For more information, see “Installing the SoftCopy Librarian” on page 47.
 - Adobe Reader. For more information, see “Adobe Reader” on page 27.
2. After you make your selections, the program installs the selected items.
- You might need to respond to prompts as the individual tools are being installed. The README files for some of the softcopy tools contain additional information to help you install these tools. User's guides are also available after you have installed certain tools.
- **IBM Softcopy Reader:** ILRJAVA\README.TXT on tools disc and Start→Programs→IBM Softcopy Reader→User's Guide
 - **IBM SoftCopy Librarian:** Start→Programs→IBM Softcopy Librarian→User's Guide
3. Once installation is complete, you can choose to see the softcopy collection index for the library or collection currently in your CD-ROM or DVD drive.
4. If you installed IBM Softcopy Reader, make sure to shut down and restart your browser. This ensures that the browser will invoke IBM Softcopy Reader to open BookManager files.

The Softcopy Collection Index

When you view the softcopy collection index from the SCTOOLS.EXE interface, you see the HTML format by default, but you can choose to see it in any of these formats, if they are available:

- **HTML:** For viewing with a Web browser. This format is only the catalog (index) portion of the complete booklet for the library or collection. The HTML format contains links that enable you to open the softcopy files for the libraries and manuals listed. Internet Explorer 5.0 or later is recommended to take advantage of all the functions provided for viewing the HTML version of the softcopy collection index.

Note: In order for the links to open the softcopy files, the preferences for your browser must point to the IBM reader program you installed for viewing BookManager books (extension .BOO), bookshelves (extension .BKS), and extended shelves (extension .XKS, for use with Softcopy Reader 3.0.0 or later).

If you install a copy of IBM Softcopy Reader from September 2000 (V2.3.1) or later and agree to have Softcopy Reader be the default reader for BookManager files, the installation process automatically updates the preferences for you. Otherwise, you cannot set up browser preferences for Softcopy Reader.

- **BookManager:** For viewing and searching with the IBM Softcopy Reader. This format is the complete collection booklet. The BookManager format provides the best search function of all the formats. It can also be used to print selected

sections of the book, but the PDF format is recommended for printing large sections or an entire book.

Note: When you select the BookManager format, you might see a warning message prompting you to select whether to open the file or save it to disk. Select *Open* it. Also, to view BookManager files without being interrupted by this warning, uncheck the box *Always ask before opening this type of file*.

- **PDF:** For viewing and printing with an Adobe Reader. This format is the complete collection booklet. From the PDF format you can print high-quality output that looks very similar to printed books received from IBM.
- **Text:** For viewing with a workstation file viewer, such as Notepad. This format is only the catalog (index) portion of the complete booklet for the library or collection.

All formats of the softcopy collection index are searchable. For example, you can look for any text or phrase that appears in the title of a publication or library.

From this window, you can also choose to view *Installing, Managing, and Using the Online Library*. This book is available in these formats:

- HTML
- BookManager
- PDF
- Text

In addition, you can see Web links that are helpful for this IBM softcopy collection. Plus, you can go directly to the *Send feedback* option to provide comments or ask questions about the install program or the IBM softcopy collection itself.

Installing Tools from a Network Drive

You might want to provide a group of users with the ability to install one or more softcopy tools from a network drive. There are several way to do this:

- The simplest way is to copy the desired executables from the collection to the desired directory on the network drive. For example, to enable users to install IBM Softcopy Reader, you could copy ILRJAVA.EXE from the \ILRJAVA directory on the tools disc of the collection to a directory on your network drive. Users could then run ILRJAVA.EXE from the network drive to install IBM Softcopy Reader.
- To run the complete SCTOOLS.EXE interface from a network drive, you need to copy the complete directory structure. All the paths are relative. (The files and directories listed below are the only ones required for SCTOOLS.EXE to install tools. The other files and directories on the tools disc provide background information.)

SCTOOLS.EXE - program for installing softcopy tools

\ADOBE - contains Adobe Reader
\AUTOHTML - contains products.txt
\ILRJAVA - contains IBM Softcopy Reader
\SCL - contains IBM SoftCopy Librarian

Note: SCTOOLS.EXE is written as a local application. It cannot run from an HTTP server and interact with users.

Adobe Reader

To help you view and print PDF files displayed by the program for installing softcopy tools, the collections and libraries containing that install program also include a recent level of Adobe Reader.

- If your computer meets the requirements described in “System Requirements” on page 21, use the install program to install an Adobe Reader.
- Otherwise, go to the ADOBE directory on the tools disc and run the EXE file to install an Adobe Reader.

If the Reader on the tools disc is not appropriate for your operating system, or if you need information about Adobe Readers, go to the products page at this Web site:

<http://www.adobe.com/>

Chapter 5. Installing IBM Softcopy Reader

IBM Softcopy Reader is made up of two programs: (1) Book Reader, and (2) Shelf Organizer. It can be installed on a personal computer with Windows 2000 or Windows XP.

Refer to Readme file

Please refer to the **Readme** file shipped with the IBM Softcopy Reader to ensure you have the latest most up-to-date installation instructions.

When you install the Softcopy Reader, four items will be installed on your workstation.

- **Readme file** — contains the latest information on the product and installation instructions
- **IBM Softcopy Reader User's Guide** — explains how to use the Softcopy Reader
- **Book Reader program** — allows you to view and search online books
- **Shelf Organizer program** — allows you to view and manage online shelves, and view or search the online books or PDFs they contain.

Note: Starting with the March 2003 IBM Online Library Collection Kits, the Book Reader and Shelf Organizer programs are now executable in the native Windows environment. You no longer need to have the Java Runtime environment installed on your machine.

Once Softcopy Reader is installed, you can run the Book Reader and Shelf Organizer programs by clicking on the icons installed on the Window's desktop, or by clicking the Start button on the Windows desktop and select the following:
Start > Programs > IBM Softcopy Reader

Software and Hardware Requirements

Required Software

- **Operating system** — One of the following:
 - Microsoft Windows 2000 or XP

Required Hardware

- Any personal computer capable of running Windows 2000 or XP with an Intel Pentium II (or higher), or compatible processor
- Display device supported by Windows 2000 or XP (VGA or better resolution)
- Any pointing device supported by Windows 2000 or XP
- A minimum of 256MB of RAM is recommended
- Hard-disk drive storage in addition to the storage required by Windows 2000 or XP:
 - IBM Softcopy Reader: 100MB (a total of 140MB of free disk space is required to run the install program.)

- One or more Windows-supported CD-ROM drives and the equipment needed to attach them to your workstation

Optional Software:

- Adobe Reader is required if you plan to view PDF files.

Optional Hardware:

- A Windows-supported printer

Directory Names of Your Books, PDFs, Shelves and Shelf Indexes

During installation you will be asked to specify the locations (path names) for books, shelves and shelf indexes on your system. You can specify paths for books, PDFs, shelves and shelf indexes:

- The hard drive(s) on your system (C:,D:,E:, etc.)
- CD-ROM drive(s) on your system
- External hard drives or CD-ROM drives that you are connected to via a network (you may have multiple CD-ROM drives that you want to access)
- Other storage devices that can be attached to your system

During installation, you will be asked to specify the drive letter of your primary CD-ROM drive. The Shelf Organizer can do an auto refresh when the CD is removed and replaced with another.

Please have this information available when you start the installation.

Installation Steps

This is the recommended sequence for installing IBM Softcopy Reader:

1. Remove any previous versions of IBM Softcopy Reader, and beta versions of Softcopy Reader for Java. See “Removing IBM Softcopy Reader From Your System” on page 36.
2. Install IBM Softcopy Reader. This program can be downloaded from IBM Online Library Collection kits, and from the IBM BookManager pages on the IBM Web site (the latest level will be on the IBM Web site).
3. Start and run Book Reader or Shelf Organizer. See “Starting Book Reader and Shelf Organizer” on page 34.

Installing IBM Softcopy Reader

These procedures allow you to install IBM Softcopy Reader, which consists of Book Reader and Shelf Organizer, on your system. The install program can be downloaded for free from:

- An IBM Online Library Collection Kit CD-ROM
- The IBM BookManager pages on the IBM Web site:

<http://www.ibm.com/software/applications/office/bkmgr/softcopyread.html>

Specifying Paths to Books, PDFs, Shelves, and Shelf Indexes

You can specify the locations (path names) for books, PDFs, shelves and shelf indexes on your system that reside on:

- The hard drive(s) on your system (C:,D:,E:, etc.)
- CD-ROM drive(s) on your system
- External hard drives or CD-ROM drives that you are connected to via a network (you may have multiple CD-ROM drives you want to access)
- Other storage devices that can be attached to your system

Installing from an IBM Online Library Collection Kit CD-ROM

IBM Online Library Collection Kit CD-ROMs contain a copy of the IBM Softcopy Reader installation program. If the collection is made up of several CDs, refer to the documentation that came with it to see which CD-ROM contains the installation program. On most collections it will be on the first CD-ROM of the set.

Softcopy Tools Installation Program

This section assumes that you are not using the softcopy tools installation program to install IBM Softcopy Reader. For information about using the softcopy tools installation program, see Chapter 4, "Program for Installing Softcopy Tools" on page 21.

These instructions assume your hard disk is **C** and your CD-ROM drive is **D**. If they are not, substitute the drive letters you are using for the letters shown in the examples.

- 1** Start the Windows program.
- 2** From the IBM Online Library Collection, insert the CD-ROM containing the Softcopy Reader installation program into the CD-ROM drive on your PC.
- 3** Click on the **Start** button.
The Start menu appears.
- 4** Select the **Run** option.
The Run window appears.
- 5** In the Run window, if the following path does not appear:
d:\ilrjava\ilrjava.exe
Then type this path: **d:\ilrjava\ilrjava.exe**
- 6** Click on **OK**.
A window will open with the following message: The InstallShield(R) Wizard will install the IBM Softcopy Reader on your computer.
- 7** Click **Next** and following the instructions on the Installation window.
- 8** During installation, you will be asked to:
 - Specify the location (paths) to books, PDFs, shelves and shelf indexes.

For example: D:\BOOKS;D:\PDF;D:\SHELVES

Note: These must be valid paths; that is, the directories must already exist in the drives specified.

Multiple CD-ROM drives: If you have more than one CD-ROM drive, you can add the paths to them.

Hard disk: If you plan to copy files to your hard disk, you can add hard drive paths as well, after defining the directories on your hard drive. For example, if your hard disk is **C** and a second CD-ROM drive is **E**, the preceding example would now be:

D:\BOOKS;D:\PDF;D:\SHELVES;C:\BOOKS;C:\PDF;
C:\SHELVES;E:\BOOKS;E:\PDF;E:\SHELVES

- Specify the drive letter of your primary CD-ROM drive.
- Select the default directory shown in the window to save any notes you create in the books, or specify your own directory.

Make sure the path for the notes directory is the same as the directory in which the program files were installed. The default is C:\Program Files\IBM\Scr.

- You have the option to specify the drive letter(s) for your CD-ROM drive(s). While optional, specifying the drive letter is recommended, particularly when using the IBM Online Library Collection CD-ROMs, so that the Shelf Organizer knows to refresh its list of Shelves when the CD in the CD-ROM drive is changed.
- If you already have the IBM Library Reader installed on your system, specify if you would like to make the IBM Softcopy Reader the default reader.

- 9** When the installation is complete, you can start using Book Reader and Shelf Organizer. You do not have to reboot your system.

Icons for the Book Reader and Shelf Organizer will be placed on your desktop during installation.

Installing from the IBM BookManager Pages on the IBM Web Site

You can download the latest level of the IBM Softcopy Reader from the IBM BookManager pages on the IBM Web site as follows:

- 1** Start the Windows program.
- 2** Open your Web browser and go to the IBM BookManager Web site:
<http://www.ibm.com/software/applications/office/bkmgr/softcopyread.html>
- 3** Click on **Download Softcopy Reader self-extracting file**.
The Save As... window will open.
- 4** Select a drive and folder on your system to download the executable Softcopy Reader installation file (ILRJAVA.EXE), then click **Save**. The Softcopy Reader file will be downloaded to this drive and folder on your system.
- 5** Click on the windows **Start** button.

The Start menu should appear.

6 Select the **Run** option.

The Run window should appear.

7 In the Run window, click on **Browse**. When the Browse window opens, select the drive and folder you specified in Step 4 to save the file, then highlight the ILRJAVA.EXE file and click on **Open**. The correct path to the ILRJAVA.EXE file should be displayed in the Run window.

8 Click on **OK**.

A window will open with the following message: The InstallShield(R) Wizard will install the IBM Softcopy Reader on your computer.

9 Click **Next** and following the instructions on the Installation window.

10 During installation, you will be asked to:

- Specify the location (paths) to books, PDFs, shelves and shelf indexes.

For example: D:\BOOKS;D:\PDF;D:\SHELVES

Note: These must be valid paths; that is, the directories must already exist in the drives specified.

Multiple CD-ROM drives: If you have more than one CD-ROM drive, you can add the paths to them.

Hard disk: If you plan to copy files to your hard disk, you can add hard drive paths as well, after defining the directories on your hard drive. For example, if your hard disk is **C** and a second CD-ROM drive is **E**, the preceding example would now be:

D:\BOOKS;D:\PDF;D:\SHELVES;C:\BOOKS;C:\PDF;C:\SHELVES;
E:\BOOKS;E:\PDF;E:\SHELVES

- Specify the drive letter of your primary CD-ROM drive.
- Select the default directory shown in the window to save any notes you create in the books, or specify your own directory.

Make sure the path for the notes directory is the same as the directory in which the program files were installed. The default is C:\Program Files\IBM\Scr.

- You have the option to specify the drive letter(s) for your CD-ROM drive(s). While optional, specifying the drive letter is recommended, particularly when using the IBM Online Library Collection CD-ROMs, so that the Shelf Organizer knows to refresh its list of Shelves when the CD in the CD-ROM drive is changed.
- If you already have the IBM Library Reader installed on your system, specify if you would like to make the IBM Softcopy Reader the default reader.

11 When the installation is complete, you can start using Book Reader and Shelf Organizer. You do not have to reboot your system.

Icons for the Book Reader and Shelf Organizer will be placed on your desktop during installation.

The installation program also establishes the necessary file associations with appropriate content type settings to ensure that Softcopy Reader is launched when Books or Shelves are selected from the user's desktop, or accessed from a browser.

Starting Book Reader and Shelf Organizer

This section shows you how to start and use Book Reader and Shelf Organizer. The following table shows when you would use each program.

Functions	Book Reader	Shelf Organizer
Open a shelf		YES
Open a book	YES	YES
Open a PDF file	NO	YES
Create a new shelf		YES
Search a book	YES (single book)	YES (multiple books)
Search a PDF file	NO	NO
Search a shelf (of books)		YES
Search an extended shelf (of PDFs)	NO	NO
Search an indexed shelf (of books)		YES
Create a note in a book	YES	
Use a bookmark	YES	
Print a topic	YES	
Copy a topic to clipboard	YES	
Save a topic as HTML	YES	

Starting Book Reader

Follow these steps to start Book Reader and open a book:

- 1** Insert the IBM Online Library collection CD into the CD-ROM drive.

Note: If you are using multiple CD-ROM drives, be sure you put all of the Online Library CDs you plan to use in the drives *before* starting Book Reader or Shelf Organizer to open the Online Library.

- 2** On the Window's Desktop, start the Book Reader either by double clicking on the Book Reader desktop icon, or by clicking on the **Start** button and do the following:
 - a. Select the **Programs** option.
 - b. Select **IBM Softcopy Reader**.
 - c. In the Softcopy Reader group, select the icon for **Book Reader**

The IBM Softcopy Reader window should open.

- 3** From the Menu Bar click on **File**, then click on **Open**.

The Open Book window should open.

- 4** On the Open book window, in the Look in window click on the **down arrow symbol**. You should see a list of drives that are physically on or attached to your system via a network.
- 5** Click on the drive letter (**C:, D:, etc.**), then click on the folder containing the book you want to open. The books contained in the folder will then be listed.
- 6** Highlight the book you want to open by clicking on it, then click on **Open**. The book should open.

For instructions on using Softcopy Reader, refer to the *Softcopy Reader: User's Guide*. You can access this guide from two places.

- The IBM Online Library Reference Shelf included on most Online Library collection kit CDs.
- The Softcopy Reader "Book Reader" and "Shelf Organizer" programs. Select **Help**, from the Menu Bar, then click on **User's Guide**.

We recommend using the User's Guide shipped with the Softcopy Reader program since it will have any last minute updates to the book.

Starting Shelf Organizer

Follow these steps to start Shelf Organizer, select a shelf, then select and open a book:

- 1** Insert the IBM Online Library Collection CD into the CD-ROM drive.
Note: If you are using multiple CD-ROM drives, be sure you put all of the Online Library Collection CDs you plan to use in the drives *before* starting Softcopy Reader or Shelf Organizer to open the Online Library.
- 2** On the Window's Desktop, start the Shelf Organizer either by double clicking on the Shelf Organizer desktop icon, or by clicking on the **Start** button and do the following:
 - a. Select the **Programs** option.
 - b. Select **IBM Softcopy Reader**.
 - c. In the Softcopy Reader group, select the icon for **Shelf Organizer**.

The IBM Softcopy Reader List of Shelves window should open. The List of Shelves sub-window shows a list of the shelves you can access. This list of shelves is from all of the directory paths you specified when installing IBM Softcopy Reader, and shelves you added to the User Defined Directories for Books, PDFs, Shelves and Shelf Indexes since installation.

- 3** From the List of Shelves sub-window, highlight the shelf that contains the book you want to open by clicking on the shelf name.

Notes:

- a. The icon to the left of the shelf name you selected will change to show an open shelf.
- b. By clicking on the **Name**, **Date**, and **Title** tabs of the window, you can change the order of how the shelves are listed:
 - Alphabetically: **Name** and **Title** tabs (ascending or descending)
 - Chronologically: **Date** tab (ascending or descending) Click once for ascending and a second time for descending.

The Shelf sub-window will display the name of the Shelf you selected and list all of the books on that Shelf.

- 4** From the Shelf sub-window, double-click on a book or PDF. This will open the Book Reader window or launch Adobe Reader to display the book or PDF respectively, that you selected.

For instructions on using Softcopy Reader, refer to the *Softcopy Reader: User's Guide*. You can access this guide from two places.

- The IBM Online Library Reference Shelf included on most Online Library collection kit CDs.
- The Softcopy Reader "Book Reader" and "Shelf Organizer" programs. Select **Help**, on the Menu Bar, then click on **User's Guide**.

We recommend using the User's Guide shipped with the Softcopy Reader program since it will have any last minute updates to the book.

Removing IBM Softcopy Reader From Your System

You can easily remove (uninstall) IBM Softcopy Reader (Book Reader and Shelf Organizer) from your system.

Note: If you have created any shelf (*.BKS or *.XKS), or notes (*.NTF) files in the directory where Softcopy Reader is installed (or its subdirectories) you should backup up those files to a different location before uninstalling.

To remove (uninstall) the program:

- 1** Double-click on **My Computer** on your Windows Desktop.
The My Computer window should open.
- 2** Double-click on the **Control Panel** folder.
The Control Panel window should open.
- 3** Double-click on **Add/Remove Programs**.
The Add/Remove Program window should open.
- 4** Scroll down the list of software and highlight **IBM Softcopy Reader** by clicking on it.
- 5** Click on the **Add/Remove** button and follow the instructions on the screen.

Part 3. Managing BookManager Softcopy

Chapter 6. Introducing the SoftCopy Librarian	39
---	----

Chapter 6. Introducing the SoftCopy Librarian

This chapter introduces and summarizes what the IBM SoftCopy Librarian can do for you and how to install it.

What the SoftCopy Librarian Can Do for You

The IBM SoftCopy Librarian V4.2 provides you with the ability to manage softcopy shelves and associated publications. Shelves can either be provided by IBM or built using the IBM BookManager shelf architecture and BookManager Build for books, or a builder application for other softcopy publications, such as Adobe Acrobat Distiller for PDFs.

The SoftCopy Librarian provides the following capabilities:

- Manages the following types of BookManager files and file types (MVS and Local Unix)
 - BookManager
 - Books (BOOK or .BOO files)
 - Shelves (BKSHELF or .BKS files)
 - Extended Shelves (XKSHELF or .XKS files)
 - Shelf indexes (BKINDEX or .BKI files)
 - IBM-supplied PDF documents (PDF or .PDF files)
- Active Management, in addition to transferring files, also includes:
 - Maintaining a catalog of the contents for each of your repositories
 - Comparing what's currently in your repositories with new sources of shelves, Books, PDF and associated publications.
 - Providing you with the comparative status of the items in the source in relation to the contents of your current repositories.
 - Updating the catalogs whenever you transfer new shelves, Books, PDFs and other publications to your repositories
 - Identifying items in your repositories that can be removed because there are newer versions of these items also in your repositories.
- Set up and maintain repositories using a variety of sources. You can obtain and transfer shelves and associated publications from:
 - CD collections from IBM
 - OEM (Original Equipment Manufacturers) CD Collections
 - The IBM PUBLIB Web site (over the Internet)
 - A local hard disk
 - Other Web sites
 - Support for PDF files obtained from either the "PUBLIB" Web site, or the Collection "CD."

Note: In general, using the Internet to obtain shelves and associated publications from IBM might be slower than using CDs. We recommend that you use the IBM CD-ROM collections for the normal quarterly

refreshes, and use the Internet only for updating your repositories between quarters with the latest releases.

- Tracking of new shelves and associated publications

The SoftCopy Librarian keeps a catalog of all the shelves and associated publications that you send to your repository from any level of a CD, from your local hard drive, from the IBM PUBLIB Web site, or any other Web site that supports the SoftCopy Librarian. When a new level of a shelf arrives, on a new CD or downloaded from a Web site, the SoftCopy Librarian compares it and its contents with the catalog and shows you whether it's brand new or whether it's changed since the last level you received. You now have a way to see, at a glance, which shelves on a CD or on a supported Web site are currently in your host repository.

- Support for OS/390 and z/OS Repositories

The SoftCopy Librarian supports repositories in sequential data sets. You can use BookManager READ/MVS to access the books and shelves on your OS/390 or z/OS host. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.
- BookManager READ/MVS requires service for APAR PQ75262 before, or when, you upload extended shelves (XKS files).

- Support for OS/390 and z/OS Unix System Services Repositories

The SoftCopy Librarian supports repositories in either hierarchical file systems or sequential data sets. You can use BookManager BookServer for OS/390 or z/OS to access the books, shelves and other publications on your OS/390 or z/OS host or server. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.

- Support for Unix-like Repositories

The SoftCopy Librarian supports repositories on Unix-like servers. You can use BookManager BookServer to access the Books, shelves, PDFs and other publications on your Unix-like server. All communication with the host is done via FTP.

- Current support is for IBM TCP/IP FTP only.

- Support for PC/LAN Repositories

The SoftCopy Librarian supports repositories on LAN server or local personal computer hard drives that can be accessed as a drive letter on Windows systems. The drive must be a valid target for a Copy command. You can use the BookManager Softcopy Reader to access shelves, Books, PDFs, and other publications on your LAN server or PC workstation.

- Support for PDF files

The SoftCopy Librarian supports PDF files and extended shelves to organize them, obtained from either the "PUBLIB" Web site, or the Collection "CD."

- READ/MVS requires service for APAR PQ75262, if you place extended shelves in a z/OS or OS/390 sequential dataset repository.
- Managing your own and other manufacturer's Books, PDFs, and other publications

The SoftCopy Librarian will let you track shelves, Books, PDFs and other publications that you create or that you might receive with products from companies other than IBM.

Note: CD Collections of softcopy shelves and associated publications from others - OEM (Original Equipment Manufacturers) - must be built using the IBM BookManager shelf architecture (for shelves containing books), or the extended shelf architecture (for shelves containing PDFs) and BookManager Build or builder application for the softcopy publication. Use IBM BookManager Softcopy Reader to build extended shelves.

- Available on all IBM Online Library CDs and from the IBM Web Site

The SoftCopy Librarian is available, at no cost, on all IBM Online Library collections and on other IBM product CDs.

The latest version of the SoftCopy Librarian is also available and can be downloaded from the following IBM Web site:

<http://www.ibm.com/software/applications/office/bkmgr/librarian.html>

Some Terms You Should Know

Here are some SoftCopy Librarian terms with which you should be familiar:

Source. Is the place from where you can obtain the shelves and associated publications that you want to place onto your system. Sources can include:

- CD drive for CD collections from IBM or other manufacturers
- The Internet for connection to IBM's online library or other online libraries
- A local hard drive or server for the shelves and associated publications you can create

Repository. Is the place where your shelves, Books, PDFs and associated publications are stored. Using SoftCopy Librarian, you specify where the repository is located and how to access it. You can define multiple repositories in these locations:

- OS/390 or z/OS host sequential data sets - identified by a high-level qualifier
- OS/390, or z/OS Unix System Services hierarchical file system - identified by an HFS directory,
- A Unix-like server - identified by a Unix-like directory
- A hard drive on a local PC or LAN server - identified by a PC directory

Catalog. Is a SoftCopy Librarian file that lists the softcopy items contained in a SoftCopy Librarian repository. You can create a catalog when you set up a new, empty repository. However, the catalog is automatically updated every time you use the SoftCopy Librarian to update your repository. The SoftCopy Librarian builds a catalog by querying the contents of the directory or the high-level qualifier (HLQ) specified during the setup of the repository and then builds the catalog information.

Overview of Setting Up the SoftCopy Librarian

In general, the steps that you must plan for are:

- 1** Determine whether your hosts and workstations meet the hardware and software requirements for using the SoftCopy Librarian.
- 2** Install the SoftCopy Librarian on your workstation.
- 3** Set up one or more repositories using:
 - OS/390 or z/OS repositories in sequential data sets.
 - OS/390, or z/OS repositories in OS/390, or z/OS Unix System Services hierarchical files.
 - Unix-like repositories.
 - PC or LAN repositories.
- 4** Create a catalog for each repository.
- 5** Transfer shelves and associated publications to your repositories.
- 6** Maintain the repositories by identifying, replacing and/or deleting softcopy items.

Overview of Using the SoftCopy Librarian

After you have installed and set up the SoftCopy Librarian, you can use it to help you:

- Compare the contents of any source (that is, a CD you received, the contents of a supported Web site, or the hard drive of a server) with the catalog for any of your repositories.

This comparison will show you which shelves, Books, PDFs and associated publications on that source are new, updated, installed, partial, or down level.

- Upload only new, updated, or partial shelves to your repository.

This saves you time and DASD space and still keeps your repository up to date. The catalog is updated automatically whenever you upload to the repository.

- Maintain your host repository.

The SoftCopy Librarian shows you which shelves in your repository can be replaced by the new and updated ones that you just transferred.

You can:

- List the Books, PDFs or other publications in a shelf
- See which Books, PDFs or other publications if any, are missing from any of the shelves
- See which Books, PDFs and other publications are “orphaned,” that is not in any shelf.

All this makes it easy for you to delete the shelves and Books, PDFs or other publications that have been replaced or are no longer needed.

Hardware and Software Requirements

This section describes the hardware and software required to install and use the SoftCopy Librarian on your hosts and workstations.

Hardware and Software Requirements for Your Workstation

This section describes the hardware and software requirements for the workstation on which you will do the following:

- Install the SoftCopy Librarian
- Create a catalog of softcopy that resides in your repositories
- Transfer softcopy shelves, Books, PDFs and other publications to your repository.

It must have the following hardware and software:

A workstation that consists of:

- A minimum 500MHz processor with 256Mb RAM is recommended.
- One of the following operating systems:
 - Windows 2000 or Windows XP
- To use OS/390, or z/OS repositories, a TCP/IP link that supports FTP communications with your host
 - Current support is for IBM TCP/IP FTP only.
- To use LAN server repositories, a network connection which allows you to access the LAN server as a drive letter
- To use local PC repositories, no additional requirements
- To use CD-ROM collections as a source, a CD-ROM drive
- To use the Internet as a source or to check for updates to the SoftCopy Librarian, an Internet connection
- A minimum of 100MB of space on your hard drive

Hardware and Software Requirements for Your OS/390, or z/OS Host Repository

This section describes the software and hardware requirements for an OS/390 or z/OS host on which you will maintain one or more softcopy repositories.

Your host must have the following hardware and software:

A Host system that consists of:

- One of the following operating systems:
 - z/OS
 - OS/390
 - MVS
- A TCP/IP link that supports FTP communications from your workstation
 - Current support is for IBM TCP/IP FTP only.

Your destination host must be inside your firewall, the SoftCopy Librarian does not provide proxy support for this transfer.

- Sufficient DASD space for the shelves, Books, PDFs and other publications that will reside in your repositories.
- If you plan to:
 - Use sequential dataset repositories, and
 - store extended shelves in them, and
 - allow your users to use READ/MVS

Then you must install service for READ/MVS APAR PQ75262, to prevent READ/MVS from listing extended shelves in its List of Shelves (READ/MVS does not currently support extended shelves).

Hardware and Software Requirements for a Unix-like Repository

This section describes the software and hardware requirements for a Unix-like server on which you will maintain one or more softcopy repositories.

Your server must have the following hardware and software:

- One of the following operating systems:
 - AIX
 - Linux
 - Any other Unix type operating system
- A TCP/IP link that supports FTP communications from your workstation

Current support is for IBM TCP/IP FTP only.

Your destination server must be inside your firewall, the SoftCopy Librarian does not provide proxy support for this transfer.

- Sufficient DASD space for the shelves, Books, PDFs and other publications that will reside in your repositories.

Hardware and Software Requirements for Your PC or LAN Repository

This section describes the software and hardware requirements for a PC or LAN on which you will keep your softcopy repositories.

- You must be able to access the repository's directory as either a drive letter.
- Sufficient DASD space for the shelves, Books PDFs and other publications that will reside in your repositories.

If you meet the requirements for installing and using the SoftCopy Librarian, when you are ready, you can continue with the information in “ Planning for Your Repositories” to help plan your repositories.

Planning for Your Repositories

This section discusses what you will need to know and some of the decisions that you must make in preparation for setting up your own repositories of shelves, books, PDFs and other publications.

Note: In addition to, or instead of, setting up your own repositories, you can access the IBM Online Library on the Internet at this URL:

<http://www.ibm.com/shop/publications/order>

You need only a browser to access the entire z/OS, OS/390, z/VM, VM, and VSE libraries.

What Does the SoftCopy Librarian Manage?

The SoftCopy Librarian actively manages the following types of files:

- BookManager
 - Books (BOOK or .BOO files)
 - Shelves (BKSHELF or .BKS files)
 - Extended Shelves (XKSHELF or .XKS files)
 - Shelf indexes (BKINDEX or .BKI files)
- IBM supplied PDF documents (PDF or .PDF files)

Active management involves not just transferring files to your repositories, it also includes:

- Maintaining a catalog of the contents for each of your repositories
- Comparing what's currently in your repositories with new sources of shelves, Books, PDF and associated publications.
- Providing you with the comparative status of the items in the source in relation to the contents of your current repositories.
- Updating the catalogs whenever you transfer new shelves, Books, PDFs and other publications to your repositories
- Identifying items in your repositories that can be removed because there are newer versions of these items also in your repositories.

How Many Repositories Might I Need?

The simplest arrangement is one repository that anyone can access. You must define at least one repository for the SoftCopy Librarian to function.

You might need more than one repository depending upon several factors, which can include:

- All your users do not have access to the same host or server
- Even if they are on the same host they may not have access to the same LPAR
- You have a large number of Books, PDFs and other publications that are easier to manage in unique sets, for example, IBM and non-IBM.
- If you are migrating from one version or release of a system to another, you might want to keep the Books, PDFs and other publications in separate repositories to make it easier to delete the older set.
- If you are running a test release of your system along with your production release, you might want to keep the two separate from each other.

Where Can I Locate My Repositories?

You can set up one or more host repositories of softcopy shelves, Books, PDFs and other publications in any of the following places:

- On z/OS or OS/390 hosts:
 - In sequential data sets
 - In the hierarchical files (HFS) of Unix System Services
- On Linux, AIX or other Unix-like servers
- On LAN servers
- On local workstations

What Information Must I Gather before I Can Define a Repository

You must provide the following information when you define your repository:

- The arrangement of your repositories.
 - How many you plan have
 - What they will contain
 - Where they will be located
- **For all repositories:** A name for each new repository.
Note: This name can be anything you want. It is the name that the SoftCopy Librarian uses on your workstation to identify your repositories.

- **For host and Unix-like repositories only:** The name or IP address and the user ID and password you use to access your host or server.

- **For all repositories:** High level qualifiers or directories, which will contain these files:

- Book (.BOOK or .BOO)
- Index (BKINDEX or .BKI)
- PDF (.PDF)
- Shelves (.BKSHELF or .BKS)
- Extended Shelves (.XKSHELF or .XKS)

Note: **High Level Qualifiers** and directories can be used for all file types.

Note: **For host repositories in sequential data sets only:** Your shelves, Books, PDFs and other publications do not require unique HLQs. For example, if your BookManager code is installed under IBMBK, then the shelves, Books, PDFs and other publications could be installed under IBMBK.SOFTCOPY.

- **For host repositories in sequential data sets only**
 - A high-level qualifier for the SoftCopy Librarian's shelf list.
 - The type of DASD device you are using
 - The block size for that DASD device (provided)
 - The volume in which the data sets will reside

- **For SMS users only:** The applicable data, management, and storage classes that you are using
- **For host, Unix-type, and LAN server repositories only** Any FTP commands required by your location to transfer the shelves and associated publications from the workstation to your host or server.

Installing the SoftCopy Librarian

This section describes:

- Where you can find the SoftCopy Librarian installation package
- How to determine which version is available for download
- How to determine whether an updated version is available
- How to install the SoftCopy Librarian on Windows 2000 and Windows XP workstations.

Softcopy Tools Installation Program

This section assumes that you are not using the softcopy tools installation program to install IBM SoftCopy Librarian. For information about using the softcopy tools installation program, see Chapter 4, “Program for Installing Softcopy Tools” on page 21.

Locating the SoftCopy Librarian Package

The install package is located on the CD-ROM containing tools, which is part of the IBM Online Library collections. The package is also located on the DVD, which is part of the IBM Online Library DVD collections. The package, in a file named EBRSCWJ.EXE, is in the SCL directory.

`\SCL\EBRSCWJ.EXE`

The latest version of the Windows install package is also available at this Web address:

<http://www.ibm.com/software/applications/office/bkmgr/librarian.html>

The filename of the SoftCopy Librarian install package is **EBRSCWJ.EXE**.

Determining If a Later Version Is Available for Download

From time-to-time, an updated version of the SoftCopy Librarian is made available for download from the IBM Web site. If you are using a Windows workstation, you can check automatically or manually if a later version than the one you currently have installed on your workstation is available. You might want to do either of these checks occasionally.

Checking for a Later Version Automatically

To check automatically, do the following:

- 1** On the SoftCopy Librarian's menu bar, select Help.
- 2** In the Help pull-down menu, select Check for Updates (automatic).

When selected, the Check for Updates (automatic) choice causes the SoftCopy Librarian, at Startup, to compare the version that you have installed with the version that is currently available at the SoftCopy Librarian Web site.

3 If there is a later version available at the Web site, you will be asked if you want to download it. If you do, click **OK**.

If you choose to download it, you will also be asked if you want to install it.

4 If you want to install the new version, click **OK**.

If you choose to install it, follow the instructions in “Installing the SoftCopy Librarian on a Windows Workstation.”

Note: If, because of your firewall, the SoftCopy Librarian cannot perform the automatic check, you can use the manual check described below.

Checking for a Later Version Manually

To check manually, do the following:

1 Locate the Check for Updates (manual) choice. Do one of the following:

- **From the Windows Start Menu:**

- a. Go to the Start menu.
- b. Select Programs.
- c. From the Programs menu, select IBM SoftCopy Librarian V4.
- d. From the Service menu, select Check for Updates (manual).

- **From the SoftCopy Librarian Help Menu:**

- a. On the SoftCopy Librarian's menu bar, select Help.
- b. In the Help pull-down menu, select Check for Updates (manual).

The Check for Updates (manual) choice, presents you with an HTML page containing a link to the SoftCopy Librarian's Readme file.

2 Click on the link to the Readme file and look at the version listed.

The first line of the Readme contains the version number.

3 Compare the version listed in the Readme with the version that you have installed.

The Readme also explains how to determine which version you have installed.

4 If there is a later version available on the Web site, you can download the Windows version of the SoftCopy Librarian install package.

Installing the SoftCopy Librarian on a Windows Workstation

To install the SoftCopy Librarian on a Windows workstation, do the following:

1 Locate the install package EBRSCWJ.EXE and invoke it from Windows Explorer, the Start->Run prompt, or a command prompt.

The InstallShield Wizard window appears. When the SoftCopy Librarian code is unpacked, the Choose Destination Location window appears in the IBM SoftCopy Librarian Setup screen.

- 2** In the Choose Destination Location window, you can accept the default destination C:\Program Files\IBM\IBM SoftCopy Librarian V4 or choose another. When you are ready, press the **Next>** button.

The Start Copying Files window appears to confirm your choices.

- 3** In the Start Copying Files window, press the **Next>** button.

A progress indicator shows the SoftCopy Librarian files being installed. When the installation is complete, the Installation Wizard Complete window appears.

- 4** In the Installation Wizard Complete window, press the **Finish** button.

After you have installed the SoftCopy Librarian code, you are ready to start the SoftCopy Librarian and prepare your host or server for setting up a repository. Refer to the SoftCopy Librarian User's Guide on this collection.

Part 4. Using BookManager and PDF Softcopy Files

Chapter 7. Setting Autorun Preferences for Collection Discs	53
Chapter 8. Using the Softcopy Collection Index with a Softcopy Repository	55
Chapter 9. Learning to Use IBM Softcopy Reader and Other IBM Readers .	57
Chapter 10. Printing Hardcopy from Softcopy Files	59
Chapter 11. Using IBM Softcopy Collections on Your z/OS, OS/390, z/VM, or VM Host	63
Chapter 12. Sharing IBM Softcopy Collections with Your VSE Host	65
Chapter 13. Using IBM Softcopy Collections on an AS/400 System	67

Chapter 7. Setting Autorun Preferences for Collection Discs

Starting in March 2002, many IBM softcopy collections include a program to set autorun preferences for the programs to run when a collection disc is inserted. For example, you can choose to automatically start Softcopy Reader, the softcopy index to the entire collection, or the softcopy index for a single disc when you insert a disc containing softcopy files. Or, you can choose not to have anything start automatically.

The program (AUTORUN.EXE) runs automatically the first time you insert a disc that contains it. A window opens where you can select the autorun preferences for each type of collection disc. These are the preferences you can set.

Note: Extended shelf files can be opened only by Softcopy Reader 3.0.0 (or later).

- **For discs containing only BookManager files:**

- Open the IBM Softcopy Reader.
- Open the disc index.
- Open the collection index.
- Show the autorun preferences window.
- Do not start any programs.

- **For discs containing BookManager and PDF files:**

- Open the IBM Softcopy Reader.
- Open the disc index.
- Open the collection index.
- Show the autorun preferences window.
- Do not start any programs.

- **For discs containing only PDF files:**

- Open the disc index.
- Open the collection index.
- Show the autorun preferences window.
- Do not start any programs.

- **For discs containing PDF and extended shelf files:**

- Open the IBM Softcopy Reader. (This option is available only if Softcopy Reader 3.0.0 or later is installed.)
- Open the disc index.
- Open the collection index.
- Show the autorun preferences window.
- Do not start any programs.

- **For discs containing BookManager, extended shelf, and PDF files:**

- Open the IBM Softcopy Reader.
- Open the disc index.
- Open the collection index.
- Show the autorun preferences window.
- Do not start any programs.

To set your autorun preferences:

1. For each type of collection disc, select an autorun preference from the selection list.

2. To preview a preference before setting it, select a tool to use now for the current disc.
3. When you are done, click the OK button.

After you save these preferences, the program does not run again unless you have set a preference to run it every time a disc containing the program is inserted.

To change your preferences after initially setting them, do one of the following:

- If you are already viewing the collection index (on a disc other than the tools disc), click on the link to AUTORUN.EXE in the tips section.
- Otherwise, go to the root directory of a collection disc (other than the tools disc) and run AUTORUN.EXE.

Chapter 8. Using the Softcopy Collection Index with a Softcopy Repository

After transferring online books from a softcopy collection to your own repository, you might want to provide the same access to these files as you have when the softcopy collection index (SCINDEX.HTM) is loaded within the SCFRAME.HTM frameset on a collection disc. The files can be:

- On your desktop
- On a local network (such as a network drive or a LAN server)
- Served by an HTTP server

Here are some tips for using the softcopy collection index with a softcopy repository.

- **Recommended browser:** To make full use of the support provided in SCFRAME.HTM, use Internet Explorer 5.0 or later.
- **For viewing BookManager files:** Install IBM Softcopy Reader 2.3.8 or later. This level of the product provides MIME-type information to simplify access to BookManager files through a browser interface.
- **For viewing PDF files:** Install Adobe Reader. To access groups of PDF files from extended shelves, install IBM Softcopy Reader 3.0.0 (or later).
- **For files on a network drive:** Map the network drive to a local drive letter. This ensures that the browser has access to the files.

To provide access to the BookManager files on that drive, open Shelf Organizer and add the local drive letter and path to the list of user-defined directories.

- **For files served by an HTTP server (Netscape users only):** To launch BookManager books and shelves with Softcopy Reader from the Netscape browser, the HTTP server administrator must modify the HTTP server configuration.

These are the specific MIME content type/subtype assignments needed for the filetype extensions supported by Softcopy Reader.

Extension	MIME content type/subtype (Softcopy Reader 3.0.0 or later)	MIME content type/subtype (earlier levels of Softcopy Reader)
.boo	application/x-boo	application/boo
.bks	application/x-bks	application/boo
.xks	application/x-xks	not supported

These assignments correspond to the content type values specified by the Softcopy Reader installation program in the .boo, .bks, and .xks helper application information at the client.

The method to make these assignments depends on the HTTP server. Here are some examples:

- For the Apache HTTP server, create AddType directives in the httpd.conf file.
- For the Microsoft IIS HTTP server, create MimeMap registry key entries.

- For the Lotus Go HTTP server, use the Configuration and Administration function to add new entries to the Mime Types form.
- Copy the contents of the root directory and \AUTOHTML directory from a numbered disc in the desired collection, using the same directory structure as on the collection.

For example, you could create a directory called \IBMBOOKS and nest the copied directories under it. Copy the files from the root directory of the collection into this top-level directory, and copy the contents of the \AUTOHTML directory of the collection disc into the \AUTOHTML directory under your top-level directory.

You should end up with a directory structure similar to this:

```
IBMBOOKS
|
-- > BOOKS
|
-- > SHELVES
|
-- > PDF
|
-- > AUTOHTML
```

- **For files not served by an HTTP server:** Delete the DISC.JS and CHKDISC.JS files from the \AUTOHTML directory on your system, and delete DISC.HTM from the top-level directory (such as IBMBOOKS). Deleting these files enables the SCINDEX.HTM file to work as if the softcopy files it links to are all on one disc.
- The links in SCINDEX.HTM assume that the book and shelf files are in the \BOOKS and \SHELVES directories, and the PDF files are in the \PDF directory. If you moved the files into other directories, you must edit the links in SCINDEX.HTM to point to those directories.
- The links assume that you are using SCINDEX.HTM and the files it links to (books, shelves, PDFs) from the same drive. There might be situations when you cannot do this. For instance, if you are linking to books that are accessible on a network server, you must change the links to match the drive letter on which the linked-to files are mounted.
- To create a desktop shortcut for launching SCFRAME.HTM from within your top-level directory (such as \IBMBOOKS):
 1. Right-click SCFRAME.HTM.
 2. Drag it to your desktop.
 3. Select the option to Create Shortcut Here.
- Each time the collection is updated, refresh your repository from the contents of the root directory and \AUTOHTML directory of the collection discs. The interface is constantly being improved, and this is the only way to be assured of getting the latest code.

Chapter 9. Learning to Use IBM Softcopy Reader and Other IBM Readers

After you insert a disc for an IBM softcopy collection, you can use the Shelf Organizer of the IBM Softcopy Reader to see a list of the shelves you have available.

- From a bookshelf, you can access, read, and search BookManager BOOK files.
- With Softcopy Reader 3.0.0 (or later), the Shelf Organizer supports extended shelves (XKS files). From an extended shelf, you can access PDF files. However, reading the PDF files still requires a separate program, such as an Adobe Reader. Also, you cannot use Softcopy Reader to search individual PDFs or extended shelves of PDFs.

For detailed instructions on using Softcopy Reader, the BookManager READ/VM licensed program, or the IBM BookManager READ component of z/OS or OS/390, you can refer to one of the following:

- The README and BOO files in the directory where the Softcopy Reader was installed, or *IBM Softcopy Reader User's Guide*, SC34-3164 (in the IBM Online Library Reference Bookshelf on most softcopy collections)
- *IBM BookManager READ/VM: Displaying Online Books*, SC23-0449 (in the *IBM Online Library Omnibus Edition: VM Collection*, SK2T-2067)
- *IBM BookManager READ/MVS: Displaying Online Books*, SC38-2034 (in the *z/OS Collection*, SK3T-4269, and in the *IBM Online Library Omnibus Edition: OS/390 Collection*, SK2T-6700)
- *IBM OS/390 BookManager Hints and Tips*, GC28-1987

Chapter 10. Printing Hardcopy from Softcopy Files

You can print your own hardcopy when you need it from the softcopy files provided on IBM softcopy collections, on a library on the Internet, or on a local repository or Web site.

- If you are viewing a softcopy file and you want hardcopy of a topic or two, you can print from the BOOK or PDF file you are viewing.
- For a complete hardcopy book that looks like a traditional manual you would order from IBM, print the PDF file for the book.

Printing from a BOOK File

How to print topics from a BookManager BOOK file depends on how you are viewing that file:

- From your workstation, with IBM Softcopy Reader (for example, to read a BookManager BOOK file from a CD-ROM)
- From a library on the Internet (such as the z/OS Internet library or the OS/390 Internet library), which uses IBM BookManager BookServer to display BookManager BOOK files
- From a host, with BookManager READ

Because the printout is from the BookManager BOOK file itself, the output looks like the BookManager BOOK file, with numbered sections and subsections instead of page numbers. But remember—you should only use the BookManager BOOK file to print a topic or two, and not the whole book.

With BookServer, if a companion PDF file is present for a BookManager BOOK file, Adobe® Reader™ can be launched for that PDF, from which desired pages in the PDF document may be printed.

Using IBM Softcopy Reader

To print the topic you are currently viewing:

1. Click on the **Print** icon or go to **File** → **Print**. This opens a Print window.
2. Click on the **Current** button. This opens your workstation Print window.
3. Complete the print options in your workstation Print window, then click **OK** to print the current topic.

To print selected topics:

1. Select the desired topics in the “table of contents” frame. Hold down the **Shift** key to select a list of topics, or hold down the **Ctrl** key to select specific topics.

To print all the topics in a chapter, expand the chapter by clicking the + sign next to the chapter heading in the table of contents. Then highlight all the topics in the chapter that you want to print. If you highlight only the main chapter topic without expanding it, you will print only the page that displays for the main chapter topic, including a list of subtopics for the chapter.

2. Click on the **Print** icon or go to **File** → **Print**. This opens a Print window.

3. Click on the **Selected** button. This opens your workstation Print window.
4. Complete the print options in your workstation Print window, then click **OK** to print the selected topics.

Using the z/OS or OS/390 Internet Library

Printing from the z/OS or OS/390 Internet library gives you a very high-quality output.

- To use the z/OS Internet library, go to <http://www.ibm.com/servers/eserver/zseries/zos/bkserv/>
- To use the OS/390 Internet library, go to <http://www.ibm.com/s390/os390/bkserv/>

To print the topic you are currently viewing:

1. Click your browser **Print** icon.
2. Follow the usual steps for printing from your browser.

To print selected topics:

1. Click the BookManager BookServer **Print** icon (not your browser **Print** icon). This opens a Print Preview window.
2. Highlight the desired topics from the selection box. Hold down the **Shift** key to select a list of topics or hold down the **Ctrl** key to select specific topics.
3. Click the **Selected topics** button. You then see a formatted preview of the topics.
4. Use your browser's print facility to produce a hardcopy document of the information shown.

To print pages from a BookManager BOOK file you are currently viewing:

1. Click the BookManager BookServer Download PDF icon, if selectable.
2. When presented with the File Download dialog, select "Open this file from its current location" and then click "OK," which will launch the Adobe Reader for the PDF.
3. From within the Adobe Reader, the desired pages in the PDF document may be printed via the Adobe Reader print function.

To print pages from a PDF document you select from a bookshelf, bookshelf search results list, or a catalog list:

1. Click the PDF icon, if present.
2. When presented with the File Download dialog, select "Open this file from its current location" and then click "OK," which will launch the Adobe Reader for the PDF.
3. From within the Adobe Reader, the desired pages in the PDF document may be printed via the Adobe Reader print function.

Using BookManager READ

If your company has established a softcopy repository on the host (z/OS, OS/390, z/VM, or VM), you can use the Print option of BookManager READ to get hardcopy of a topic or two. However, BookManager READ by itself (without other programs such as DCF and BookMaster, which are separate programs) provides a lower quality print than printing from BookManager BookServer—it is essentially a screen print. Sometimes, though, BookManager READ may be the only available option. In that case, here's how to proceed.

1. Open the book you are interested in.
2. To set your print options, select the Options pull-down menu, then select the print option and specify the desired values.
3. Use the PRINT command to print one or more topics in the book.
(BookManager READ/MVS invokes the ISPF panels you normally use to print at your site. BookManager READ/VM invokes the program specified in the print options.)

Enter the command in one of the following ways:

PRINT

PRINT topic1

PRINT topic1 **TO** topic2

PRINT topic1 **FOR** number-of-topics

- To print the current topic, enter the **PRINT** command without operands.
- To print all of a topic (such as 1.0), including its subtopics, enter the next topic number (such as 2.0), then prev. Make note of the last topic number (for example, 1.6.4), then enter the **PRINT** command with the complete range (**PRINT 1.0 TO 1.6.4**).

Printing a PDF File

In the workstation environment, you use an Adobe® Reader™ to view and print PDF files. But sometimes you need alternatives. For large or graphically complex books that need to be printed on AFP™ printer, you might want to have the host handle the transforms, instead doing it on the workstation before sending the file. Also, you may want to be able to print PDFs stored in a host repository. z/OS or OS/390 and the optional Infoprint Server feature support these additional options for printing PDF files.

Using an Adobe Reader

1. Install an Adobe Reader on your computer. Starting in September 2000, many IBM softcopy collections contain a recent level of an Adobe Reader (at no extra charge). You can also go to the Adobe Web site at <http://www.adobe.com> for other readers or more information.
2. Open the PDF you want to print. The PDF can be on a CD-ROM, on the z/OS Internet library—anywhere you can view it with an Adobe Reader.
3. Select the Reader's Print option.
4. Select the desired printer and specify other print options as appropriate.
5. Click OK to print the file.

Reminder: Be aware that if you decide to print a subset of a book from a PDF file, the “pages” (as understood by Adobe Reader) are totally sequential. The Reader views the front cover as page 1 and takes off from there—no Roman numeral page numbers for the front matter, no section numbering. So, when you specify the pages to print, be sure to enter the page numbers from the Reader's point of view (check the page box at the bottom of the screen) and not as they appear on the individual pages of the book.

Using a LAN- or Host-attached AFP Printer

Some PDF files are too large or graphically complex to print on the typical desktop or LAN-attached printer. z/OS and OS/390 provide a solution. Infoprint Server (an optional, priced feature of z/OS and OS/390), with the Infoprint Server Transforms (free to Infoprint Server customers), lets you print high-quality hardcopy of PDF files on high-speed LAN-attached or host-attached AFP printers managed by PSF for OS/390.

- Workstation users on a LAN connected to z/OS or OS/390 can print PDFs from a CD-ROM, the Web, or the LAN.
- Host users can print PDFs from an MVS or HFS data set, such as a host repository of softcopy files, or PDFs uploaded from a CD-ROM.

At a high-level, these are the requirements:

- InfoPrint Server and the InfoPrint Server Transforms must be installed on z/OS or OS/390.
- The system administrator must define one or more AFP printers to Infoprint Server and configure the printer definitions to use the PDF to AFP transform. (PostScript to AFP and PCL to AFP transforms are also available at no extra cost.)
- For host users, the system administrator can customize the AOPPRINT JCL procedure to create a job for printing PDF documents on AFP printers. Host users can also use the OS/390 UNIX lp command to print PDF documents on AFP printers, and the OS/390 UNIX pdf2afp command to create AFP documents.
- Workstation users can download an Infoprint Server Windows client (the OS/390 Printer Port Monitor) to route workstation print requests to Infoprint Server on z/OS or OS/390 and to AFP printers. Workstation users can also submit print requests using the Internet Printing Protocol available on Windows 2000, the SMB protocol available on all Windows systems, and the TCP/IP LPR command available on most workstation platforms.

For an overview of this support, visit <http://www.ibm.com/printers>. For details on this support, see the z/OS Infoprint Server documentation in any of these locations:

- *z/OS Collection*, SK3T-4269
- z/OS Internet library, at <http://www.ibm.com/servers/eserver/zseries/zos/bkserv/>
- *OS/390 Collection*, SK2T-6700
- OS/390 Internet library, at <http://www.ibm.com/s390/os390/bkserv/>

Chapter 11. Using IBM Softcopy Collections on Your z/OS, OS/390, z/VM, or VM Host

After using the IBM SoftCopy Librarian to transfer bookshelves, indexes, and books to your z/OS, OS/390, z/VM, or VM host, you need to make the bookshelves available and usable on your host system. This chapter explains how to do this.

Making Bookshelves Available on z/OS or OS/390

- 1** Start the z/OS or OS/390 BookManager Reader (whichever is appropriate) and go to the list of bookshelves.
- 2** Do **not** select any bookshelves. Select **Books** choice on the action bar and press Enter.
- 3** In the window that appears, select **6. Perform file functions**.
- 4** In the window that appears, select **5. Add**.
- 5** Type, between single quotation marks, the name of the first bookshelf you uploaded and press **Enter**.

```
'ibmbk.ez2shelf-name.bkshe1f'
```

You may want to add to the master list, which is defined by the QLSHELF parameter in the EOXVOPTS REXX EXEC. For example, if you look at the EOXVOPTS member, you see a statement like this:
QLSHELF = "'EOY.BKLSHELF'"

The name of the master list here is:
'EOY.BKLSHELF' The bookshelf is now added.
- 6** Repeat steps 4, 5, and 6 for each bookshelf in BKSHELF.LST. When you have finished, press **F12** to return to the list of bookshelves.
- 7** Type a slash (/) next to each bookshelf you just added.
- 8** Select the **Books** choice on the action bar and press **Enter**.
- 9** In the window that appears, select **6. Perform file functions**.
- 10** In the window that appears, select **4. Edit**.
- 11** In the window that appears, select **4. Add data set names**.
- 12** In the window that appears, type the high-level qualifier that you added to each file name, and press **Enter**. For example, `ibmbk`
- 13** Press **F12** to return to the previous window.
- 14** Press **F6** to skip the bookshelf you just added. The next bookshelf you selected appears.

- 15** Repeat steps 10, 11, 12, and 13 for each bookshelf you selected.
- 16** When you have finished with all the bookshelves, a window with the list of bookshelves reappears.
- 17** Press **F5** to refresh the list and see the newly added bookshelves.

You are now ready to use the new bookshelves. You can use the **BOOKMGR** command in your host session to view the bookshelves and books in a collection of IBM books. Refer to the BookManager READ/MVS books for more information about using BookManager READ on your host.

Note: To conserve space on your host DASD, you can release any unused space you allocated when you uploaded the books and bookshelf search indexes. You can use DFHSM to migrate the data set.

Making Bookshelves Available on z/VM or VM

Although it is not required, you should add the bookshelf files to the BookManager public library. Otherwise, you can access them directly if the minidisk containing the files is currently accessible.

When you are finished transferring files to your z/VM or VM host, you can use the **BOOKMGR** command in your host session to view the bookshelves and books.

Chapter 12. Sharing IBM Softcopy Collections with Your VSE Host

You can share IBM softcopy collections with the users of your VSE host in two ways:

- **For VSE running under VM:** You can install the BookManager READ/VM licensed program on your VM host and upload the files you want to use.
- **For stand-alone VSE:** You can install IBM Softcopy Reader on your workstations and use the collections at these workstations.

Distributing IBM Softcopy Collections to VSE Workstations

You can distribute IBM softcopy collections to VSE workstations that do not have CD-ROM or DVD readers by using diskettes and using the PUN Queue.

Distributing IBM Softcopy Collections Using Diskettes

You can copy the IBM Softcopy Reader and softcopy files to diskettes on one workstation and copy them to the hard disk on another workstation.

Uploading Books, Bookshelves, and Indexes to the PUN Queue

You can transfer files to the VSE/POWER PUN queue from one workstation and then retrieve them from the queue at another workstation.

- 1** At your VSE host, make sure the VSE/POWER data file has enough free space. Enter the command **D Q** at the system console.

The system displays the percentage of space already used in the data queue. To determine how much free space is available in the data file, multiply the displayed values for free DBLK groups, DBLK group size, and DBLK size (free DBLK groups × DBLK group size × DBLK size).

To send files, set up the VSE host for normal file transfer to or from a workstation (see *VSE/ESA Programming and Workstation Guide*).

- 2** At the workstation OS/2 or DOS command prompt, switch to the drive with the directory containing the files you want to transfer. If the books are on your F drive, type: `f:`
- 3** Change to the directory on that drive containing the files. If the books are on the \BOOKS directory, type: `cd \books`
- 4** Do one of the following to transfer files to the PUN queue:
 - Use individual DOS or OS/2 SEND commands to transfer files to the PUN queue. For example:

```
send dto32e00.bo0 dto32e00 (file=pun binary class=v dest=any  
lrecl=4000
```
 - Create an OS/2 command like the following to transfer three books to the PUN queue at the same time:

```
SEND GETBOOK.CMD GETBOOK (FILE=PUN BINARY CLASS=V DEST=ANY  
LRECL=4000
```

```
SEND DT032E00.B00 DT032E00 (FILE=PUN BINARY CLASS=V DEST=ANY
LRECL=4000
SEND DT0U2000.B00 DT0U2000 (FILE=PUN BINARY CLASS=V DEST=ANY
LRECL=4000
SEND DT0R2000.B00 DT0R2000 (FILE=PUN BINARY CLASS=V DEST=ANY
LRECL=4000
```

Explanation:

- The command file sends three books to PUN.
- For DOS, this file would be named GETBOOK.BAT instead of GETBOOK.COMD.
- CLASS=V designates the files belong to this specific queue class. You should make sure PUN is not started for the class you select.
- DEST=ANY so any user can retrieve the books from the queue.
- GETBOOK.COMD is a file for retrieving the books.

Receiving Books, Bookshelves, and Indexes from the PUN Queue

After you have transferred files to the VSE/POWER PUN queue from a workstation, you can retrieve them from the queue at another workstation.

Before receiving any files, you should decide into which directory or partition on the receiving workstation you want to put them. The following example assumes you want to put the books into the \BOOKS directory on your C hard disk. After you decide where you want to put the books, make sure the destination you chose is in the PATH statement on the workstation.

- 1** Set up the VSE host for normal file transfer to a workstation.
- 2** At the workstation receiving the files from the PUN queue, use individual DOS or OS/2 RECEIVE commands to transfer files from PUN.

If you sent a command file like the one described below to the PUN queue, you can receive it, and use it to receive the other files. For example, to receive the GETBOOK file from PUN queue:

For OS/2: receive d:\books\getbook.cmd getbook (file=pun binary class=v

For DOS: receive d:\books\getbook.bat getbook (file=pun binary class=v

After you have retrieved the command file, use it to retrieve one or more queue entries from PUN. For example, if the GETBOOK file contains RECEIVE commands for three books, entering getbook receives the following files:

```
RECEIVE D:\BOOKS\DT032E00.B00 DT032E00 (FILE=PUN BINARY CLASS=V
RECEIVE D:\BOOKS\DT0U2000.B00 DT0U2000 (FILE=PUN BINARY CLASS=V
RECEIVE D:\BOOKS\DT00R000.B00 DT00R000 (FILE=PUN BINARY CLASS=V
```

The queue entries remain in PUN until you use PDELETE to delete them.

Chapter 13. Using IBM Softcopy Collections on an AS/400 System

You can share IBM softcopy collections on your AS/400 System using InfoSeeker on the AS/400 System to read books or using IBM Softcopy Reader on an AS/400-attached workstation.

AS/400 InfoSeeker became part of the Operating System/400 in Version 3 Release 1. It is a version of the BookManager Library Reader specially designed for use on the AS/400 System. With InfoSeeker, you can view online books from any workstation, including non-programmable workstations.

The PC-based Softcopy Reader provides features not available with InfoSeeker, such as allowing you to:

- Display the pictures in the books
- Add margin notes to the books
- Print topics with better quality
- Print pictures

On AS/400 Advanced Series systems using PowerPC technology and OS/400 Version 3 Release 6, you can install online books on the system by using the AS/400 CD-ROM drive. See “Installing Books on OS/400 Version 3 Release 6 or Later” on page 69 for the procedure to do this.

On Version 3 Release 1 systems, you can transfer online books from your CD-ROM to an AS/400 directory. You must do this if you want to view the books using InfoSeeker from a non-programmable workstation attached to an AS/400 System.

You can also use IBM softcopy collections from a CD-ROM or DVD drive on a workstation.

Notes:

1. OS/400 support of InfoSeeker exists through, but not beyond, Version 4 Release 3 of the base operating system.
2. Softcopy information for AS/400 systems is now provided through Information Center CD-ROMs (such as *AS/400 Information Center CD-ROM (V4)*, SK3T-2027) instead of through softcopy collections.

Installing and Using InfoSeeker on Your AS/400 System

For information on setting up an IBM softcopy collection and using InfoSeeker, see:

- *AS/400 InfoSeeker: Getting Started*, SC41-3001 (V3R2)
- *AS/400 InfoSeeker: Use*, SC41-3002 (V3R2)

Once the books are installed, you start InfoSeeker by entering

`strinfskr`

on the AS/400 command line.

Using Directories on the AS/400 System to Share Softcopy Collections

Client Access for OS/400 allows you to share the IBM books and bookshelves among several users who have programmable workstations. Each workstation can have the IBM Softcopy Reader installed or you can install the IBM Softcopy Reader in a shared AS/400 directory.

For more information on setting up and using these directories, see *AS/400 Client Access for Windows 95/NT Setup*, SC41-3512.

Using the SCRT to Install Books to an AS/400 System Directory

You can use the Softcopy Receiver Tool (SCRT) to transfer IBM softcopy collections from a CD-ROM or DVD on your personal computer to a directory on an AS/400 System.

Final Shipment of SCRT in September 2001

The Softcopy Receiver Tool is no longer supported as of September 2001.

The SCRT is being shipped for the last time on the September and October 2001 softcopy collections. You should start using IBM SoftCopy Librarian instead.

Starting in December 2001, softcopy collections will not include the SCRT. Instead, only the IBM SoftCopy Librarian will be included.

Note the following considerations for AS/400 when running SCRT V1.3:

- The SCRT cannot install to a root drive on an AS/400 System.
- A drive must be assigned to the AS/400 System directory.

When using Client Access for AS/400, PC drive letters can be assigned to AS/400 directories (or folders). Normally, libraries on IBM softcopy collections are installed to the QBKBOOKS/BOOKS folder on the AS/400. Therefore, the PC drive letter should be assigned to QBKBOOKS. For example, if drive j is assigned to QBKBOOKS on AS/400, the destination path for installing the collection using SCRT would be j:\books.

Copying IBM Books to an AS/400 System Directory

The following examples assume D is the drive letter for the CD-ROM drive, \B00KS is the directory containing the books on the CD-ROM, I is the drive letter assigned to the AS/400 System, and \QBKB00KS\B00KS is the directory to contain the Client Access for OS/400 books on the AS/400 System.

Note: The QBKB00KS/B00KS directory is created when OS/400 is installed. It is the default directory for online books.

The examples also assume you are copying the Client Access for OS/400 bookshelf and books. The file names for most Client Access for OS/400 books and its bookshelf begin with the letters QBKAK (V3R1) or QBJAK (V3R6). If you want to use different books or directories, substitute their names for the names used in the examples.

To copy IBM books and bookshelves from a CD-ROM to a Client Access for OS/400 folder, follow these instructions:

1 Switch to the drive letter assigned to the AS/400 System. Type:

```
i:
```

2 Copy the books you want in the folder from the CD-ROM with the COPY or XCOPY command. Type:

```
copy d:\books\qbkak*.boo i:\qbkbooks\books
copy d:\shelves\qbkak*.bks i:\qbkbooks\books
copy d:\books\qbkak*.bki i:\qbkbooks\books
```

You can also use the SCRT to install the books to the AS/400 System. Simply specify the path to the AS/400 directory as the target for the SCRT.

Users can now access the books and bookshelves by assigning the directory drive to their workstations and identifying that drive to the Softcopy Reader installation program if they are installing the IBM Softcopy Reader on their workstations.

Users of InfoSeeker can also access the books once they are installed in the directory. If the books are placed in a directory other than qbkbooks/books, you must define the directory to InfoSeeker. Use the Work with System Value (WRKSYSVAL) OS/400 control language command to specify the folder path in the QBOOKPATH system value. The paths specified for QBOOKPATH (up to five paths can be defined) must be of the form:

```
/QDLS/directory
```

to correctly access the collection in the directory. For example, the default value is:

```
/QDLS/QBKBOOKS/BOOKS
```

Installing Books on OS/400 Version 3 Release 6 or Later

To install books to an AS/400 System from the AS/400 CD-ROM drive, place the CD-ROM in the drive. Enter:

```
rstshf *shelf shelf(*list) dev(optical-device) vol(volume-name)
```

on the AS/400 command line. *optical-device* is the name assigned to your CD-ROM drive on the AS/400 System (normally opt01); *volume-name* is the internal identifier of the CD-ROM platter. To determine the volume name, use the Work with Optical Volume (WRKOPTVOL) OS/400 control language command.

A list of bookshelves is presented so you can select the ones you want to install. You can also choose whether you want the books installed to the AS/400 System (the bookshelves and bookshelf index files will be installed).

To access books directly from the CD-ROM, you must identify the CD-ROM volume to InfoSeeker. Use the Work with System Value (WRKSYSVAL) OS/400 control language command to specify the folder path in the QBOOKPATH system value.

To access books and bookshelves from the CD-ROM, you do not need to install anything to the AS/400 System. Simply use the WRKSYSVAL command to identify the BOOKS and SHELVES directories on the CD-ROM to InfoSeeker. The paths specified for QBOOKPATH (up to five paths can be defined) must be of the form:

/QOPT/volume-name/directory

to correctly access the CD-ROM. The QBOOKPATH system value can contain paths to directories (QDLS) and the CD-ROM (QOPT).

For complete descriptions of these procedures, look in any of these softcopy collections:

- *AS/400 Softcopy Library and Information Directory CD-ROMs (V3R6), SK2T-2839*
- *AS/400 Softcopy Library and Information Directory CD-ROMs (V3R7), SK2T-8290*
- *AS/400 Information Center CD-ROM (V4), SK3T-2027*

Part 5. Appendixes

Appendix A. Installing IBM Softcopy Collections on a LAN Server	73
Appendix B. Setting Up a Walk-Up-and-Use Library Kiosk	75
Appendix C. Notices	77

Appendix A. Installing IBM Softcopy Collections on a LAN Server

You can put IBM Softcopy Reader and IBM softcopy collections on a LAN. You may want to put the collections of IBM books on a LAN because:

- You want to centralize control and support of the softcopy collections.
- You do not have CD-ROM or DVD drives for all your workstations.
- You do not have space on each workstation for Softcopy Reader and the books.

There are different ways to use the LAN server. You can:

- Put the CD-ROMs or DVDs containing the IBM softcopy collections on one or more of the LAN server's CD-ROM or DVD drives, and put Softcopy Reader on a LAN server hard disk.
- Put the CD-ROMs or DVDs on one or more of the LAN server's hard disks, and put Softcopy Reader on a LAN server hard disk.
- Put the CD-ROMs or DVDs on one or more of the LAN server's CD-ROM or DVD drives, and put Softcopy Reader on the hard disk in each workstation. Putting Softcopy Reader on each workstation's hard disk may also improve performance.

Planning for LAN Setup

To make IBM softcopy collections available to users on a LAN, you need to put the books, shelves, and indexes, and IBM Softcopy Reader out on the drives of the server and give users access to these drives. You can install the readers on each individual workstation, or on a drive on the server. You can also define the readers as public applications, so whenever a workstation is booted, icons for the readers appear.

Your LAN setup must have the following:

- User access to the books, shelves, and indexes.
- User access to the Softcopy Reader code.
- BookManager pointing to the directory containing the books.

Users should see this setup automatically when they logon to the LAN.

You may want to consider attaching at least one CD-ROM or DVD drive for each disc containing IBM books you want to use and additional drives for any other discs you plan to use. Additional CD-ROM or DVD drives minimize the swapping of discs at the server.

To improve user access to softcopy on a LAN server, you might want to copy some of the tools or interfaces provided on softcopy collections.

- For information about the interface and executables for installing softcopy tools, see "Installing Tools from a Network Drive" on page 26.
- For information about the interface to the softcopy collection index, see Chapter 8, "Using the Softcopy Collection Index with a Softcopy Repository" on page 55.

Appendix B. Setting Up a Walk-Up-and-Use Library Kiosk

You can set up a walk-up-and-use kiosk for your IBM softcopy collections. One kiosk can serve your department or one or more can serve your entire organization. You just need to place a terminal or workstation with access to the softcopy collections in a location that is convenient for the members of your organization to get to when they need information. If you are the administrator for your company's hardcopy library, you may already have a kiosk that you use for other kinds of library access. You may be able to add the IBM softcopy collections to the terminal or workstation that you are already using as a kiosk. To set up a kiosk, you can do the following:

- 1** Decide how the kiosk should be set up. You can do one of the following:
 - a. Set up a Windows or AIX/6000 workstation and the IBM softcopy collections yourself in your department or library.
 - b. Work with your LAN administrator to set up a Windows or AIX/6000 LAN-connected workstation that has access to a LAN server containing the IBM softcopy collections.
 - c. Work with your z/OS, OS/390, z/VM, or VM system administrator to set up a host-connected terminal or workstation that has access to a z/OS, OS/390, z/VM, or VM host that contains IBM softcopy collections. You may need to help your administrator by uploading the contents of the softcopy collections to your host system.

- 2** Use the collections at your workstation or give them to the LAN administrator or your host system administrator. Do one of the following:
 - a. Use the collections in one or more CD-ROM or DVD drives attached to your kiosk. You might want to put the drives in a secure place to prevent users from switching discs without your knowing it.
 - b. Copy the books and IBM Softcopy Reader from the discs on a CD-ROM or DVD drive attached to your kiosk onto a large hard disk in the kiosk.
 - c. If your kiosk does not have its own CD-ROM or DVD drive but is connected to a host, you can upload the books and the Softcopy Reader from the discs at a workstation that has a CD-ROM or DVD drive to your host and then download them to your kiosk.
 - d. Upload the books from the discs at a workstation that has a CD-ROM or DVD drive to your z/OS, OS/390, z/VM, or VM host.

- 3** Provide instructions to your users so they can get access to the IBM softcopy collections.

To improve user access to softcopy on a kiosk, you might want to copy some of the tools or interfaces provided on softcopy collections.

- For information about the interface and executables for installing softcopy tools, see “Installing Tools from a Network Drive” on page 26.
- For information about the interface to the softcopy collection index, see Chapter 8, “Using the Softcopy Collection Index with a Softcopy Repository” on page 55.

Appendix C. Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10594-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Mail Station P300
2455 South Road
Poughkeepsie, NY 12601-5400
U.S.A

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Terms and Conditions for Items in the Online Library

Before using or copying books and programs on IBM softcopy collections, you must first read and agree to the terms and conditions specified for them. If you do not agree, return the collection to IBM. By using and copying the books or programs, you agree to the terms and conditions and the license agreement.

Using and Copying Online Books

Unlicensed books have order numbers that begin with the letters **G** or **S**. The terms and conditions for using and copying unlicensed books provided in softcopy format (such as BookManager or PDF) are stated in a file called BOOKENG.AGR on collections that contain these files. The file is in text format and can be displayed or printed from your personal computer.

Licensed books have order numbers that begin with the letter **L**. These books are classified "Licensed Materials—Property of IBM." The terms and conditions for using licensed books are stated in the *Licensed Program Specifications* for the product to which they apply and in the IBM Customer Agreement.

Using and Distributing the IBM Softcopy Reader Program

The terms and conditions for using and distributing the IBM Softcopy Reader program are stated in a file called PLALRENG.AGR included on IBM softcopy collections that contain these programs. The file is in text format and can be displayed or printed from your personal computer.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States, other countries, or both:

AFP	MORE
AIX	MVS
AS/400	Operating System/400
AT	OS/2
BookManager	OS/390
BookMaster	OS/400
CICS	PowerPC
Current	RACF
DB2	Redbooks
eServer	SecureWay
GDDM	VSE/ESA
IBM	z/OS
IBMLink	z/OS.e
IMS	z/VM
Infoprint	zSeries
iSeries	400
Library Reader	

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Intel, Intel Inside (logos), MMX and Pentium are trademarks of Intel Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

SET and the SET Logo are trademarks owned by SET Secure Electronic Transaction LLC.

Other company, product, and service names may be trademarks or service marks of others.

Index

A

- Adobe Reader 17, 27
 - printing PDF files 61
 - printing PDF files for companion BOOK files 7, 59
- AFP printer
 - printing PDF files 62
- AS/400 system
 - installing and using InfoSeeker on 67
 - sharing softcopy collections by using directories 68
 - system directory
 - copying IBM books to an 68
 - using the SCRT to install books to an 68
 - using online libraries on 8
- autorun preferences for collection discs, setting 53

B

- basic entitled product feature codes, nonbillable 8
- billable (non-entitled) product feature codes 9
- BOOK files
 - AS/400 system directory
 - copying to 68
 - installing through the SCRT 68
 - MIME content type/subtype assignment 55
 - OS/400 Version 3 Release 6, installing on 69
 - printing 59
 - BookManager READ 61
 - BookServer, from companion PDF 7, 59
 - Internet library 60
 - Softcopy Reader 59
 - receiving from the PUN queue 66
 - uploading to the PUN queue 65
- Book Reader
 - opening 34
 - starting 34
- BookManager information on the World Wide Web 8
- BookManager READ
 - identifying the latest level via the Internet 14
 - printing BOOK files 61
- BOOKMGR command, VM host session 64
- BookServer
 - printing companion PDF for BOOK file 7, 59
 - serving online libraries through a Web browser 7
- bookshelves
 - making available on READ/VM 64
 - making available on z/OS reader or OS/390 reader 63
 - MIME content type/subtype assignment 55
 - receiving from the PUN queue 66
 - uploading to the PUN queue 65

C

- centralizing softcopy collections on a host system 7
- CICS, transferring files to 15
- code page requirements 15
- configuration
 - Softcopy Reader 31
- copying
 - IBM books to an AS/400 system directory 68

D

- description of SCRT 39
- description of SoftCopy Librarian 39
- directories
 - AS/400 system
 - copying IBM books to 68
 - installing books on through the SCRT 68
 - sharing softcopy collections 68
 - file management programs 6
 - optional 6
 - softcopy collections 5, 6
 - Softcopy Reader 6
 - upload programs 6
- diskettes, distributing IBM softcopy collections using 65
- distributing softcopy collections
 - on a kiosk 75
 - to VSE workstations 65
 - using diskettes 65
- downloading IBM Softcopy Reader from the Internet 14

E

- entitled basic product feature codes, nonbillable 8
- entitled product feature codes, nonbillable 9
- extended shelves (XKS files)
 - autorun preference support for vii, 53
 - MIME content type/subtype assignment 55
 - SoftCopy Librarian support for x, 39
 - Softcopy Reader Shelf Organizer support for ix, 13, 17, 29, 57

F

- feature codes
 - billable (non-entitled) 9
 - nonbillable (entitled basic) 8
 - nonbillable (entitled) 9
- file management programs, directories for 6
- files
 - information 5

files (*continued*)
 optional 6
 transferring to CICS 15
functions of the SCRT 42
functions of the SoftCopy Librarian 42

H

hardware
 optional
 Softcopy Reader 30
 required
 Softcopy Reader 29
host repository
 requirements 43
host system
 sharing and centralizing softcopy collections 7

I

IBM Library Reader for Windows not supported 14
IBM Library Reader/2 not supported 14
IBM Library Reader/DOS not supported 14
IBM Publication Center 10
IBM Softcopy Reader
 See Softcopy Reader
identifying the latest level of IBM reader programs via
 the Internet 14
index to softcopy collection, using with a softcopy
 repository 55
indexes
 receiving from the PUN queue 66
 uploading to the PUN queue 65
Infoprint Server Transforms
 printing PDF files 62
information files 5
InfoSeeker
 AS/400 system, installing and using on 67
 considerations for Library Readers 15
installing
 InfoSeeker on your AS/400 system 67
 on AS/400 system directory, using the SCRT 68
 on OS/400 Version 3 Release 6 69
 SoftCopy Librarian 47
 Softcopy Reader 29, 30
 from a CD-ROM 31
 from the Web 32
 softcopy tools
 from a network drive 26
 from a softcopy collection 21
Internet
 downloading Softcopy Reader from 14
 identifying the latest level of IBM reader programs
 via 14
 printing BOOK files from an Internet library 60
 using online libraries on 7

Internet (*continued*)
 using PDFs on 8
intranet
 using online libraries on 7
 using PDFs on 8
introducing the SCRT 39
introducing the SoftCopy Librarian 39

K

kiosk for distributing softcopy collections 75

L

level of IBM reader programs via the Internet, identifying
 the latest 14
Library Reader
 See Softcopy Reader

M

making bookshelves available on READ/VM 64
MIME content type/subtype assignment for
 BookManager files 55

N

network, using softcopy collectins on 7
non-entitled product feature codes, billable 9
nonbillable (entitled basic) product feature codes 8
nonbillable (entitled) product feature codes 9

O

Online Library
 See also softcopy collections
 contents of 3
opening
 Book Reader 34
 Shelf Organizer 35
 softcopy collections
 Softcopy Reader 34
optional
 directories and files 6
 hardware
 Softcopy Reader 30
 software
 Softcopy Reader 30
ordering IBM softcopy collections 10
OS/390, making bookshelves available on 63
OS/400 Version 3 Release 6, installing books on 69

P

paths
 device, specifying
 Softcopy Reader 31

- paths (*continued*)
 - temporary, specifying
 - Windows 95 or later 36
- PDF files 17
 - printing 61
 - Adobe Reader 61
 - AFP printer 62
 - BookServer, for companion BOOK 7, 59
 - Infoprint Server Transforms 62
 - SoftCopy Librarian support for x, 39
 - Softcopy Reader Shelf Organizer support for via extended shelves ix, 13, 17, 29, 57
 - Web browser access 8
- planning for installation of Softcopy Reader 15
- planning for repositories 44
- PNS 9
 - information on the World Wide Web 9
 - subscription through 9
- Portable Document Format (PDF) files on IBM softcopy collections
 - See PDF files
- preferences for collection discs, setting 53
- printable files (PDF) on IBM softcopy collections
 - See PDF files
- printing 59
 - BOOK files 59
 - BookManager READ 61
 - BookServer, from companion PDF 7, 59
 - IBM Softcopy Reader 59
 - Internet library 60
 - PDF files 17, 61
 - Adobe Reader 61
 - AFP printer 62
 - BookServer, for companion BOOK 7, 59
 - Infoprint Server Transforms 62
 - PDF files for companion BOOK files 7
- product feature codes
 - billable (non-entitled) 9
 - nonbillable (entitled basic) 8
 - nonbillable (entitled) 9
- Publication Notification System (PNS)
 - See PNS
- Publication Ordering System (POS)
 - See IBM Publication Center
- PUN queue
 - receiving books, bookshelves, and indexes from 66
 - uploading books, bookshelves, and indexes to 65

R

- READ for Windows not supported 14
- READ/2 not supported 14
- READ/6000 not supported 14
- READ/DOS not supported 14
- READ/VM, making bookshelves available on 64

- receiving books, bookshelves, and indexes, from the PUN queue 66
- relationship between the collections 5
- repositories
 - planning for 44
- requirements
 - code page 15
 - hardware
 - Softcopy Reader 29
 - host repository 43
 - software
 - Softcopy Reader 29

S

- SCINDEX.HTM, using with a softcopy repository 55
- SCRT
 - AS/400 system directory, installing books onto 68
 - functions of 42
 - general description of 39
 - introducing 39
 - workstation requirements 43
- setting autorun preferences for collection discs 53
- sharing online libraries
 - throughout your business 6
- sharing softcopy collections
 - on a host system 7
 - on AS/400 system, using directories 68
- Shelf Organizer
 - opening 35
 - starting 35
- single-copy purchase 9
- SLSS
 - See PNS
- softcopy collection index, using with a softcopy repository 55
- softcopy collections 3
 - AS/400 system
 - sharing through directories 68
 - using on 8
 - directories 5, 6
 - distributing on diskettes 65
 - how they are kept up to date 5
 - how they are made available 8
 - installing or updating from
 - Softcopy Reader 31
 - network, using on 7
 - opening
 - Softcopy Reader 34
 - ordering 10
 - relationship between 5
 - setting up a kiosk 75
 - sharing and centralizing on host system 7
 - sharing and using throughout your business 6
 - using 6
 - using in your business 6

- softcopy collections (*continued*)
 - VSE workstations, distributing to 65
 - Web browser access
 - serving via BookServer 7
 - workstation, using on 6
 - World Wide Web, catalogs on 11
 - World Wide Web, information on 10
- SoftCopy Librarian
 - functions of 42
 - general description of 39
 - host repository requirements 43
 - installation 47
 - introducing 39
 - planning for repositories 44
 - workstation requirements 43
- Softcopy Reader 13
 - Book Reader
 - opening 34
 - starting 34
 - configuration
 - directories 6
 - downloading from the Internet 14
 - identifying the latest level via the Internet 14
 - installation, planning for 15
 - installing from the Web 32
 - printing BOOK files 59
 - removing 36
 - Shelf Organizer
 - accessing PDF files via extended shelves ix, 13, 17, 29, 57
 - opening 35
 - starting 35
 - software and hardware requirements 29
 - uninstalling 36
- softcopy tools
 - installing from a network drive 26
 - installing from a softcopy collection 21
- software
 - optional
 - required
 - Softcopy Reader 29
- software and hardware requirements
 - Softcopy Reader 29
- specifying
 - temporary paths
 - Windows 95 or later 36
- stand-alone VSE 65
- starting
 - Book Reader 34
 - Shelf Organizer 35
- subscription through PNS 9

T

- temporary paths
 - specifying
 - Windows 95 or later 36

- transferring files to CICS 15

U

- uninstalling
 - Softcopy Reader 36
- updating from a CD-ROM
 - Softcopy Reader 31
- upload programs, directories for 6
- uploading
 - to the PUN queue 65
- using
 - directories on the AS/400 system to share softcopy collections 68
 - InfoSeeker on your AS/400 system, installing and 67
 - online libraries
 - on an AS/400 system 8
 - via BookServer 7
 - PDFs
 - via Web server 8
 - SCRT
 - to install books to an AS/400 system directory 68
 - softcopy collections
 - in your business 6
 - on your network 7
 - on your workstation 6
- using SCINDEX.HTM with a softcopy repository 55
- using the softcopy collection index with a softcopy repository 55
- utilities 6

V

- VSE
 - running under VM 65
 - stand-alone 65
 - workstations, distributing IBM softcopy collections to 65

W

- Web server
 - serving PDFs on the Internet or an intranet 8
- Windows
 - opening softcopy collections
 - Softcopy Reader 34
- workstation requirements
 - for SCRT 43
 - SoftCopy Librarian 43
- workstations
 - distributing IBM softcopy collections to VSE 65
 - using softcopy collections 6
- World Wide Web (WWW)
 - BookManager information 8

World Wide Web (WWW) *(continued)*
catalogs for softcopy collections 11
information about softcopy collections 10
ordering softcopy collections
IBM Publication Center 10
PNS application for publications subscriptions 9

X

XKS files

See extended shelves (XKS files)

Z

z/OS, making bookshelves available on 63

Do You Have Questions, Problems, or Suggestions?

Softcopy Reader and SoftCopy Librarian

To report problems with using the Softcopy Reader or SoftCopy Librarian, send an e-mail to bookmgr@us.ibm.com to directly contact BookManager Product Support.

Other Topics

To report problems with installing or using the library, or accessing books, see the sections that follow.

In the U.S.A.

Do the following:

- 1** Call the IBM Support Center, 1+800+IBM-SERV. You will first connect with a voice menu. Press **0** at any time to connect with a customer service representative.
- 2** Tell the customer rep your customer number (access code). If you do not have a customer number, use **BookMgr** as your generic customer number or access key.
- 3** The customer rep will ask you if this is a new or an existing problem. Answer:
 - **New** if this is the first time you have called about this problem.
 - **Existing** if you have a problem management record (PMR) number already assigned to the problem.

Note: Make sure you have your PMR number available.
- 4** The customer rep will ask you what software application operating system you are using. Answer "My product ID is 5648-032-00 and the queue is SCKIT,118."
- 5** Give the customer rep your name, address, phone number, and a description of the problem. The customer rep will generate your PMR and queue it to SCKIT.
- 6** Hang up and wait for a call back.

In Other Countries

Go to the IBM Software Support Handbook at <http://techsupport.services.ibm.com/guides/handbook.html> for detailed instructions on how to contact IBM, and for the contact telephone numbers in worldwide locations.

In All Locations

For problems, questions, or suggestions about any of the books, contact IBM:

- **Mail** the Readers' Comments form from the back of this booklet or one that you printed from an online book, or address comments to:
IBM Corporation
Department 55JA, Mail Station P384
2455 South Road
Poughkeepsie, NY 12601-6400
U.S.A.
- **FAX** comments to:
In the U.S. and Canada: 1+845+432-9405

In other countries.: IAC+1+845+432-9405

- **Send** comments electronically to:

Internet: mhvrcfs@us.ibm.com

World Wide Web: <http://www.ibm.com/servers/eserver/zseries/softcopy/feedback.htm>

IBMLink: IBMUSM10(MHVRCFS)

If you do not use the Readers' Comments form, please mention the order number of this guide (GC31-8311-27) or the book you are using in your comments. If you would like a reply, include your name and address, your company's name, and your phone or FAX number.

IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

Communicating Your Comments to IBM

IBM Online Library
Installing, Managing, and Using
the Online Library
Publication No. GC31-8311-27

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM. Whichever method you choose, make sure you send your name, address, and telephone number if you would like a reply.

Feel free to comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. However, the comments you send should pertain to only the information in this manual and the way in which the information is presented. To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

If you are mailing a reader's comment form (RCF) from a country other than the United States, you can give the RCF to the local IBM branch office or IBM representative for postage-paid mailing.

- If you prefer to send comments by mail, use the RCF at the back of this book.
- If you prefer to send comments by FAX, use this number:
 - FAX: (International Access Code)+1+845+432-9405
- If you prefer to send comments electronically, use the following e-mail address:
 - mhvrdfs@us.ibm.com

Make sure to include the following in your note:

- Title and publication number of this book
- Page number or topic to which your comment applies

Optionally, if you include your telephone number, we will be able to respond to your comments by phone.

Reader's Comments — We'd Like to Hear from You

IBM Online Library Installing, Managing, and Using the Online Library

Publication No. GC31-8311-27

You may use this form to communicate your comments about this publication, its organization, or subject matter, with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you. Your comments will be sent to the author's department for whatever review and action, if any, are deemed appropriate.

Note: Copies of IBM publications are not stocked at the location to which this form is addressed. Please direct any requests for copies of publications, or for assistance in using your IBM system, to your IBM representative or to the IBM branch office serving your locality.

Today's date: _____

What is your occupation?

Newsletter number of latest Technical Newsletter (if any) concerning this publication:

How did you use this publication?

- | | | | |
|--------------------------|-------------------------------|--------------------------|------------------------|
| <input type="checkbox"/> | As an introduction | <input type="checkbox"/> | As a text (student) |
| <input type="checkbox"/> | As a reference manual | <input type="checkbox"/> | As a text (instructor) |
| <input type="checkbox"/> | For another purpose (explain) | | |

Is there anything you especially like or dislike about the organization, presentation, or writing in this manual? Helpful comments include general usefulness of the book; possible additions, deletions, and clarifications; specific errors and omissions.

Page Number: Comment:

Name

Address

Company or Organization

Phone No.




Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation
Department 55JA, Mail Station P384
2455 South Road
Poughkeepsie, NY 12601-5400



Fold and Tape

Please do not staple

Fold and Tape



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

GC31-8311-27

